

globus gsi callback

2.8

Generated by Doxygen 1.7.3

Sat Apr 30 2011 06:48:38

Contents

1	Globus GSI Callback	1
2	Deprecated List	1
3	Module Index	1
3.1	Modules	1
4	Module Documentation	2
4.1	Activation	2
4.1.1	Detailed Description	2
4.1.2	Define Documentation	2
4.2	Callback Functions	2
4.2.1	Detailed Description	3
4.2.2	Typedef Documentation	3
4.2.3	Function Documentation	3
4.3	Callback Data Functions	5
4.3.1	Detailed Description	7
4.3.2	Typedef Documentation	7
4.3.3	Function Documentation	7
4.4	GSI Callback Constants	14
4.4.1	Enumeration Type Documentation	15

1 Globus GSI Callback

The Globus GSI Callback library. This library contains functions that extend OpenSSL path validation.

- [Activation](#)
- [Callback Functions](#)
- [Callback Data Functions](#)

2 Deprecated List

Global [globus_gsi_callback_get_multiple_limited_proxy_ok](#)(globus_gsi_callback_data_t callback_data, int *multiple_limited_proxy_ok)
This function always returns true now. It will be removed in the next release.

Global [globus_gsi_callback_set_multiple_limited_proxy_ok](#)(globus_gsi_callback_data_t callback_data, int multiple_limited_proxy_ok)
This function has been turned into a no-op. It will be removed in the next release.

3 Module Index

3.1 Modules

Here is a list of all modules:

Activation	2
Callback Functions	2

4 Module Documentation

4.1 Activation

Globus GSI Callback uses standard Globus module activation and deactivation.

Defines

- `#define GLOBUS_GSI_CALLBACK_MODULE`

4.1.1 Detailed Description

Globus GSI Callback uses standard Globus module activation and deactivation. Before any Globus GSI Callback functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_CALLBACK_MODULE)
```

This function returns `GLOBUS_SUCCESS` if Globus GSI Callback was successfully initialized, and you are therefore allowed to subsequently call Globus GSI Callback functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSI Callback, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_CALLBACK_MODULE)
```

This function should be called once for each time Globus GSI Callback was activated.

4.1.2 Define Documentation

4.1.2.1 `#define GLOBUS_GSI_CALLBACK_MODULE`

Module descriptor.

4.2 Callback Functions

Functions that plug into various plug points in the OpenSSL path validation mechanism.

Typedefs

- `typedef int(* globus_gsi_extension_callback_t)(globus_gsi_callback_data_t callback_data, X509_EXTENSION *extension)`

Get callback data index from `X509_STORE`

- `globus_result_t globus_gsi_callback_get_X509_STORE_callback_data_index(int *index)`

Get callback data index from SSL structure

- `globus_result_t globus_gsi_callback_get_SSL_callback_data_index (int *index)`

Certificate verify wrapper

- `int globus_gsi_callback_X509_verify_cert (X509_STORE_CTX *context, void *arg)`

Independent path validation callback.

- `int globus_gsi_callback_create_proxy_callback (int preverify_ok, X509_STORE_CTX *x509_context)`

SSL path validation callback.

- `int globus_gsi_callback_handshake_callback (int preverify_ok, X509_STORE_CTX *x509_context)`

OpenSSL X509.check.issued() wrapper

- `int globus_gsi_callback_check_issued (X509_STORE_CTX *context, X509 *cert, X509 *issuer)`

4.2.1 Detailed Description

Functions that plug into various plug points in the OpenSSL path validation mechanism. These functions add CRL checking, X509 Extension handling and proxy validation.

4.2.2 Typedef Documentation

4.2.2.1 `typedef int(* globus_gsi_extension_callback_t)(globus_gsi_callback_data_t callback_data, X509_EXTENSION *extension)`

Typedef for a callback that may be registered for dealing with unhandled X.509 extension.

4.2.3 Function Documentation

4.2.3.1 `globus_result_t globus_gsi_callback_get_X509_STORE_callback_data_index (int *index)`

Retrieve or create the index for our callback data structure in the X509_STORE.

Parameters

<i>index</i>	Will contain the index upon return
--------------	------------------------------------

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.2.3.2 `globus_result_t globus_gsi_callback_get_SSL_callback_data_index (int * index)`

Retrieve or create the index for our callback data structure in the SSL structure.

Parameters

<i>index</i>	Will contain the index upon return
--------------	------------------------------------

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.2.3.3 `int globus_gsi_callback_X509_verify_cert (X509_STORE_CTX * context, void * arg)`

This function wraps the OpenSSL certificate verification callback for the purpose of replacing the standard issuer check with one that deals with proxy certificates.

Should be used with `SSL_CTX_set_cert_verify_callback()`

Parameters

<i>context</i>	The X509_STORE_CTX for which to register the callback.
<i>arg</i>	Arguments to the callback. Currently ignored.

Returns

1 on success 0 on failure

4.2.3.4 `int globus_gsi_callback_create_proxy_callback (int preverify_ok, X509_STORE_CTX * x509_context)`

This function provides a path validation callback for validation outside of a SSL session.

It should be used in `X509_STORE_set_verify_cb_func()`.

Parameters

<i>preverify_ok</i>	Communicates the result of default validation steps performed by OpenSSL
<i>x509_context</i>	The validation state object

Returns

1 on success 0 on failure

4.2.3.5 `int globus_gsi_callback_handshake_callback (int preverify_ok, X509_STORE_CTX * x509_context)`

This function provides a path validation callback for the validation part of establishing a SSL session.

It handles proxy certificates, X509 Extensions and CRL checking. It should be used in `SSL_CTX_set_verify()`.

Parameters

<i>preverify_ok</i>	Communicates the result of default validation steps performed by OpenSSL
<i>x509_context</i>	The validation state object.

Returns

1 on success 0 on failure

4.2.3.6 int globus_gsi_callback_check_issued (X509_STORE_CTX * context, X509 * cert, X509 * issuer)

This function wraps the OpenSSL X509_check_issued() call and catches the error caused by the fact that a proxy certificate issuer may not have to have the correct KeyUsage fields set.

Parameters

<i>context</i>	The validation state object.
<i>cert</i>	The certificate to check
<i>issuer</i>	The issuer certificate to check

Returns

1 on success 0 on failure

4.3 Callback Data Functions

Functions that deal with the data structure that contains state associated with the path validation callback.

Typedefs

- typedef struct globus_l_gsi_callback_data_s * [globus_gsi_callback_data_t](#)

Initializing and destroying a callback data structure

- globus_result_t [globus_gsi_callback_data_init](#) (globus_gsi_callback_data_t *callback_data)
- globus_result_t [globus_gsi_callback_data_destroy](#) (globus_gsi_callback_data_t callback_data)

Copying a callback data structure

- globus_result_t [globus_gsi_callback_data_copy](#) (globus_gsi_callback_data_t source, globus_gsi_callback_data_t *dest)

Getting and setting the certificate chain depth

- globus_result_t [globus_gsi_callback_get_cert_depth](#) (globus_gsi_callback_data_t callback_data, int *cert_depth)
- globus_result_t [globus_gsi_callback_set_cert_depth](#) (globus_gsi_callback_data_t callback_data, int cert_depth)

Getting and setting the "proxy chain" depth

- globus_result_t [globus_gsi_callback_get_proxy_depth](#) (globus_gsi_callback_data_t callback_data, int *proxy_depth)
- globus_result_t [globus_gsi_callback_set_proxy_depth](#) (globus_gsi_callback_data_t callback_data, int proxy_depth)

Getting and setting the certificate type

- globus_result_t [globus_gsi_callback_get_cert_type](#) (globus_gsi_callback_data_t callback_data, globus_gsi_cert_utils_cert_type_t *cert_type)
- globus_result_t [globus_gsi_callback_set_cert_type](#) (globus_gsi_callback_data_t callback_data, globus_gsi_cert_utils_cert_type_t cert_type)

Getting and setting the certificate chain

- globus_result_t [globus_gsi_callback_get_cert_chain](#) (globus_gsi_callback_data_t callback_data, STACK_OF(X509)**cert_chain)
- globus_result_t [globus_gsi_callback_set_cert_chain](#) (globus_gsi_callback_data_t callback_data, STACK_OF(X509)*cert_chain)

Getting and setting the limited proxy handling setting

- globus_result_t [globus_gsi_callback_get_multiple_limited_proxy_ok](#) (globus_gsi_callback_data_t callback_data, int *multiple_limited_proxy_ok)
- globus_result_t [globus_gsi_callback_set_multiple_limited_proxy_ok](#) (globus_gsi_callback_data_t callback_data, int multiple_limited_proxy_ok)

Getting and setting a set of X.509 extension OIDs.

- globus_result_t [globus_gsi_callback_get_extension_oids](#) (globus_gsi_callback_data_t callback_data, void **extension_oids)
- globus_result_t [globus_gsi_callback_set_extension_oids](#) (globus_gsi_callback_data_t callback_data, void *extension_oids)

Getting and setting the trusted certificate directory

- globus_result_t [globus_gsi_callback_get_cert_dir](#) (globus_gsi_callback_data_t callback_data, char **cert_dir)
- globus_result_t [globus_gsi_callback_set_cert_dir](#) (globus_gsi_callback_data_t callback_data, char *cert_dir)

Getting and setting the callback to be called for unknown X.509 extensions

- globus_result_t [globus_gsi_callback_get_extension_cb](#) (globus_gsi_callback_data_t callback_data, [globus_gsi_extension_callback_t](#) *extension_cb)
- globus_result_t [globus_gsi_callback_set_extension_cb](#) (globus_gsi_callback_data_t callback_data, [globus_gsi_extension_callback_t](#) extension_cb)

Getting and setting the error status

- globus_result_t [globus_gsi_callback_get_error](#) (globus_gsi_callback_data_t callback_data, globus_result_t *error)
- globus_result_t [globus_gsi_callback_set_error](#) (globus_gsi_callback_data_t callback_data, globus_result_t error)

Getting and setting the check self-signed policy flag

- globus_result_t [globus_gsi_callback_get_check_policy_for_self_signed_certs](#) (globus_gsi_callback_data_t callback_data, globus_bool_t *check)
- globus_result_t [globus_gsi_callback_set_check_policy_for_self_signed_certs](#) (globus_gsi_callback_data_t callback_data, globus_bool_t check)

4.3.1 Detailed Description

Functions that deal with the data structure that contains state associated with the path validation callback.

4.3.2 Typedef Documentation

4.3.2.1 typedef struct globus_l_gsi_callback_data_s* globus_gsi_callback_data_t

Callback data typedef.

4.3.3 Function Documentation

4.3.3.1 globus_result_t globus_gsi_callback_data_init (globus_gsi_callback_data_t * *callback_data*)

This function initializes a globus_gsi_callback_data_t.

Parameters

<i>callback_data</i>	Reference to the structure to be initialized
----------------------	--

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.2 globus_result_t globus_gsi_callback_data_destroy (globus_gsi_callback_data_t *callback_data*)

This function destroys a globus_gsi_callback_data_t.

Parameters

<i>callback_data</i>	The structure to be destroyed
----------------------	-------------------------------

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.3 `globus_result_t globus_gsi_callback_data_copy (globus_gsi_callback_data_t source, globus_gsi_callback_data_t * dest)`

This function copies a `globus_gsi_callback_data_t`.

Parameters

<i>source</i>	The structure to be copied
<i>dest</i>	The destination of the copy

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.4 `globus_result_t globus_gsi_callback_get_cert_depth (globus_gsi_callback_data_t callback_data, int * cert_depth)`

This function returns the certificate chain depth.

Parameters

<i>callback_data</i>	The <code>globus_gsi_callback_data_t</code> to retrieve the depth from
<i>cert_depth</i>	The returned certificate chain depth

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.5 `globus_result_t globus_gsi_callback_set_cert_depth (globus_gsi_callback_data_t callback_data, int cert_depth)`

This function sets the certificate chain depth.

Parameters

<i>callback_data</i>	The <code>globus_gsi_callback_data_t</code> to retrieve the depth from
<i>cert_depth</i>	The certificate chain depth

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.6 `globus_result_t globus_gsi_callback_get_proxy_depth (globus_gsi_callback_data_t callback_data, int * proxy_depth)`

This function returns the number of proxies in the certificate chain.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to retrieve the depth from
<i>proxy_depth</i>	The returned "proxy chain" depth

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.7 globus_result_t globus_gsi_callback_set_proxy_depth (globus_gsi_callback_data_t *callback_data*, int *proxy_depth*)

This function sets the number of proxies in the certificate chain.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to retrieve the depth from
<i>proxy_depth</i>	The "proxy chain" depth

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.8 globus_result_t globus_gsi_callback_get_cert_type (globus_gsi_callback_data_t *callback_data*, globus_gsi_cert_utils_cert_type_t * *cert_type*)

This function returns the certificate type of the certificate currently being processed.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to retrieve the certificate type from
<i>cert_type</i>	Variable containing the certificate type on return

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.9 globus_result_t globus_gsi_callback_set_cert_type (globus_gsi_callback_data_t *callback_data*, globus_gsi_cert_utils_cert_type_t *cert_type*)

This function sets the certificate type of the certificate currently being processed.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to set the certificate type on
<i>cert_type</i>	The certificate type

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.10 **globus_result_t globus_gsi_callback_get_cert_chain (globus_gsi_callback_data_t *callback_data*, STACK_OF(X509)** *cert_chain*)**

This function returns the certificate chain associated with the callback data.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to retrieve the certificate chain from.
<i>cert_chain</i>	Contains the certificate chain upon successful return

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.11 **globus_result_t globus_gsi_callback_set_cert_chain (globus_gsi_callback_data_t *callback_data*, STACK_OF(X509)* *cert_chain*)**

This function sets the certificate chain associated with the callback data.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to set the certificate chain on
<i>cert_chain</i>	The certificate chain

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.12 **globus_result_t globus_gsi_callback_get_multiple_limited_proxy_ok (globus_gsi_callback_data_t *callback_data*, int * *multiple_limited_proxy_ok*)**

This function gets the value of the limited proxy handling setting.

This setting determines whether path validation will accept limited proxies that have been further delegated, ie certificate chains with a limited proxy followed by further proxies.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to get the limited proxy setting from
<i>multiple_limited_proxy_ok</i>	Contains the value of the setting upon successful return.

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

Deprecated

This function always returns true now. It will be removed in the next release.

4.3.3.13 **globus_result_t globus_gsi_callback_set_multiple_limited_proxy_ok (globus_gsi_callback_data_t *callback_data*, int *multiple_limited_proxy_ok*)**

This function sets the value of the limited proxy handling setting.

This setting determines whether path validation will accept limited proxies that have been further delegated, ie certificate chains with a limited proxy followed by further proxies.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to set the limited proxy setting on
<i>multiple_limited_proxy_ok</i>	The value of the setting

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

Deprecated

This function has been turned into a no-op. It will be removed in the next release.

4.3.3.14 **globus_result_t globus_gsi_callback_get_extension_oids (globus_gsi_callback_data_t *callback_data*, void ** *extension_oids*)**

This function gets a list of X.509 extension OIDs that may be used by the extensions callback to allow or disallow certain extensions.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to get the array of extension OIDs from.
<i>extension_oids</i>	Contains the list of extension OIDs upon successful return.

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.15 **globus_result_t globus_gsi_callback_set_extension_oids (globus_gsi_callback_data_t *callback_data*, void * *extension_oids*)**

This function sets a list of X.509 extension OIDs that may be used by the extensions callback to allow or disallow certain extensions.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to get the array of extension OIDs from.
<i>extension_oids</i>	The list of extension OIDs

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.16 **globus_result_t globus_gsi_callback_get_cert_dir (globus_gsi_callback_data_t *callback_data*, char ** *cert_dir*)**

This function gets the trusted certificate directory from the callback data.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to get the trusted certificates directory from.
<i>cert_dir</i>	Contains the path to the trusted certificate directory upon successful return.

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.17 **globus_result_t globus_gsi_callback_set_cert_dir (globus_gsi_callback_data_t *callback_data*, char * *cert_dir*)**

This function sets the trusted certificate directory on the callback data.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to set the trusted certificates directory on.
<i>cert_dir</i>	The path to the trusted certificate directory

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.18 **globus_result_t globus_gsi_callback_get_extension_cb (globus_gsi_callback_data_t *callback_data*, globus_gsi_extension_callback_t * *extension_cb*)**

This function gets the callback that is called for unknown X.509 extensions.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to get the callback information from
<i>extension_cb</i>	Contains the extension callback upon successful return.

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.19 **globus_result_t globus_gsi_callback_set_extension_cb (globus_gsi_callback_data_t *callback_data*, globus_gsi_extension_callback_t *extension_cb*)**

This function sets the callback that is called for unknown X.509 extensions.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to set the callback information on
<i>extension_cb</i>	The extension callback

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.20 globus_result_t globus_gsi_callback_get_error (globus_gsi_callback_data_t *callback_data*, globus_result_t * *error*)

This function gets the error status stored in the callback data.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to get the error from
<i>error</i>	Contains the error upon successful return.

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.21 globus_result_t globus_gsi_callback_set_error (globus_gsi_callback_data_t *callback_data*, globus_result_t *error*)

This function sets the error status stored in the callback data.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to set the error on
<i>error</i>	The error

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

4.3.3.22 globus_result_t globus_gsi_callback_get_check_policy_for_self_signed_certs (globus_gsi_callback_data_t *callback_data*, globus_bool_t * *check*)

This function gets the value of the "check policy for self-signed certificates flag" in the callback data.

If this is set then the CA signing policy for a self-signed certificate must include a policy line that allows it to sign itself.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to get the error from
<i>check</i>	Contains the value of the flag upon successful return.

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

Since

Globus Toolkit 4.2.1

4.3.3.23 globus_result_t globus_gsi_callback_set_check_policy_for_self_signed_certs (globus_gsi_callback_data_t *callback_data*, globus_bool_t *check*)

This function sets the value of the "check policy for self-signed certificates flag" in the callback data.

If this is set then the CA signing policy for a self-signed certificate must include a policy line that allows it to sign itself.

Parameters

<i>callback_data</i>	The globus_gsi_callback_data_t to set the error on
<i>check</i>	New value of the flag

Returns

GLOBUS_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

Since

Globus Toolkit 4.2.1

4.4 GSI Callback Constants

Enumerations

- enum globus_gsi_callback_error_t {
GLOBUS_GSI_CALLBACK_ERROR_SUCCESS = 0,
GLOBUS_GSI_CALLBACK_ERROR_VERIFY_CRED = 1,
GLOBUS_GSI_CALLBACK_ERROR_CERT_NOT_YET_VALID = 2,
GLOBUS_GSI_CALLBACK_ERROR_CANT_GET_LOCAL_CA_CERT = 3,
GLOBUS_GSI_CALLBACK_ERROR_CERT_HAS_EXPIRED = 4,
GLOBUS_GSI_CALLBACK_ERROR_INVALID_PROXY = 5,
GLOBUS_GSI_CALLBACK_ERROR_LIMITED_PROXY = 6,
GLOBUS_GSI_CALLBACK_ERROR_INVALID_CRL = 7,
GLOBUS_GSI_CALLBACK_ERROR_REVOKED_CERT = 8,
GLOBUS_GSI_CALLBACK_ERROR_MIXING_DIFFERENT_PROXY_TYPES = 9,
GLOBUS_GSI_CALLBACK_ERROR_WITH_SIGNING_POLICY = 10,
GLOBUS_GSI_CALLBACK_ERROR_OLD_GAA = 11,
GLOBUS_GSI_CALLBACK_ERROR_CALLBACK_DATA = 12,
GLOBUS_GSI_CALLBACK_ERROR_ERRNO = 13,
GLOBUS_GSI_CALLBACK_ERROR_CERT_CHAIN = 14,
GLOBUS_GSI_CALLBACK_ERROR_WITH_CALLBACK_DATA_INDEX = 15,

`GLOBUS_GSI_CALLBACK_ERROR_PROXY_PATH_LENGTH_EXCEEDED = 16,`
`GLOBUS_GSI_CALLBACK_ERROR_LAST = 18 }`

4.4.1 Enumeration Type Documentation

4.4.1.1 `enum globus_gsi_callback_error_t`

GSI Callback Error codes.

Enumerator:

GLOBUS_GSI_CALLBACK_ERROR_SUCCESS Success - never used.

GLOBUS_GSI_CALLBACK_ERROR_VERIFY_CRED Error verifying credential.

GLOBUS_GSI_CALLBACK_ERROR_CERT_NOT_YET_VALID The certificate is not yet valid.

GLOBUS_GSI_CALLBACK_ERROR_CANT_GET_LOCAL_CA_CERT Unable to discover a local trusted CA for a given certificate.

GLOBUS_GSI_CALLBACK_ERROR_CERT_HAS_EXPIRED The certificate has expired.

GLOBUS_GSI_CALLBACK_ERROR_INVALID_PROXY The proxy format is invalid.

GLOBUS_GSI_CALLBACK_ERROR_LIMITED_PROXY Limited proxies are not accepted.

GLOBUS_GSI_CALLBACK_ERROR_INVALID_CRL Invalid CRL.

GLOBUS_GSI_CALLBACK_ERROR_REVOKED_CERT The certificate has been revoked.

GLOBUS_GSI_CALLBACK_ERROR_MIXING_DIFFERENT_PROXY_TYPES The cert chain contains both legacy on rfc compliant proxies.

GLOBUS_GSI_CALLBACK_ERROR_WITH_SIGNING_POLICY Could not verify certificate chain against the signing policy for the issuing CA.

GLOBUS_GSI_CALLBACK_ERROR_OLD_GAA OldGAA error.

GLOBUS_GSI_CALLBACK_ERROR_CALLBACK_DATA Error with the callback data structure.

GLOBUS_GSI_CALLBACK_ERROR_ERRNO System error.

GLOBUS_GSI_CALLBACK_ERROR_CERT_CHAIN Error setting or getting the cert chain from callback data.

GLOBUS_GSI_CALLBACK_ERROR_WITH_CALLBACK_DATA_INDEX Error getting callback data index.

GLOBUS_GSI_CALLBACK_ERROR_PROXY_PATH_LENGTH_EXCEEDED Exceeded the path length specified in the proxy cert info extension.

GLOBUS_GSI_CALLBACK_ERROR_LAST Last marker - never used.

Index

Activation, 1

Callback Data Functions, 5

Callback Functions, 2

globus_gsi_callback_constants

 GLOBUS_GSI_CALLBACK_ERROR_CALLBACK_DATA, 15

 GLOBUS_GSI_CALLBACK_ERROR_CANT_GET_LOCAL_CA_CERT, 15

 GLOBUS_GSI_CALLBACK_ERROR_CERT_CHAIN, 15

 GLOBUS_GSI_CALLBACK_ERROR_CERT_HAS_EXPIRED, 15

 GLOBUS_GSI_CALLBACK_ERROR_CERT_NOT_YET_VALID, 15

 GLOBUS_GSI_CALLBACK_ERROR_ERRNO, 15

 GLOBUS_GSI_CALLBACK_ERROR_INVALID_CRL, 15

 GLOBUS_GSI_CALLBACK_ERROR_INVALID_PROXY, 15

 GLOBUS_GSI_CALLBACK_ERROR_LAST, 15

 GLOBUS_GSI_CALLBACK_ERROR_LIMITED_PROXY, 15

 GLOBUS_GSI_CALLBACK_ERROR_MIXING_DIFFERENT_PROXY_TYPES, 15

 GLOBUS_GSI_CALLBACK_ERROR_OLD_GAA, 15

 GLOBUS_GSI_CALLBACK_ERROR_PROXY_PATH_LENGTH_EXCEEDED, 15

 GLOBUS_GSI_CALLBACK_ERROR_REVOKED_CERT, 15

 GLOBUS_GSI_CALLBACK_ERROR_SUCCESS, 15

 GLOBUS_GSI_CALLBACK_ERROR_VERIFY_CRED, 15

 GLOBUS_GSI_CALLBACK_ERROR_WITH_CALLBACK_DATA_INDEX, 15

 GLOBUS_GSI_CALLBACK_ERROR_WITH_SIGNING_POLICY, 15

GLOBUS_GSI_CALLBACK_ERROR_CALLBACK_DATA

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_CANT_GET_LOCAL_CA_CERT

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_CERT_CHAIN

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_CERT_HAS_EXPIRED

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_CERT_NOT_YET_VALID

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_ERRNO

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_INVALID_CRL

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_INVALID_PROXY

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_LAST

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_LIMITED_PROXY

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_MIXING_DIFFERENT_PROXY_TYPES

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_OLD_GAA

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_PROXY_PATH_LENGTH_EXCEEDED

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_REVOKED_CERT

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_SUCCESS

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_VERIFY_CRED

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_WITH_CALLBACK_DATA_INDEX

 globus_gsi_callback_constants, 15

GLOBUS_GSI_CALLBACK_ERROR_WITH_SIGNING_POLICY

 globus_gsi_callback_constants, 15

globus_gsi_callback

 globus_gsi_callback_check_issued, 4

 globus_gsi_callback_create_proxy_callback, 4

 globus_gsi_callback_get_SSL_callback_data_index, 3

 globus_gsi_callback_get_X509_STORE_callback_data_index, 3

 globus_gsi_callback_handshake_callback, 4

 globus_gsi_callback_X509_verify_cert, 3

 globus_gsi_extension_callback_t, 3

globus_gsi_callback_activation

 GLOBUS_GSI_CALLBACK_MODULE, 2

globus_gsi_callback_check_issued

 globus_gsi_callback, 4

globus_gsi_callback_constants

 globus_gsi_callback_error_t, 15

globus_gsi_callback_create_proxy_callback

 globus_gsi_callback, 4

globus_gsi_callback_data

 globus_gsi_callback_data_copy, 7

 globus_gsi_callback_data_destroy, 7

 globus_gsi_callback_data_init, 7

 globus_gsi_callback_data_t, 7

- globus_gsi_callback_get_cert_chain, [9](#)
- globus_gsi_callback_get_cert_depth, [8](#)
- globus_gsi_callback_get_cert_dir, [11](#)
- globus_gsi_callback_get_cert_type, [9](#)
- globus_gsi_callback_get_check_policy_for_self_signed_certs, [13](#)
- globus_gsi_callback_get_error, [13](#)
- globus_gsi_callback_get_extension_cb, [12](#)
- globus_gsi_callback_get_extension_oids, [11](#)
- globus_gsi_callback_get_multiple_limited_proxy_ok, [10](#)
- globus_gsi_callback_get_proxy_depth, [8](#)
- globus_gsi_callback_set_cert_chain, [10](#)
- globus_gsi_callback_set_cert_depth, [8](#)
- globus_gsi_callback_set_cert_dir, [12](#)
- globus_gsi_callback_set_cert_type, [9](#)
- globus_gsi_callback_set_check_policy_for_self_signed_certs, [14](#)
- globus_gsi_callback_set_error, [13](#)
- globus_gsi_callback_set_extension_cb, [12](#)
- globus_gsi_callback_set_extension_oids, [11](#)
- globus_gsi_callback_set_multiple_limited_proxy_ok, [10](#)
- globus_gsi_callback_set_proxy_depth, [8](#)
- globus_gsi_callback_data_copy
- globus_gsi_callback_data, [7](#)
- globus_gsi_callback_data_destroy
- globus_gsi_callback_data, [7](#)
- globus_gsi_callback_data_init
- globus_gsi_callback_data, [7](#)
- globus_gsi_callback_data_t
- globus_gsi_callback_data, [7](#)
- globus_gsi_callback_error_t
- globus_gsi_callback_constants, [15](#)
- globus_gsi_callback_get_cert_chain
- globus_gsi_callback_data, [9](#)
- globus_gsi_callback_get_cert_depth
- globus_gsi_callback_data, [8](#)
- globus_gsi_callback_get_cert_dir
- globus_gsi_callback_data, [11](#)
- globus_gsi_callback_get_cert_type
- globus_gsi_callback_data, [9](#)
- globus_gsi_callback_get_check_policy_for_self_signed_certs
- globus_gsi_callback_data, [13](#)
- globus_gsi_callback_get_error
- globus_gsi_callback_data, [13](#)
- globus_gsi_callback_get_extension_cb
- globus_gsi_callback_data, [12](#)
- globus_gsi_callback_get_extension_oids
- globus_gsi_callback_data, [11](#)
- globus_gsi_callback_get_multiple_limited_proxy_ok
- globus_gsi_callback_data, [10](#)
- globus_gsi_callback_get_proxy_depth
- globus_gsi_callback_data, [8](#)
- globus_gsi_callback_get_SSL_callback_data_index
- globus_gsi_callback, [3](#)
- globus_gsi_callback_get_X509_STORE_callback_data_index
- globus_gsi_callback, [3](#)
- globus_gsi_callback_handshake_callback
- globus_gsi_callback, [4](#)
- GLOBUS_GSI_CALLBACK_MODULE
- globus_gsi_callback_activation, [2](#)
- globus_gsi_callback_set_cert_chain
- globus_gsi_callback_data, [10](#)
- globus_gsi_callback_set_cert_depth
- globus_gsi_callback_data, [8](#)
- globus_gsi_callback_set_cert_dir
- globus_gsi_callback_data, [12](#)
- globus_gsi_callback_set_cert_type
- globus_gsi_callback_data, [9](#)
- globus_gsi_callback_set_check_policy_for_self_signed_certs
- globus_gsi_callback_data, [14](#)
- globus_gsi_callback_set_error
- globus_gsi_callback_data, [13](#)
- globus_gsi_callback_set_extension_cb
- globus_gsi_callback_data, [12](#)
- globus_gsi_callback_set_extension_oids
- globus_gsi_callback_data, [11](#)
- globus_gsi_callback_set_multiple_limited_proxy_ok
- globus_gsi_callback_data, [10](#)
- globus_gsi_callback_set_proxy_depth
- globus_gsi_callback_data, [8](#)
- globus_gsi_callback_X509_verify_cert
- globus_gsi_callback, [3](#)
- globus_gsi_extension_callback_t
- globus_gsi_callback, [3](#)
- GSI Callback Constants, [14](#)