

Free Component Library (FCL):  
Reference guide.

---

Reference guide for FCL units.  
Document version 2.1  
May 2012

Michaël Van Canneyt

---

# Contents

0.1	Overview	56
<b>1</b>	<b>Reference for unit 'ascii85'</b>	<b>57</b>
1.1	Used units	57
1.2	Overview	57
1.3	Constants, types and variables	57
1.3.1	Types	57
1.4	TASCII85DecoderStream	58
1.4.1	Description	58
1.4.2	Method overview	58
1.4.3	Property overview	58
1.4.4	TASCII85DecoderStream.Create	58
1.4.5	TASCII85DecoderStream.Decode	59
1.4.6	TASCII85DecoderStream.Close	59
1.4.7	TASCII85DecoderStream.ClosedP	59
1.4.8	TASCII85DecoderStream.Destroy	59
1.4.9	TASCII85DecoderStream.Read	60
1.4.10	TASCII85DecoderStream.Seek	60
1.4.11	TASCII85DecoderStream.BExpectBoundary	60
1.5	TASCII85EncoderStream	60
1.5.1	Description	60
1.5.2	Method overview	61
1.5.3	Property overview	61
1.5.4	TASCII85EncoderStream.Create	61
1.5.5	TASCII85EncoderStream.Destroy	61
1.5.6	TASCII85EncoderStream.Write	61
1.5.7	TASCII85EncoderStream.Width	62
1.5.8	TASCII85EncoderStream.Boundary	62
1.6	TASCII85RingBuffer	62
1.6.1	Description	62
1.6.2	Method overview	62

1.6.3	Property overview	62
1.6.4	TASCII85RingBuffer.Write	63
1.6.5	TASCII85RingBuffer.Read	63
1.6.6	TASCII85RingBuffer.FillCount	63
1.6.7	TASCII85RingBuffer.Size	63
<b>2</b>	<b>Reference for unit 'AVL_Tree'</b>	<b>64</b>
2.1	Used units	64
2.2	Overview	64
2.3	TAVLTree	64
2.3.1	Description	64
2.3.2	Method overview	65
2.3.3	Property overview	65
2.3.4	TAVLTree.Find	65
2.3.5	TAVLTree.FindKey	66
2.3.6	TAVLTree.FindSuccessor	66
2.3.7	TAVLTree.FindPrecessor	66
2.3.8	TAVLTree.FindLowest	66
2.3.9	TAVLTree.FindHighest	67
2.3.10	TAVLTree.FindNearest	67
2.3.11	TAVLTree.FindPointer	67
2.3.12	TAVLTree.FindLeftMost	67
2.3.13	TAVLTree.FindRightMost	68
2.3.14	TAVLTree.FindLeftMostKey	68
2.3.15	TAVLTree.FindRightMostKey	68
2.3.16	TAVLTree.FindLeftMostSameKey	68
2.3.17	TAVLTree.FindRightMostSameKey	69
2.3.18	TAVLTree.Add	69
2.3.19	TAVLTree.Delete	69
2.3.20	TAVLTree.Remove	69
2.3.21	TAVLTree.RemovePointer	70
2.3.22	TAVLTree.MoveDataLeftMost	70
2.3.23	TAVLTree.MoveDataRightMost	70
2.3.24	TAVLTree.Clear	70
2.3.25	TAVLTree.FreeAndClear	71
2.3.26	TAVLTree.FreeAndDelete	71
2.3.27	TAVLTree.ConsistencyCheck	71
2.3.28	TAVLTree.WriteReportToStream	71
2.3.29	TAVLTree.ReportAsString	72
2.3.30	TAVLTree.SetNodeManager	72

2.3.31	TAVLTree.Create	72
2.3.32	TAVLTree.Destroy	72
2.3.33	TAVLTree.GetEnumerator	73
2.3.34	TAVLTree.OnCompare	73
2.3.35	TAVLTree.Count	73
2.4	TAVLTreeNode	73
2.4.1	Description	73
2.4.2	Method overview	73
2.4.3	TAVLTreeNode.Clear	74
2.4.4	TAVLTreeNode.TreeDepth	74
2.5	TAVLTreeNodeEnumerator	74
2.5.1	Description	74
2.5.2	Method overview	74
2.5.3	Property overview	74
2.5.4	TAVLTreeNodeEnumerator.Create	74
2.5.5	TAVLTreeNodeEnumerator.MoveNext	75
2.5.6	TAVLTreeNodeEnumerator.Current	75
2.6	TAVLTreeNodeMemManager	75
2.6.1	Description	75
2.6.2	Method overview	75
2.6.3	Property overview	75
2.6.4	TAVLTreeNodeMemManager.DisposeNode	76
2.6.5	TAVLTreeNodeMemManager.NewNode	76
2.6.6	TAVLTreeNodeMemManager.Clear	76
2.6.7	TAVLTreeNodeMemManager.Create	76
2.6.8	TAVLTreeNodeMemManager.Destroy	76
2.6.9	TAVLTreeNodeMemManager.MinimumFreeNode	77
2.6.10	TAVLTreeNodeMemManager.MaximumFreeNodeRatio	77
2.6.11	TAVLTreeNodeMemManager.Count	77
2.7	TBaseAVLTreeNodeManager	77
2.7.1	Description	77
2.7.2	Method overview	78
2.7.3	TBaseAVLTreeNodeManager.DisposeNode	78
2.7.4	TBaseAVLTreeNodeManager.NewNode	78
<b>3</b>	<b>Reference for unit 'base64'</b>	<b>79</b>
3.1	Used units	79
3.2	Overview	79
3.3	Constants, types and variables	79
3.3.1	Types	79

3.4	Procedures and functions	80
3.4.1	DecodeStringBase64	80
3.4.2	EncodeStringBase64	80
3.5	EBase64DecodingException	80
3.5.1	Description	80
3.6	TBase64DecodingStream	80
3.6.1	Description	80
3.6.2	Method overview	81
3.6.3	Property overview	81
3.6.4	TBase64DecodingStream.Create	81
3.6.5	TBase64DecodingStream.Reset	81
3.6.6	TBase64DecodingStream.Read	81
3.6.7	TBase64DecodingStream.Seek	82
3.6.8	TBase64DecodingStream.EOF	82
3.6.9	TBase64DecodingStream.Mode	82
3.7	TBase64EncodingStream	83
3.7.1	Description	83
3.7.2	Method overview	83
3.7.3	TBase64EncodingStream.Create	83
3.7.4	TBase64EncodingStream.Destroy	83
3.7.5	TBase64EncodingStream.Flush	84
3.7.6	TBase64EncodingStream.Write	84
3.7.7	TBase64EncodingStream.Seek	84
<b>4</b>	<b>Reference for unit 'BlowFish'</b>	<b>85</b>
4.1	Used units	85
4.2	Overview	85
4.3	Constants, types and variables	85
4.3.1	Constants	85
4.3.2	Types	85
4.4	EBlowFishError	86
4.4.1	Description	86
4.5	TBlowFish	86
4.5.1	Description	86
4.5.2	Method overview	86
4.5.3	TBlowFish.Create	86
4.5.4	TBlowFish.Encrypt	87
4.5.5	TBlowFish.Decrypt	87
4.6	TBlowFishDeCryptStream	87
4.6.1	Description	87

4.6.2	Method overview	87
4.6.3	TBlowFishDeCryptStream.Read	87
4.6.4	TBlowFishDeCryptStream.Seek	88
4.7	TBlowFishEncryptStream	88
4.7.1	Description	88
4.7.2	Method overview	88
4.7.3	TBlowFishEncryptStream.Destroy	88
4.7.4	TBlowFishEncryptStream.Write	89
4.7.5	TBlowFishEncryptStream.Seek	89
4.7.6	TBlowFishEncryptStream.Flush	89
4.8	TBlowFishStream	90
4.8.1	Description	90
4.8.2	Method overview	90
4.8.3	Property overview	90
4.8.4	TBlowFishStream.Create	90
4.8.5	TBlowFishStream.Destroy	90
4.8.6	TBlowFishStream.BlowFish	91
<b>5</b>	<b>Reference for unit 'bufstream'</b>	<b>92</b>
5.1	Used units	92
5.2	Overview	92
5.3	Constants, types and variables	92
5.3.1	Constants	92
5.4	TBufStream	92
5.4.1	Description	92
5.4.2	Method overview	93
5.4.3	Property overview	93
5.4.4	TBufStream.Create	93
5.4.5	TBufStream.Destroy	93
5.4.6	TBufStream.Buffer	94
5.4.7	TBufStream.Capacity	94
5.4.8	TBufStream.BufferPos	94
5.4.9	TBufStream.BufferSize	94
5.5	TReadBufStream	95
5.5.1	Description	95
5.5.2	Method overview	95
5.5.3	TReadBufStream.Seek	95
5.5.4	TReadBufStream.Read	95
5.6	TWriteBufStream	96
5.6.1	Description	96

5.6.2	Method overview	96
5.6.3	TWriteBufStream.Destroy	96
5.6.4	TWriteBufStream.Seek	96
5.6.5	TWriteBufStream.Write	96
<b>6</b>	<b>Reference for unit 'CacheCls'</b>	<b>98</b>
6.1	Used units	98
6.2	Overview	98
6.3	Constants, types and variables	98
6.3.1	Resource strings	98
6.3.2	Types	98
6.4	ECacheError	99
6.4.1	Description	99
6.5	TCache	99
6.5.1	Description	99
6.5.2	Method overview	100
6.5.3	Property overview	100
6.5.4	TCache.Create	100
6.5.5	TCache.Destroy	100
6.5.6	TCache.Add	100
6.5.7	TCache.AddNew	101
6.5.8	TCache.FindSlot	101
6.5.9	TCache.IndexOf	101
6.5.10	TCache.Remove	102
6.5.11	TCache.Data	102
6.5.12	TCache.MRUSlot	102
6.5.13	TCache.LRUSlot	103
6.5.14	TCache.SlotCount	103
6.5.15	TCache.Slots	103
6.5.16	TCache.OnIsDataEqual	103
6.5.17	TCache.OnFreeSlot	104
<b>7</b>	<b>Reference for unit 'contnrs'</b>	<b>105</b>
7.1	Used units	105
7.2	Overview	105
7.3	Constants, types and variables	105
7.3.1	Constants	105
7.3.2	Types	106
7.4	Procedures and functions	109
7.4.1	RSHash	109
7.5	EDuplicate	109

7.5.1	Description	109
7.6	EKeyNotFound	109
7.6.1	Description	109
7.7	TBucketList	109
7.7.1	Description	109
7.7.2	Method overview	110
7.7.3	TBucketList.Create	110
7.8	TClassList	110
7.8.1	Description	110
7.8.2	Method overview	110
7.8.3	Property overview	110
7.8.4	TClassList.Add	111
7.8.5	TClassList.Extract	111
7.8.6	TClassList.Remove	111
7.8.7	TClassList.IndexOf	111
7.8.8	TClassList.First	112
7.8.9	TClassList.Last	112
7.8.10	TClassList.Insert	112
7.8.11	TClassList.Items	112
7.9	TComponentList	113
7.9.1	Description	113
7.9.2	Method overview	113
7.9.3	Property overview	113
7.9.4	TComponentList.Destroy	113
7.9.5	TComponentList.Add	113
7.9.6	TComponentList.Extract	114
7.9.7	TComponentList.Remove	114
7.9.8	TComponentList.IndexOf	114
7.9.9	TComponentList.First	115
7.9.10	TComponentList.Last	115
7.9.11	TComponentList.Insert	115
7.9.12	TComponentList.Items	115
7.10	TCustomBucketList	116
7.10.1	Description	116
7.10.2	Method overview	116
7.10.3	Property overview	116
7.10.4	TCustomBucketList.Destroy	116
7.10.5	TCustomBucketList.Clear	116
7.10.6	TCustomBucketList.Add	117
7.10.7	TCustomBucketList.Assign	117



7.10.8	TCustomBucketList.Exists	117
7.10.9	TCustomBucketList.Find	117
7.10.10	TCustomBucketList.ForEach	118
7.10.11	TCustomBucketList.Remove	118
7.10.12	TCustomBucketList.Data	118
7.11	TFPCustomHashTable	118
7.11.1	Description	118
7.11.2	Method overview	119
7.11.3	Property overview	119
7.11.4	TFPCustomHashTable.Create	119
7.11.5	TFPCustomHashTable.CreateWith	120
7.11.6	TFPCustomHashTable.Destroy	120
7.11.7	TFPCustomHashTable.ChangeTableSize	120
7.11.8	TFPCustomHashTable.Clear	120
7.11.9	TFPCustomHashTable.Delete	121
7.11.10	TFPCustomHashTable.Find	121
7.11.11	TFPCustomHashTable.IsEmpty	121
7.11.12	TFPCustomHashTable.HashFunction	121
7.11.13	TFPCustomHashTable.Count	122
7.11.14	TFPCustomHashTable.HashTableSize	122
7.11.15	TFPCustomHashTable.HashTable	122
7.11.16	TFPCustomHashTable.VoidSlots	122
7.11.17	TFPCustomHashTable.LoadFactor	123
7.11.18	TFPCustomHashTable.AVGChainLen	123
7.11.19	TFPCustomHashTable.MaxChainLength	123
7.11.20	TFPCustomHashTable.NumberOfCollisions	123
7.11.21	TFPCustomHashTable.Density	124
7.12	TFPDataHashTable	124
7.12.1	Description	124
7.12.2	Method overview	124
7.12.3	Property overview	124
7.12.4	TFPDataHashTable.Add	124
7.12.5	TFPDataHashTable.Items	125
7.13	TFPHashList	125
7.13.1	Description	125
7.13.2	Method overview	126
7.13.3	Property overview	126
7.13.4	TFPHashList.Create	126
7.13.5	TFPHashList.Destroy	126
7.13.6	TFPHashList.Add	127

7.13.7	TFPHashList.Clear	127
7.13.8	TFPHashList.NameOfIndex	127
7.13.9	TFPHashList.HashOfIndex	127
7.13.10	TFPHashList.GetNextCollision	128
7.13.11	TFPHashList.Delete	128
7.13.12	TFPHashList.Error	128
7.13.13	TFPHashList.Expand	128
7.13.14	TFPHashList.Extract	129
7.13.15	TFPHashList.IndexOf	129
7.13.16	TFPHashList.Find	129
7.13.17	TFPHashList.FindIndexOf	129
7.13.18	TFPHashList.FindWithHash	130
7.13.19	TFPHashList.Rename	130
7.13.20	TFPHashList.Remove	130
7.13.21	TFPHashList.Pack	130
7.13.22	TFPHashList.ShowStatistics	131
7.13.23	TFPHashList.ForEachCall	131
7.13.24	TFPHashList.Capacity	131
7.13.25	TFPHashList.Count	131
7.13.26	TFPHashList.Items	132
7.13.27	TFPHashList.List	132
7.13.28	TFPHashList.Strs	132
7.14	TFPHashObject	132
7.14.1	Description	132
7.14.2	Method overview	133
7.14.3	Property overview	133
7.14.4	TFPHashObject.CreateNotOwned	133
7.14.5	TFPHashObject.Create	133
7.14.6	TFPHashObject.ChangeOwner	133
7.14.7	TFPHashObject.ChangeOwnerAndName	134
7.14.8	TFPHashObject.Rename	134
7.14.9	TFPHashObject.Name	134
7.14.10	TFPHashObject.Hash	134
7.15	TFPHashObjectList	135
7.15.1	Method overview	135
7.15.2	Property overview	135
7.15.3	TFPHashObjectList.Create	135
7.15.4	TFPHashObjectList.Destroy	135
7.15.5	TFPHashObjectList.Clear	136
7.15.6	TFPHashObjectList.Add	136

7.15.7	TFPHashObjectList.NameOfIndex	136
7.15.8	TFPHashObjectList.HashOfIndex	137
7.15.9	TFPHashObjectList.GetNextCollision	137
7.15.10	TFPHashObjectList.Delete	137
7.15.11	TFPHashObjectList.Expand	137
7.15.12	TFPHashObjectList.Extract	138
7.15.13	TFPHashObjectList.Remove	138
7.15.14	TFPHashObjectList.IndexOf	138
7.15.15	TFPHashObjectList.Find	138
7.15.16	TFPHashObjectList.FindIndexOf	139
7.15.17	TFPHashObjectList.FindWithHash	139
7.15.18	TFPHashObjectList.Rename	139
7.15.19	TFPHashObjectList.FindInstanceOf	139
7.15.20	TFPHashObjectList.Pack	140
7.15.21	TFPHashObjectList.ShowStatistics	140
7.15.22	TFPHashObjectList.ForEachCall	140
7.15.23	TFPHashObjectList.Capacity	140
7.15.24	TFPHashObjectList.Count	141
7.15.25	TFPHashObjectList.OwnsObjects	141
7.15.26	TFPHashObjectList.Items	141
7.15.27	TFPHashObjectList.List	141
7.16	TFPObjectHashTable	142
7.16.1	Description	142
7.16.2	Method overview	142
7.16.3	Property overview	142
7.16.4	TFPObjectHashTable.Create	142
7.16.5	TFPObjectHashTable.CreateWith	142
7.16.6	TFPObjectHashTable.Add	143
7.16.7	TFPObjectHashTable.Items	143
7.16.8	TFPObjectHashTable.OwnsObjects	143
7.17	TFPObjectList	144
7.17.1	Description	144
7.17.2	Method overview	144
7.17.3	Property overview	144
7.17.4	TFPObjectList.Create	144
7.17.5	TFPObjectList.Destroy	145
7.17.6	TFPObjectList.Clear	145
7.17.7	TFPObjectList.Add	145
7.17.8	TFPObjectList.Delete	146
7.17.9	TFPObjectList.Exchange	146

7.17.10 TFPObjectList.Expand . . . . .	146
7.17.11 TFPObjectList.Extract . . . . .	146
7.17.12 TFPObjectList.Remove . . . . .	147
7.17.13 TFPObjectList.IndexOf . . . . .	147
7.17.14 TFPObjectList.FindInstanceOf . . . . .	147
7.17.15 TFPObjectList.Insert . . . . .	148
7.17.16 TFPObjectList.First . . . . .	148
7.17.17 TFPObjectList.Last . . . . .	148
7.17.18 TFPObjectList.Move . . . . .	148
7.17.19 TFPObjectList.Assign . . . . .	149
7.17.20 TFPObjectList.Pack . . . . .	149
7.17.21 TFPObjectList.Sort . . . . .	149
7.17.22 TFPObjectList.ForEachCall . . . . .	150
7.17.23 TFPObjectList.Capacity . . . . .	150
7.17.24 TFPObjectList.Count . . . . .	150
7.17.25 TFPObjectList.OwnsObjects . . . . .	150
7.17.26 TFPObjectList.Items . . . . .	151
7.17.27 TFPObjectList.List . . . . .	151
7.18 TFPStringHashTable . . . . .	151
7.18.1 Description . . . . .	151
7.18.2 Method overview . . . . .	151
7.18.3 Property overview . . . . .	152
7.18.4 TFPStringHashTable.Add . . . . .	152
7.18.5 TFPStringHashTable.Items . . . . .	152
7.19 THTCustomNode . . . . .	152
7.19.1 Description . . . . .	152
7.19.2 Method overview . . . . .	152
7.19.3 Property overview . . . . .	152
7.19.4 THTCustomNode.CreateWith . . . . .	153
7.19.5 THTCustomNode.HasKey . . . . .	153
7.19.6 THTCustomNode.Key . . . . .	153
7.20 THTDataNode . . . . .	153
7.20.1 Description . . . . .	153
7.20.2 Property overview . . . . .	154
7.20.3 THTDataNode.Data . . . . .	154
7.21 THTObjectNode . . . . .	154
7.21.1 Description . . . . .	154
7.21.2 Property overview . . . . .	154
7.21.3 THTObjectNode.Data . . . . .	154
7.22 THTOwnedObjectNode . . . . .	154

7.22.1	Description	154
7.22.2	Method overview	155
7.22.3	THTOwnedObjectNode.Destroy	155
7.23	THTStringNode	155
7.23.1	Description	155
7.23.2	Property overview	155
7.23.3	THTStringNode.Data	155
7.24	TObjectBucketList	155
7.24.1	Description	155
7.24.2	Method overview	156
7.24.3	Property overview	156
7.24.4	TObjectBucketList.Add	156
7.24.5	TObjectBucketList.Remove	156
7.24.6	TObjectBucketList.Data	156
7.25	TObjectList	157
7.25.1	Description	157
7.25.2	Method overview	157
7.25.3	Property overview	157
7.25.4	TObjectList.create	157
7.25.5	TObjectList.Add	157
7.25.6	TObjectList.Extract	158
7.25.7	TObjectList.Remove	158
7.25.8	TObjectList.IndexOf	158
7.25.9	TObjectList.FindInstanceOf	159
7.25.10	TObjectList.Insert	159
7.25.11	TObjectList.First	159
7.25.12	TObjectList.Last	159
7.25.13	TObjectList.OwnsObjects	160
7.25.14	TObjectList.Items	160
7.26	TObjectQueue	160
7.26.1	Method overview	160
7.26.2	TObjectQueue.Push	160
7.26.3	TObjectQueue.Pop	161
7.26.4	TObjectQueue.Peek	161
7.27	TObjectStack	161
7.27.1	Description	161
7.27.2	Method overview	161
7.27.3	TObjectStack.Push	161
7.27.4	TObjectStack.Pop	162
7.27.5	TObjectStack.Peek	162

7.28	TOrderedList	162
7.28.1	Description	162
7.28.2	Method overview	163
7.28.3	TOrderedList.Create	163
7.28.4	TOrderedList.Destroy	163
7.28.5	TOrderedList.Count	163
7.28.6	TOrderedList.AtLeast	164
7.28.7	TOrderedList.Push	164
7.28.8	TOrderedList.Pop	164
7.28.9	TOrderedList.Peek	164
7.29	TQueue	165
7.29.1	Description	165
7.30	TStack	165
7.30.1	Description	165
<b>8</b>	<b>Reference for unit 'CustApp'</b>	<b>166</b>
8.1	Used units	166
8.2	Overview	166
8.3	Constants, types and variables	166
8.3.1	Types	166
8.3.2	Variables	167
8.4	TCustomApplication	167
8.4.1	Description	167
8.4.2	Method overview	167
8.4.3	Property overview	168
8.4.4	TCustomApplication.Create	168
8.4.5	TCustomApplication.Destroy	168
8.4.6	TCustomApplication.HandleException	168
8.4.7	TCustomApplication.Initialize	169
8.4.8	TCustomApplication.Run	169
8.4.9	TCustomApplication.ShowException	169
8.4.10	TCustomApplication.Terminate	170
8.4.11	TCustomApplication.FindOptionIndex	170
8.4.12	TCustomApplication.GetOptionValue	170
8.4.13	TCustomApplication.HasOption	171
8.4.14	TCustomApplication.CheckOptions	171
8.4.15	TCustomApplication.GetEnvironmentList	172
8.4.16	TCustomApplication.Log	172
8.4.17	TCustomApplication.ExeName	172
8.4.18	TCustomApplication.HelpFile	173

8.4.19	<a href="#">TCustomApplication.Terminated</a>	173
8.4.20	<a href="#">TCustomApplication.Title</a>	173
8.4.21	<a href="#">TCustomApplication.OnException</a>	174
8.4.22	<a href="#">TCustomApplication.ConsoleApplication</a>	174
8.4.23	<a href="#">TCustomApplication.Location</a>	174
8.4.24	<a href="#">TCustomApplication.Params</a>	174
8.4.25	<a href="#">TCustomApplication.ParamCount</a>	175
8.4.26	<a href="#">TCustomApplication.EnvironmentVariable</a>	175
8.4.27	<a href="#">TCustomApplication.OptionChar</a>	175
8.4.28	<a href="#">TCustomApplication.CaseSensitiveOptions</a>	176
8.4.29	<a href="#">TCustomApplication.StopOnException</a>	176
8.4.30	<a href="#">TCustomApplication.EventLogFilter</a>	176
<b>9</b>	<b>Reference for unit 'daemonapp'</b>	<b>177</b>
9.1	<a href="#">Used units</a>	177
9.2	<a href="#">Overview</a>	177
9.3	<a href="#">Daemon application architecture</a>	178
9.4	<a href="#">Constants, types and variables</a>	178
9.4.1	<a href="#">Resource strings</a>	178
9.4.2	<a href="#">Types</a>	179
9.4.3	<a href="#">Variables</a>	182
9.5	<a href="#">Procedures and functions</a>	182
9.5.1	<a href="#">Application</a>	182
9.5.2	<a href="#">DaemonError</a>	183
9.5.3	<a href="#">RegisterDaemonApplicationClass</a>	183
9.5.4	<a href="#">RegisterDaemonClass</a>	183
9.5.5	<a href="#">RegisterDaemonMapper</a>	183
9.6	<a href="#">EDaemon</a>	184
9.6.1	<a href="#">Description</a>	184
9.7	<a href="#">TCustomDaemon</a>	184
9.7.1	<a href="#">Description</a>	184
9.7.2	<a href="#">Method overview</a>	184
9.7.3	<a href="#">Property overview</a>	184
9.7.4	<a href="#">TCustomDaemon.LogMessage</a>	184
9.7.5	<a href="#">TCustomDaemon.ReportStatus</a>	185
9.7.6	<a href="#">TCustomDaemon.Definition</a>	185
9.7.7	<a href="#">TCustomDaemon.DaemonThread</a>	185
9.7.8	<a href="#">TCustomDaemon.Controller</a>	186
9.7.9	<a href="#">TCustomDaemon.Status</a>	186
9.7.10	<a href="#">TCustomDaemon.Logger</a>	186

9.8	TCustomDaemonApplication	186
9.8.1	Description	186
9.8.2	Method overview	187
9.8.3	Property overview	187
9.8.4	TCustomDaemonApplication.Destroy	187
9.8.5	TCustomDaemonApplication.ShowException	187
9.8.6	TCustomDaemonApplication.CreateDaemon	187
9.8.7	TCustomDaemonApplication.StopDaemons	188
9.8.8	TCustomDaemonApplication.InstallDaemons	188
9.8.9	TCustomDaemonApplication.RunDaemons	188
9.8.10	TCustomDaemonApplication.UnInstallDaemons	188
9.8.11	TCustomDaemonApplication.ShowHelp	189
9.8.12	TCustomDaemonApplication.CreateForm	189
9.8.13	TCustomDaemonApplication.OnRun	189
9.8.14	TCustomDaemonApplication.EventLog	190
9.8.15	TCustomDaemonApplication.GUIMainLoop	190
9.8.16	TCustomDaemonApplication.GuiHandle	190
9.8.17	TCustomDaemonApplication.RunMode	190
9.9	TCustomDaemonMapper	191
9.9.1	Description	191
9.9.2	Method overview	191
9.9.3	Property overview	191
9.9.4	TCustomDaemonMapper.Create	191
9.9.5	TCustomDaemonMapper.Destroy	191
9.9.6	TCustomDaemonMapper.DaemonDefs	192
9.9.7	TCustomDaemonMapper.OnCreate	192
9.9.8	TCustomDaemonMapper.OnDestroy	192
9.9.9	TCustomDaemonMapper.OnRun	192
9.9.10	TCustomDaemonMapper.OnInstall	193
9.9.11	TCustomDaemonMapper.OnUnInstall	193
9.10	TDaemon	193
9.10.1	Description	193
9.10.2	Property overview	194
9.10.3	TDaemon.Definition	194
9.10.4	TDaemon.Status	194
9.10.5	TDaemon.OnStart	194
9.10.6	TDaemon.OnStop	195
9.10.7	TDaemon.OnPause	195
9.10.8	TDaemon.OnContinue	195
9.10.9	TDaemon.OnShutDown	196



9.10.10	TDaemon.OnExecute	196
9.10.11	TDaemon.BeforeInstall	196
9.10.12	TDaemon.AfterInstall	197
9.10.13	TDaemon.BeforeUnInstall	197
9.10.14	TDaemon.AfterUnInstall	197
9.10.15	TDaemon.OnControlCode	197
9.11	TDaemonApplication	198
9.11.1	Description	198
9.12	TDaemonController	198
9.12.1	Description	198
9.12.2	Method overview	198
9.12.3	Property overview	198
9.12.4	TDaemonController.Create	198
9.12.5	TDaemonController.Destroy	199
9.12.6	TDaemonController.StartService	199
9.12.7	TDaemonController.Main	199
9.12.8	TDaemonController.Controller	199
9.12.9	TDaemonController.ReportStatus	200
9.12.10	TDaemonController.Daemon	200
9.12.11	TDaemonController.Params	200
9.12.12	TDaemonController.LastStatus	200
9.12.13	TDaemonController.CheckPoint	201
9.13	TDaemonDef	201
9.13.1	Description	201
9.13.2	Method overview	201
9.13.3	Property overview	201
9.13.4	TDaemonDef.Create	201
9.13.5	TDaemonDef.Destroy	202
9.13.6	TDaemonDef.DaemonClass	202
9.13.7	TDaemonDef.Instance	202
9.13.8	TDaemonDef.DaemonClassName	202
9.13.9	TDaemonDef.Name	203
9.13.10	TDaemonDef.Description	203
9.13.11	TDaemonDef.DisplayName	203
9.13.12	TDaemonDef.RunArguments	203
9.13.13	TDaemonDef.Options	204
9.13.14	TDaemonDef.Enabled	204
9.13.15	TDaemonDef.WinBindings	204
9.13.16	TDaemonDef.OnCreateInstance	204
9.13.17	TDaemonDef.LogStatusReport	205

---

9.14	TDaemonDefs	205
9.14.1	Description	205
9.14.2	Method overview	205
9.14.3	Property overview	205
9.14.4	TDaemonDefs.Create	205
9.14.5	TDaemonDefs.IndexOfDaemonDef	206
9.14.6	TDaemonDefs.FindDaemonDef	206
9.14.7	TDaemonDefs.DaemonDefByName	206
9.14.8	TDaemonDefs.Daemons	206
9.15	TDaemonMapper	207
9.15.1	Description	207
9.15.2	Method overview	207
9.15.3	TDaemonMapper.Create	207
9.15.4	TDaemonMapper.CreateNew	207
9.16	TDaemonThread	208
9.16.1	Description	208
9.16.2	Method overview	208
9.16.3	Property overview	208
9.16.4	TDaemonThread.Create	208
9.16.5	TDaemonThread.Execute	208
9.16.6	TDaemonThread.CheckControlMessage	209
9.16.7	TDaemonThread.StopDaemon	209
9.16.8	TDaemonThread.PauseDaemon	209
9.16.9	TDaemonThread.ContinueDaemon	209
9.16.10	TDaemonThread.ShutDownDaemon	210
9.16.11	TDaemonThread.InterrogateDaemon	210
9.16.12	TDaemonThread.Daemon	210
9.17	TDependencies	210
9.17.1	Description	210
9.17.2	Method overview	210
9.17.3	Property overview	211
9.17.4	TDependencies.Create	211
9.17.5	TDependencies.Items	211
9.18	TDependency	211
9.18.1	Description	211
9.18.2	Method overview	211
9.18.3	Property overview	211
9.18.4	TDependency.Assign	212
9.18.5	TDependency.Name	212
9.18.6	TDependency.IsGroup	212

9.19	TWinBindings	212
9.19.1	Description	212
9.19.2	Method overview	212
9.19.3	Property overview	213
9.19.4	TWinBindings.Create	213
9.19.5	TWinBindings.Destroy	213
9.19.6	TWinBindings.Assign	213
9.19.7	TWinBindings.ErrCode	213
9.19.8	TWinBindings.Win32ErrCode	214
9.19.9	TWinBindings.Dependencies	214
9.19.10	TWinBindings.GroupName	214
9.19.11	TWinBindings.Password	215
9.19.12	TWinBindings.UserName	215
9.19.13	TWinBindings.StartType	215
9.19.14	TWinBindings.WaitHint	215
9.19.15	TWinBindings.IDTag	216
9.19.16	TWinBindings.ServiceType	216
9.19.17	TWinBindings.ErrorSeverity	216
<b>10</b>	<b>Reference for unit 'db'</b>	<b>217</b>
10.1	Used units	217
10.2	Overview	217
10.3	Constants, types and variables	217
10.3.1	Constants	217
10.3.2	Types	218
10.4	Procedures and functions	231
10.4.1	BuffersEqual	231
10.4.2	DatabaseError	231
10.4.3	DatabaseErrorFmt	232
10.4.4	DateTimeRecToDateTime	232
10.4.5	DateTimeToDateTimeRec	232
10.4.6	DisposeMem	232
10.4.7	ExtractFieldName	233
10.4.8	SkipComments	233
10.5	EDatabaseError	233
10.5.1	Description	233
10.6	EUpdateError	233
10.6.1	Description	233
10.6.2	Method overview	234
10.6.3	Property overview	234

10.6.4	EUpdateError.Create	234
10.6.5	EUpdateError.Destroy	234
10.6.6	EUpdateError.Context	234
10.6.7	EUpdateError.ErrorCode	235
10.6.8	EUpdateError.OriginalException	235
10.6.9	EUpdateError.PreviousError	235
10.7	IProviderSupport	236
10.7.1	Method overview	236
10.7.2	IProviderSupport.PSEndTransaction	236
10.7.3	IProviderSupport.PSExecute	236
10.7.4	IProviderSupport.PSExecuteStatement	236
10.7.5	IProviderSupport.PSGetAttributes	236
10.7.6	IProviderSupport.PSGetCommandText	237
10.7.7	IProviderSupport.PSGetCommandType	237
10.7.8	IProviderSupport.PSGetDefaultOrder	237
10.7.9	IProviderSupport.PSGetIndexDefs	237
10.7.10	IProviderSupport.PSGetKeyFields	237
10.7.11	IProviderSupport.PSGetParams	237
10.7.12	IProviderSupport.PSGetQuoteChar	237
10.7.13	IProviderSupport.PSGetTableName	237
10.7.14	IProviderSupport.PSGetUpdateException	237
10.7.15	IProviderSupport.PSInTransaction	238
10.7.16	IProviderSupport.PSIsSQLBased	238
10.7.17	IProviderSupport.PSIsSQLSupported	238
10.7.18	IProviderSupport.PSReset	238
10.7.19	IProviderSupport.PSSetCommandText	238
10.7.20	IProviderSupport.PSSetParams	238
10.7.21	IProviderSupport.PSStartTransaction	238
10.7.22	IProviderSupport.PSUpdateRecord	238
10.8	TAutoIncField	239
10.8.1	Description	239
10.8.2	Method overview	239
10.8.3	TAutoIncField.Create	239
10.9	TBCDField	239
10.9.1	Description	239
10.9.2	Method overview	239
10.9.3	Property overview	240
10.9.4	TBCDField.CheckTypeSize	240
10.9.5	TBCDField.Create	240
10.9.6	TBCDField.CheckRange	240

10.9.7 TBCDField.Value . . . . .	240
10.9.8 TBCDField.Precision . . . . .	241
10.9.9 TBCDField.Currency . . . . .	241
10.9.10 TBCDField.MaxValue . . . . .	241
10.9.11 TBCDField.MinValue . . . . .	242
10.9.12 TBCDField.Size . . . . .	242
10.10 TBinaryField . . . . .	242
10.10.1 Description . . . . .	242
10.10.2 Method overview . . . . .	242
10.10.3 Property overview . . . . .	242
10.10.4 TBinaryField.CheckTypeSize . . . . .	243
10.10.5 TBinaryField.Create . . . . .	243
10.10.6 TBinaryField.Size . . . . .	243
10.11 TBlobField . . . . .	243
10.11.1 Description . . . . .	243
10.11.2 Method overview . . . . .	243
10.11.3 Property overview . . . . .	244
10.11.4 TBlobField.Create . . . . .	244
10.11.5 TBlobField.Clear . . . . .	244
10.11.6 TBlobField.IsBlob . . . . .	244
10.11.7 TBlobField.LoadFromFile . . . . .	244
10.11.8 TBlobField.LoadFromStream . . . . .	245
10.11.9 TBlobField.SaveToFile . . . . .	245
10.11.10 TBlobField.SaveToStream . . . . .	245
10.11.11 TBlobField.SetFieldType . . . . .	246
10.11.12 TBlobField.BlobSize . . . . .	246
10.11.13 TBlobField.Modified . . . . .	246
10.11.14 TBlobField.Value . . . . .	246
10.11.15 TBlobField.Transliterate . . . . .	247
10.11.16 TBlobField.BlobType . . . . .	247
10.11.17 TBlobField.Size . . . . .	247
10.12 TBooleanField . . . . .	247
10.12.1 Description . . . . .	247
10.12.2 Method overview . . . . .	248
10.12.3 Property overview . . . . .	248
10.12.4 TBooleanField.Create . . . . .	248
10.12.5 TBooleanField.Value . . . . .	248
10.12.6 TBooleanField.DisplayValues . . . . .	248
10.13 TBytesField . . . . .	249
10.13.1 Description . . . . .	249

10.13.2 Method overview . . . . .	249
10.13.3 TBytesField.Create . . . . .	249
10.14 TCheckConstraint . . . . .	249
10.14.1 Description . . . . .	249
10.14.2 Method overview . . . . .	250
10.14.3 Property overview . . . . .	250
10.14.4 TCheckConstraint.Assign . . . . .	250
10.14.5 TCheckConstraint.CustomConstraint . . . . .	250
10.14.6 TCheckConstraint.ErrorMessage . . . . .	250
10.14.7 TCheckConstraint.FromDictionary . . . . .	251
10.14.8 TCheckConstraint.ImportedConstraint . . . . .	251
10.15 TCheckConstraints . . . . .	251
10.15.1 Description . . . . .	251
10.15.2 Method overview . . . . .	251
10.15.3 Property overview . . . . .	251
10.15.4 TCheckConstraints.Create . . . . .	252
10.15.5 TCheckConstraints.Add . . . . .	252
10.15.6 TCheckConstraints.Items . . . . .	252
10.16 TCurrencyField . . . . .	252
10.16.1 Description . . . . .	252
10.16.2 Method overview . . . . .	253
10.16.3 Property overview . . . . .	253
10.16.4 TCurrencyField.Create . . . . .	253
10.16.5 TCurrencyField.Currency . . . . .	253
10.17 TCustomConnection . . . . .	253
10.17.1 Description . . . . .	253
10.17.2 Method overview . . . . .	253
10.17.3 Property overview . . . . .	254
10.17.4 TCustomConnection.Close . . . . .	254
10.17.5 TCustomConnection.Destroy . . . . .	254
10.17.6 TCustomConnection.Open . . . . .	254
10.17.7 TCustomConnection.DataSetCount . . . . .	255
10.17.8 TCustomConnection.DataSets . . . . .	255
10.17.9 TCustomConnection.Connected . . . . .	255
10.17.10 TCustomConnection.LoginPrompt . . . . .	256
10.17.11 TCustomConnection.AfterConnect . . . . .	256
10.17.12 TCustomConnection.AfterDisconnect . . . . .	256
10.17.13 TCustomConnection.BeforeConnect . . . . .	256
10.17.14 TCustomConnection.BeforeDisconnect . . . . .	257
10.17.15 TCustomConnection.OnLogin . . . . .	257

10.18	TDatabase	257
10.18.1	Description	257
10.18.2	Method overview	258
10.18.3	Property overview	258
10.18.4	TDatabase.Create	258
10.18.5	TDatabase.Destroy	258
10.18.6	TDatabase.CloseDataSets	258
10.18.7	TDatabase.CloseTransactions	259
10.18.8	TDatabase.StartTransaction	259
10.18.9	TDatabase.EndTransaction	259
10.18.10	TDatabase.TransactionCount	259
10.18.11	TDatabase.Transactions	260
10.18.12	TDatabase.Directory	260
10.18.13	TDatabase.IsSQLBased	260
10.18.14	TDatabase.Connected	261
10.18.15	TDatabase.DatabaseName	261
10.18.16	TDatabase.KeepConnection	261
10.18.17	TDatabase.Params	261
10.19	TDataLink	262
10.19.1	Description	262
10.19.2	Method overview	262
10.19.3	Property overview	262
10.19.4	TDataLink.Create	262
10.19.5	TDataLink.Destroy	263
10.19.6	TDataLink.Edit	263
10.19.7	TDataLink.UpdateRecord	263
10.19.8	TDataLink.ExecuteAction	263
10.19.9	TDataLink.UpdateAction	264
10.19.10	TDataLink.Active	264
10.19.11	TDataLink.ActiveRecord	264
10.19.12	TDataLink.BOF	264
10.19.13	TDataLink.BufferCount	265
10.19.14	TDataLink.DataSet	265
10.19.15	TDataLink.DataSource	265
10.19.16	TDataLink.DataSourceFixed	265
10.19.17	TDataLink.Editing	266
10.19.18	TDataLink.Eof	266
10.19.19	TDataLink.ReadOnly	266
10.19.20	TDataLink.RecordCount	266
10.20	TDataSet	267

10.20.1 Description . . . . .	267
10.20.2 Method overview . . . . .	269
10.20.3 Property overview . . . . .	270
10.20.4 TDataSet.Create . . . . .	271
10.20.5 TDataSet.Destroy . . . . .	271
10.20.6 TDataSet.ActiveBuffer . . . . .	271
10.20.7 TDataSet.GetFieldData . . . . .	271
10.20.8 TDataSet.SetFieldData . . . . .	272
10.20.9 TDataSet.Append . . . . .	272
10.20.10 TDataSet.AppendRecord . . . . .	272
10.20.11 IFDataSet.BookmarkValid . . . . .	273
10.20.12 TDataSet.Cancel . . . . .	273
10.20.13 TDataSet.CheckBrowseMode . . . . .	273
10.20.14 IFDataSet.ClearFields . . . . .	273
10.20.15 TDataSet.Close . . . . .	274
10.20.16 TDataSet.ControlsDisabled . . . . .	274
10.20.17 TDataSet.CompareBookmarks . . . . .	274
10.20.18 IFDataSet.CreateBlobStream . . . . .	275
10.20.19 TDataSet.CursorPosChanged . . . . .	275
10.20.20 TDataSet.DataConvert . . . . .	275
10.20.21 IFDataSet.Delete . . . . .	275
10.20.22 TDataSet.DisableControls . . . . .	276
10.20.23 TDataSet.Edit . . . . .	276
10.20.24 IFDataSet.EnableControls . . . . .	277
10.20.25 TDataSet.FieldByName . . . . .	277
10.20.26 IFDataSet.FindField . . . . .	277
10.20.27 TDataSet.FindFirst . . . . .	278
10.20.28 IFDataSet.FindLast . . . . .	278
10.20.29 TDataSet.FindNext . . . . .	278
10.20.30 IFDataSet.FindPrior . . . . .	278
10.20.31 IFDataSet.First . . . . .	279
10.20.32 TDataSet.FreeBookmark . . . . .	279
10.20.33 IFDataSet.GetBookmark . . . . .	279
10.20.34 TDataSet.GetCurrentRecord . . . . .	280
10.20.35 TDataSet.GetFieldList . . . . .	280
10.20.36 IFDataSet.GetFieldNames . . . . .	280
10.20.37 TDataSet.GotoBookmark . . . . .	280
10.20.38 TDataSet.Insert . . . . .	281
10.20.39 TDataSet.InsertRecord . . . . .	281
10.20.40 IFDataSet.IsEmpty . . . . .	281



10.20.41	DataSet.IsLinkedTo	281
10.20.42	DataSet.IsSequenced	282
10.20.43	DataSet.Last	282
10.20.44	DataSet.Locate	282
10.20.45	DataSet.Lookup	283
10.20.46	DataSet.MoveBy	283
10.20.47	DataSet.Next	283
10.20.48	DataSet.Open	284
10.20.49	DataSet.Post	284
10.20.50	DataSet.Prior	285
10.20.51	DataSet.Refresh	285
10.20.52	DataSet.Resync	285
10.20.53	DataSet.SetFields	285
10.20.54	DataSet.Translate	286
10.20.55	DataSet.UpdateCursorPos	286
10.20.56	DataSet.UpdateRecord	286
10.20.57	DataSet.UpdateStatus	287
10.20.58	DataSet.BlockReadSize	287
10.20.59	DataSet.BOF	287
10.20.60	DataSet.Bookmark	287
10.20.61	DataSet.CanModify	288
10.20.62	DataSet.DataSource	288
10.20.63	DataSet.DefaultFields	289
10.20.64	DataSet.EOF	289
10.20.65	DataSet.FieldCount	290
10.20.66	DataSet.FieldDefs	290
10.20.67	DataSet.Found	290
10.20.68	DataSet.Modified	291
10.20.69	DataSet.IsUniDirectional	291
10.20.70	DataSet.RecordCount	291
10.20.71	DataSet.RecNo	292
10.20.72	DataSet.RecordSize	292
10.20.73	DataSet.State	292
10.20.74	DataSet.Fields	293
10.20.75	DataSet.FieldValues	293
10.20.76	DataSet.Filter	293
10.20.77	DataSet.Filtered	294
10.20.78	DataSet.FilterOptions	294
10.20.79	DataSet.Active	294
10.20.80	DataSet.AutoCalcFields	295

10.20.81	DataSet.BeforeOpen	295
10.20.82	DataSet.AfterOpen	296
10.20.83	DataSet.BeforeClose	296
10.20.84	DataSet.AfterClose	296
10.20.85	DataSet.BeforeInsert	296
10.20.86	DataSet.AfterInsert	297
10.20.87	DataSet.BeforeEdit	297
10.20.88	DataSet.AfterEdit	297
10.20.89	DataSet.BeforePost	298
10.20.90	DataSet.AfterPost	298
10.20.91	DataSet.BeforeCancel	298
10.20.92	DataSet.AfterCancel	299
10.20.93	DataSet.BeforeDelete	299
10.20.94	DataSet.AfterDelete	299
10.20.95	DataSet.BeforeScroll	299
10.20.96	DataSet.AfterScroll	300
10.20.97	DataSet.BeforeRefresh	300
10.20.98	DataSet.AfterRefresh	300
10.20.99	DataSet.OnCalcFields	301
10.20.100	DataSet.OnDeleteError	301
10.20.101	DataSet.OnEditError	301
10.20.102	DataSet.OnFilterRecord	302
10.20.103	DataSet.OnNewRecord	302
10.20.104	DataSet.OnPostError	303
10.21	TDataSource	303
10.21.1	Description	303
10.21.2	Method overview	303
10.21.3	Property overview	304
10.21.4	TDataSource.Create	304
10.21.5	TDataSource.Destroy	304
10.21.6	TDataSource.Edit	304
10.21.7	TDataSource.IsLinkedTo	305
10.21.8	TDataSource.State	305
10.21.9	TDataSource.AutoEdit	305
10.21.10	TDataSource.DataSet	305
10.21.11	TDataSource.Enabled	306
10.21.12	TDataSource.OnStateChange	306
10.21.13	TDataSource.OnDataChange	306
10.21.14	TDataSource.OnUpdateData	307
10.22	TDateField	307

---

10.22.1 Description	307
10.22.2 Method overview	307
10.22.3 TDateField.Create	307
10.23TDateTimeField	307
10.23.1 Description	307
10.23.2 Method overview	308
10.23.3 Property overview	308
10.23.4 TDateTimeField.Create	308
10.23.5 TDateTimeField.Value	308
10.23.6 TDateTimeField.DisplayFormat	308
10.23.7 TDateTimeField.EditMask	309
10.24TDBDataset	309
10.24.1 Description	309
10.24.2 Method overview	309
10.24.3 Property overview	309
10.24.4 TDBDataset.destroy	310
10.24.5 TDBDataset.DataBase	310
10.24.6 TDBDataset.Transaction	310
10.25TDBTransaction	310
10.25.1 Description	310
10.25.2 Method overview	311
10.25.3 Property overview	311
10.25.4 TDBTransaction.Create	311
10.25.5 TDBTransaction.destroy	311
10.25.6 TDBTransaction.CloseDataSets	311
10.25.7 TDBTransaction.DataBase	312
10.25.8 TDBTransaction.Active	312
10.26TDefCollection	312
10.26.1 Description	312
10.26.2 Method overview	312
10.26.3 Property overview	312
10.26.4 TDefCollection.create	313
10.26.5 TDefCollection.Find	313
10.26.6 TDefCollection.GetItemNames	313
10.26.7 TDefCollection.IndexOf	313
10.26.8 TDefCollection.Dataset	314
10.26.9 TDefCollection.Updated	314
10.27TDetailDataLink	314
10.27.1 Description	314
10.27.2 Property overview	314

10.27.3 TDetailDataLink.DetailDataSet . . . . .	314
10.28 TField . . . . .	315
10.28.1 Description . . . . .	315
10.28.2 Method overview . . . . .	315
10.28.3 Property overview . . . . .	317
10.28.4 TField.CheckTypeSize . . . . .	318
10.28.5 TField.Create . . . . .	318
10.28.6 TField.Destroy . . . . .	318
10.28.7 TField.Assign . . . . .	318
10.28.8 TField.AssignValue . . . . .	319
10.28.9 TField.Clear . . . . .	319
10.28.10 TField.FocusControl . . . . .	319
10.28.11 TField.GetData . . . . .	319
10.28.12 TField.IsBlob . . . . .	320
10.28.13 TField.IsValidChar . . . . .	320
10.28.14 TField.RefreshLookupList . . . . .	320
10.28.15 TField.SetData . . . . .	321
10.28.16 TField.SetFieldType . . . . .	321
10.28.17 TField.Validate . . . . .	321
10.28.18 TField.AsBCD . . . . .	322
10.28.19 TField.AsBoolean . . . . .	322
10.28.20 TField.AsCurrency . . . . .	322
10.28.21 TField.AsDateTime . . . . .	323
10.28.22 TField.AsFloat . . . . .	323
10.28.23 TField.AsLongint . . . . .	323
10.28.24 TField.AsLargeInt . . . . .	324
10.28.25 TField.AsInteger . . . . .	324
10.28.26 TField.AsString . . . . .	324
10.28.27 TField.AsWideString . . . . .	325
10.28.28 TField.AsVariant . . . . .	325
10.28.29 TField.AttributeSet . . . . .	325
10.28.30 TField.Calculated . . . . .	326
10.28.31 TField.CanModify . . . . .	326
10.28.32 TField.CurValue . . . . .	326
10.28.33 TField.DataSet . . . . .	326
10.28.34 TField.DataSize . . . . .	327
10.28.35 TField.DataType . . . . .	327
10.28.36 TField.DisplayName . . . . .	327
10.28.37 TField.DisplayText . . . . .	327
10.28.38 TField.EditMask . . . . .	328

10.28.39	Field.EditMaskPtr	328
10.28.40	Field.FieldNo	328
10.28.41	Field.IsIndexField	329
10.28.42	Field.IsNull	329
10.28.43	Field.Lookup	329
10.28.44	Field.NewValue	329
10.28.45	Field.Offset	330
10.28.46	Field.Size	330
10.28.47	Field.Text	330
10.28.48	Field.ValidChars	330
10.28.49	Field.Value	331
10.28.50	Field.OldValue	331
10.28.51	Field.LookupList	331
10.28.52	Field.Alignment	332
10.28.53	Field.CustomConstraint	332
10.28.54	Field.ConstraintErrorMessage	332
10.28.55	Field.DefaultExpression	333
10.28.56	Field.DisplayLabel	333
10.28.57	Field.DisplayWidth	333
10.28.58	Field.FieldKind	333
10.28.59	Field.FieldName	334
10.28.60	Field.HasConstraints	334
10.28.61	Field.Index	334
10.28.62	Field.ImportedConstraint	334
10.28.63	Field.KeyFields	335
10.28.64	Field.LookupCache	335
10.28.65	Field.LookupDataSet	335
10.28.66	Field.LookupKeyFields	336
10.28.67	Field.LookupResultField	336
10.28.68	Field.Origin	336
10.28.69	Field.ProviderFlags	336
10.28.70	Field.ReadOnly	337
10.28.71	Field.Required	337
10.28.72	Field.Visible	337
10.28.73	Field.OnChange	338
10.28.74	Field.OnGetText	338
10.28.75	Field.OnSetText	338
10.28.76	Field.OnValidate	338
10.29	FieldDef	339
10.29.1	Description	339

10.29.2 Method overview . . . . .	339
10.29.3 Property overview . . . . .	339
10.29.4 TFieldDef.Create . . . . .	339
10.29.5 TFieldDef.Destroy . . . . .	340
10.29.6 TFieldDef.Assign . . . . .	340
10.29.7 TFieldDef.CreateField . . . . .	340
10.29.8 TFieldDef.FieldClass . . . . .	341
10.29.9 TFieldDef.FieldNo . . . . .	341
10.29.10 TFieldDef.InternalCalcField . . . . .	341
10.29.11 TFieldDef.Required . . . . .	341
10.29.12 TFieldDef.Attributes . . . . .	342
10.29.13 TFieldDef.DataType . . . . .	342
10.29.14 TFieldDef.Precision . . . . .	342
10.29.15 TFieldDef.Size . . . . .	342
10.30 TFieldDefs . . . . .	343
10.30.1 Description . . . . .	343
10.30.2 Method overview . . . . .	343
10.30.3 Property overview . . . . .	343
10.30.4 TFieldDefs.Create . . . . .	343
10.30.5 TFieldDefs.Add . . . . .	343
10.30.6 TFieldDefs.AddFieldDef . . . . .	344
10.30.7 TFieldDefs.Assign . . . . .	344
10.30.8 TFieldDefs.Find . . . . .	344
10.30.9 TFieldDefs.Update . . . . .	344
10.30.10 TFieldDefs.MakeNameUnique . . . . .	345
10.30.11 TFieldDefs.HiddenFields . . . . .	345
10.30.12 TFieldDefs.Items . . . . .	345
10.31 Tfields . . . . .	345
10.31.1 Description . . . . .	345
10.31.2 Method overview . . . . .	346
10.31.3 Property overview . . . . .	346
10.31.4 Tfields.Create . . . . .	346
10.31.5 Tfields.Destroy . . . . .	346
10.31.6 Tfields.Add . . . . .	346
10.31.7 Tfields.CheckFieldName . . . . .	347
10.31.8 Tfields.CheckFieldNames . . . . .	347
10.31.9 Tfields.Clear . . . . .	347
10.31.10 Tfields.FindField . . . . .	348
10.31.11 Tfields.FieldByName . . . . .	348
10.31.12 Tfields.FieldByNumber . . . . .	348

10.31.13	TFields.GetEnumerator	348
10.31.14	TFields.GetFieldNames	349
10.31.15	TFields.IndexOf	349
10.31.16	TFields.Remove	349
10.31.17	TFields.Count	349
10.31.18	TFields.Dataset	350
10.31.19	TFields.Fields	350
10.32	TFieldsEnumerator	350
10.32.1	Description	350
10.32.2	Method overview	351
10.32.3	Property overview	351
10.32.4	TFieldsEnumerator.Create	351
10.32.5	TFieldsEnumerator.MoveNext	351
10.32.6	TFieldsEnumerator.Current	351
10.33	TFloatField	352
10.33.1	Description	352
10.33.2	Method overview	352
10.33.3	Property overview	352
10.33.4	TFloatField.Create	352
10.33.5	TFloatField.CheckRange	352
10.33.6	TFloatField.Value	353
10.33.7	TFloatField.Currency	353
10.33.8	TFloatField.MaxValue	353
10.33.9	TFloatField.MinValue	354
10.33.10	TFloatField.Precision	354
10.34	TFMTBCDField	354
10.34.1	Method overview	354
10.34.2	Property overview	354
10.34.3	TFMTBCDField.CheckTypeSize	355
10.34.4	TFMTBCDField.Create	355
10.34.5	TFMTBCDField.CheckRange	355
10.34.6	TFMTBCDField.Value	355
10.34.7	TFMTBCDField.Precision	355
10.34.8	TFMTBCDField.Currency	355
10.34.9	TFMTBCDField.MaxValue	355
10.34.10	TFMTBCDField.MinValue	355
10.34.11	TFMTBCDField.Size	356
10.35	TGraphicField	356
10.35.1	Description	356
10.35.2	Method overview	356

10.35.3 TGraphicField.Create . . . . .	356
10.36 TGuidField . . . . .	356
10.36.1 Description . . . . .	356
10.36.2 Method overview . . . . .	357
10.36.3 Property overview . . . . .	357
10.36.4 TGuidField.CheckTypeSize . . . . .	357
10.36.5 TGuidField.Create . . . . .	357
10.36.6 TGuidField.AsGuid . . . . .	357
10.37 TIndexDef . . . . .	357
10.37.1 Description . . . . .	357
10.37.2 Method overview . . . . .	358
10.37.3 Property overview . . . . .	358
10.37.4 TIndexDef.Create . . . . .	358
10.37.5 TIndexDef.Destroy . . . . .	358
10.37.6 TIndexDef.Expression . . . . .	358
10.37.7 TIndexDef.Fields . . . . .	359
10.37.8 TIndexDef.CaseInsFields . . . . .	359
10.37.9 TIndexDef.DescFields . . . . .	359
10.37.10 TIndexDef.Options . . . . .	360
10.37.11 TIndexDef.Source . . . . .	360
10.38 TIndexDefs . . . . .	360
10.38.1 Description . . . . .	360
10.38.2 Method overview . . . . .	360
10.38.3 Property overview . . . . .	360
10.38.4 TIndexDefs.Create . . . . .	361
10.38.5 TIndexDefs.Destroy . . . . .	361
10.38.6 TIndexDefs.Add . . . . .	361
10.38.7 TIndexDefs.AddIndexDef . . . . .	361
10.38.8 TIndexDefs.Find . . . . .	362
10.38.9 TIndexDefs.FindIndexForFields . . . . .	362
10.38.10 TIndexDefs.GetIndexForFields . . . . .	362
10.38.11 TIndexDefs.Update . . . . .	362
10.38.12 TIndexDefs.Items . . . . .	363
10.39 TIntegerField . . . . .	363
10.39.1 Description . . . . .	363
10.40 TLargeintField . . . . .	363
10.40.1 Description . . . . .	363
10.40.2 Method overview . . . . .	363
10.40.3 Property overview . . . . .	363
10.40.4 TLargeintField.Create . . . . .	364



10.40.5 TLargeintField.CheckRange . . . . .	364
10.40.6 TLargeintField.Value . . . . .	364
10.40.7 TLargeintField.MaxValue . . . . .	364
10.40.8 TLargeintField.MinValue . . . . .	365
10.41 TLongintField . . . . .	365
10.41.1 Description . . . . .	365
10.41.2 Method overview . . . . .	365
10.41.3 Property overview . . . . .	365
10.41.4 TLongintField.Create . . . . .	365
10.41.5 TLongintField.CheckRange . . . . .	366
10.41.6 TLongintField.Value . . . . .	366
10.41.7 TLongintField.MaxValue . . . . .	366
10.41.8 TLongintField.MinValue . . . . .	366
10.42 TLookupList . . . . .	367
10.42.1 Description . . . . .	367
10.42.2 Method overview . . . . .	367
10.42.3 TLookupList.Create . . . . .	367
10.42.4 TLookupList.Destroy . . . . .	367
10.42.5 TLookupList.Add . . . . .	367
10.42.6 TLookupList.Clear . . . . .	368
10.42.7 TLookupList.FirstKeyByValue . . . . .	368
10.42.8 TLookupList.ValueOfKey . . . . .	368
10.42.9 TLookupList.ValuesToStrings . . . . .	368
10.43 TMasterDataLink . . . . .	369
10.43.1 Description . . . . .	369
10.43.2 Method overview . . . . .	369
10.43.3 Property overview . . . . .	369
10.43.4 TMasterDataLink.Create . . . . .	369
10.43.5 TMasterDataLink.Destroy . . . . .	369
10.43.6 TMasterDataLink.FieldNames . . . . .	370
10.43.7 TMasterDataLink.Fields . . . . .	370
10.43.8 TMasterDataLink.OnMasterChange . . . . .	370
10.43.9 TMasterDataLink.OnMasterDisable . . . . .	370
10.44 TMasterParamsDataLink . . . . .	371
10.44.1 Description . . . . .	371
10.44.2 Method overview . . . . .	371
10.44.3 Property overview . . . . .	371
10.44.4 TMasterParamsDataLink.Create . . . . .	371
10.44.5 TMasterParamsDataLink.RefreshParamNames . . . . .	371
10.44.6 TMasterParamsDataLink.CopyParamsFromMaster . . . . .	372

10.44.7 TMasterParamsDataLink.Params	372
10.45 TMemoField	372
10.45.1 Description	372
10.45.2 Method overview	372
10.45.3 Property overview	372
10.45.4 TMemoField.Create	373
10.45.5 TMemoField.Transliterate	373
10.46 TNamedItem	373
10.46.1 Description	373
10.46.2 Property overview	373
10.46.3 TNamedItem.DisplayName	373
10.46.4 TNamedItem.Name	374
10.47 TNumericField	374
10.47.1 Description	374
10.47.2 Method overview	374
10.47.3 Property overview	374
10.47.4 TNumericField.CheckTypeSize	374
10.47.5 TNumericField.Create	374
10.47.6 TNumericField.Alignment	375
10.47.7 TNumericField.DisplayFormat	375
10.47.8 TNumericField.EditFormat	375
10.48 TParam	376
10.48.1 Description	376
10.48.2 Method overview	376
10.48.3 Property overview	377
10.48.4 TParam.Create	377
10.48.5 TParam.Assign	377
10.48.6 TParam.AssignField	378
10.48.7 TParam.AssignToField	378
10.48.8 TParam.AssignFieldValue	378
10.48.9 TParam.AssignFromField	379
10.48.10 TParam.Clear	379
10.48.11 TParam.GetData	379
10.48.12 TParam.GetDataSize	379
10.48.13 TParam.LoadFromFile	380
10.48.14 TParam.LoadFromStream	380
10.48.15 TParam.SetBlobData	380
10.48.16 TParam.SetData	380
10.48.17 TParam.AsBlob	381
10.48.18 TParam.AsBoolean	381

10.48.19	TPParam.AsCurrency	381
10.48.20	TPParam.AsDate	382
10.48.21	TPParam.AsDateTime	382
10.48.22	TPParam.AsFloat	382
10.48.23	TPParam.AsInteger	382
10.48.24	TPParam.AsLargeInt	383
10.48.25	TPParam.AsMemo	383
10.48.26	TPParam.AsSmallInt	383
10.48.27	TPParam.AsString	383
10.48.28	TPParam.AsTime	384
10.48.29	TPParam.AsWord	384
10.48.30	TPParam.AsFmtBCD	384
10.48.31	TPParam.Bound	384
10.48.32	TPParam.Dataset	385
10.48.33	TPParam.IsNull	385
10.48.34	TPParam.NativeStr	385
10.48.35	TPParam.Text	385
10.48.36	TPParam.Value	386
10.48.37	TPParam.AsWideString	386
10.48.38	TPParam.DataType	386
10.48.39	TPParam.Name	386
10.48.40	TPParam.NumericScale	387
10.48.41	TPParam.ParamType	387
10.48.42	TPParam.Precision	387
10.48.43	TPParam.Size	388
10.49	TParams	388
10.49.1	Description	388
10.49.2	Method overview	388
10.49.3	Property overview	389
10.49.4	TParams.Create	389
10.49.5	TParams.AddParam	389
10.49.6	TParams.AssignValues	389
10.49.7	TParams.CreateParam	389
10.49.8	TParams.FindParam	390
10.49.9	TParams.GetParamList	390
10.49.10	TParams.IsEqual	390
10.49.11	TParams.ParamByName	391
10.49.12	TParams.ParseSQL	391
10.49.13	TParams.RemoveParam	392
10.49.14	TParams.CopyParamValuesFromDataset	392

10.49.15	TParams.Dataset	392
10.49.16	TParams.Items	393
10.49.17	TParams.ParamValues	393
10.50	TSmallintField	393
10.50.1	Description	393
10.50.2	Method overview	393
10.50.3	TSmallintField.Create	394
10.51	TStringField	394
10.51.1	Description	394
10.51.2	Method overview	394
10.51.3	Property overview	394
10.51.4	TStringField.CheckTypeSize	394
10.51.5	TStringField.Create	394
10.51.6	TStringField.SetFieldType	395
10.51.7	TStringField.FixedChar	395
10.51.8	TStringField.Transliterate	395
10.51.9	TStringField.Value	395
10.51.10	TStringField.EditMask	396
10.51.11	TStringField.Size	396
10.52	TTimeField	396
10.52.1	Description	396
10.52.2	Method overview	396
10.52.3	TTimeField.Create	397
10.53	TVarBytesField	397
10.53.1	Description	397
10.53.2	Method overview	397
10.53.3	TVarBytesField.Create	397
10.54	TVariantField	397
10.54.1	Description	397
10.54.2	Method overview	398
10.54.3	TVariantField.CheckTypeSize	398
10.54.4	TVariantField.Create	398
10.55	TWideMemoField	398
10.55.1	Description	398
10.55.2	Method overview	398
10.55.3	Property overview	398
10.55.4	TWideMemoField.Create	399
10.55.5	TWideMemoField.Value	399
10.56	TWideStringField	399
10.56.1	Description	399

10.56.2 Method overview . . . . .	399
10.56.3 Property overview . . . . .	399
10.56.4 TWideStringField.CheckTypeSize . . . . .	400
10.56.5 TWideStringField.Create . . . . .	400
10.56.6 TWideStringField.SetFieldType . . . . .	400
10.56.7 TWideStringField.Value . . . . .	400
10.57 TWordField . . . . .	400
10.57.1 Description . . . . .	400
10.57.2 Method overview . . . . .	401
10.57.3 TWordField.Create . . . . .	401
<b>11 Reference for unit 'dbugintf'</b>	<b>402</b>
11.1 Overview . . . . .	402
11.2 Writing a debug server . . . . .	402
11.3 Constants, types and variables . . . . .	402
11.3.1 Resource strings . . . . .	402
11.3.2 Constants . . . . .	403
11.3.3 Types . . . . .	403
11.4 Procedures and functions . . . . .	403
11.4.1 GetDebuggingEnabled . . . . .	403
11.4.2 InitDebugClient . . . . .	404
11.4.3 SendBoolean . . . . .	404
11.4.4 SendDateTime . . . . .	404
11.4.5 SendDebug . . . . .	404
11.4.6 SendDebugEx . . . . .	405
11.4.7 SendDebugFmt . . . . .	405
11.4.8 SendDebugFmtEx . . . . .	405
11.4.9 SendInteger . . . . .	406
11.4.10 SendMethodEnter . . . . .	406
11.4.11 SendMethodExit . . . . .	406
11.4.12 SendPointer . . . . .	407
11.4.13 SendSeparator . . . . .	407
11.4.14 SetDebuggingEnabled . . . . .	407
11.4.15 StartDebugServer . . . . .	407
<b>12 Reference for unit 'dbugmsg'</b>	<b>409</b>
12.1 Used units . . . . .	409
12.2 Overview . . . . .	409
12.3 Constants, types and variables . . . . .	409
12.3.1 Constants . . . . .	409
12.3.2 Types . . . . .	410

12.4	Procedures and functions	410
12.4.1	DebugMessageName	410
12.4.2	ReadDebugMessageFromStream	410
12.4.3	WriteDebugMessageToStream	411
<b>13</b>	<b>Reference for unit 'eventlog'</b>	<b>412</b>
13.1	Used units	412
13.2	Overview	412
13.3	Constants, types and variables	412
13.3.1	Resource strings	412
13.3.2	Types	413
13.4	ELogError	413
13.4.1	Description	413
13.5	TEventLog	414
13.5.1	Description	414
13.5.2	Method overview	414
13.5.3	Property overview	414
13.5.4	TEventLog.Destroy	414
13.5.5	TEventLog.EventTypeToString	415
13.5.6	TEventLog.RegisterMessageFile	415
13.5.7	TEventLog.UnRegisterMessageFile	416
13.5.8	TEventLog.Log	416
13.5.9	TEventLog.Warning	416
13.5.10	TEventLog.Error	417
13.5.11	TEventLog.Debug	417
13.5.12	TEventLog.Info	417
13.5.13	TEventLog.AppendContent	417
13.5.14	TEventLog.Identification	418
13.5.15	TEventLog.LogType	418
13.5.16	TEventLog.Active	418
13.5.17	TEventLog.RaiseExceptionOnError	418
13.5.18	TEventLog.DefaultEventType	419
13.5.19	TEventLog.FileName	419
13.5.20	TEventLog.TimeStampFormat	419
13.5.21	TEventLog.CustomLogType	420
13.5.22	TEventLog.EventIDOffset	420
13.5.23	TEventLog.OnGetCustomCategory	420
13.5.24	TEventLog.OnGetCustomEventID	421
13.5.25	TEventLog.OnGetCustomEvent	421
<b>14</b>	<b>Reference for unit 'ezcgi'</b>	<b>422</b>

14.1	Used units	422
14.2	Overview	422
14.3	Constants, types and variables	422
14.3.1	Constants	422
14.4	ECGIException	422
14.4.1	Description	422
14.5	TEZcgi	423
14.5.1	Description	423
14.5.2	Method overview	423
14.5.3	Property overview	423
14.5.4	TEZcgi.Create	423
14.5.5	TEZcgi.Destroy	423
14.5.6	TEZcgi.Run	424
14.5.7	TEZcgi.WriteContent	424
14.5.8	TEZcgi.PutLine	424
14.5.9	TEZcgi.GetValue	425
14.5.10	TEZcgi.DoPost	425
14.5.11	TEZcgi.DoGet	425
14.5.12	TEZcgi.Values	425
14.5.13	TEZcgi.Names	426
14.5.14	TEZcgi.Variables	426
14.5.15	TEZcgi.VariableCount	427
14.5.16	TEZcgi.Name	427
14.5.17	TEZcgi.Email	427
<b>15</b>	<b>Reference for unit 'fpTimer'</b>	<b>428</b>
15.1	Used units	428
15.2	Overview	428
15.3	Constants, types and variables	428
15.3.1	Types	428
15.3.2	Variables	428
15.4	TFPCustomTimer	429
15.4.1	Description	429
15.4.2	Method overview	429
15.4.3	TFPCustomTimer.Create	429
15.4.4	TFPCustomTimer.Destroy	429
15.4.5	TFPCustomTimer.StartTimer	430
15.4.6	TFPCustomTimer.StopTimer	430
15.5	TFPTimer	430
15.5.1	Description	430

15.5.2	Property overview	430
15.5.3	TFPTimer.Enabled	430
15.5.4	TFPTimer.Interval	431
15.5.5	TFPTimer.OnTimer	431
15.6	TFPTimerDriver	431
15.6.1	Description	431
15.6.2	Method overview	431
15.6.3	Property overview	431
15.6.4	TFPTimerDriver.Create	432
15.6.5	TFPTimerDriver.StartTimer	432
15.6.6	TFPTimerDriver.StopTimer	432
15.6.7	TFPTimerDriver.Timer	432
<b>16</b>	<b>Reference for unit 'gettext'</b>	<b>433</b>
16.1	Used units	433
16.2	Overview	433
16.3	Constants, types and variables	433
16.3.1	Constants	433
16.3.2	Types	433
16.4	Procedures and functions	434
16.4.1	GetLanguageIDs	434
16.4.2	TranslateResourceStrings	435
16.4.3	TranslateUnitResourceStrings	435
16.5	EMOFileError	435
16.5.1	Description	435
16.6	TMOFile	435
16.6.1	Description	435
16.6.2	Method overview	436
16.6.3	TMOFile.Create	436
16.6.4	TMOFile.Destroy	436
16.6.5	TMOFile.Translate	436
<b>17</b>	<b>Reference for unit 'idea'</b>	<b>437</b>
17.1	Used units	437
17.2	Overview	437
17.3	Constants, types and variables	437
17.3.1	Constants	437
17.3.2	Types	438
17.4	Procedures and functions	438
17.4.1	CipherIdea	438
17.4.2	DeKeyIdea	438



17.4.3	EnKeyIdea	439
17.5	EIDEAError	439
17.5.1	Description	439
17.6	TIDEADeCryptStream	439
17.6.1	Description	439
17.6.2	Method overview	439
17.6.3	TIDEADeCryptStream.Create	440
17.6.4	TIDEADeCryptStream.Read	440
17.6.5	TIDEADeCryptStream.Seek	440
17.7	TIDEAEncryptStream	441
17.7.1	Description	441
17.7.2	Method overview	441
17.7.3	TIDEAEncryptStream.Create	441
17.7.4	TIDEAEncryptStream.Destroy	441
17.7.5	TIDEAEncryptStream.Write	442
17.7.6	TIDEAEncryptStream.Seek	442
17.7.7	TIDEAEncryptStream.Flush	442
17.8	TIDEAStream	442
17.8.1	Description	442
17.8.2	Method overview	443
17.8.3	Property overview	443
17.8.4	TIDEAStream.Create	443
17.8.5	TIDEAStream.Key	443
<b>18</b>	<b>Reference for unit 'inicol'</b>	<b>444</b>
18.1	Used units	444
18.2	Overview	444
18.3	Constants, types and variables	444
18.3.1	Constants	444
18.4	EIniCol	445
18.4.1	Description	445
18.5	TIniCollection	445
18.5.1	Description	445
18.5.2	Method overview	445
18.5.3	Property overview	445
18.5.4	TIniCollection.Load	445
18.5.5	TIniCollection.Save	446
18.5.6	TIniCollection.SaveToIni	446
18.5.7	TIniCollection.SaveToFile	446
18.5.8	TIniCollection.LoadFromIni	447

18.5.9	TIniCollection.LoadFromFile	447
18.5.10	TIniCollection.Prefix	447
18.5.11	TIniCollection.SectionPrefix	448
18.5.12	TIniCollection.FileName	448
18.5.13	TIniCollection.GlobalSection	448
18.6	TIniCollectionItem	449
18.6.1	Description	449
18.6.2	Method overview	449
18.6.3	Property overview	449
18.6.4	TIniCollectionItem.SaveToIni	449
18.6.5	TIniCollectionItem.LoadFromIni	449
18.6.6	TIniCollectionItem.SaveToFile	450
18.6.7	TIniCollectionItem.LoadFromFile	450
18.6.8	TIniCollectionItem.SectionName	450
18.7	TNamedIniCollection	451
18.7.1	Description	451
18.7.2	Method overview	451
18.7.3	Property overview	451
18.7.4	TNamedIniCollection.IndexOfUserData	451
18.7.5	TNamedIniCollection.IndexOfName	451
18.7.6	TNamedIniCollection.FindByName	452
18.7.7	TNamedIniCollection.FindByUserData	452
18.7.8	TNamedIniCollection.NamedItems	452
18.8	TNamedIniCollectionItem	452
18.8.1	Description	452
18.8.2	Property overview	452
18.8.3	TNamedIniCollectionItem.UserData	453
18.8.4	TNamedIniCollectionItem.Name	453
<b>19</b>	<b>Reference for unit 'IniFiles'</b>	<b>454</b>
19.1	Used units	454
19.2	Overview	454
19.3	TCustomIniFile	454
19.3.1	Description	454
19.3.2	Method overview	455
19.3.3	Property overview	455
19.3.4	TCustomIniFile.Create	455
19.3.5	TCustomIniFile.Destroy	456
19.3.6	TCustomIniFile.SectionExists	456
19.3.7	TCustomIniFile.ReadString	456

19.3.8	<a href="#">TCustomIniFile.WriteString</a>	457
19.3.9	<a href="#">TCustomIniFile.ReadInteger</a>	457
19.3.10	<a href="#">TCustomIniFile.WriteInteger</a>	457
19.3.11	<a href="#">TCustomIniFile.ReadBool</a>	457
19.3.12	<a href="#">TCustomIniFile.WriteBool</a>	458
19.3.13	<a href="#">TCustomIniFile.ReadDate</a>	458
19.3.14	<a href="#">TCustomIniFile.ReadDateTime</a>	458
19.3.15	<a href="#">TCustomIniFile.ReadFloat</a>	459
19.3.16	<a href="#">TCustomIniFile.ReadTime</a>	459
19.3.17	<a href="#">TCustomIniFile.ReadBinaryStream</a>	459
19.3.18	<a href="#">TCustomIniFile.WriteDate</a>	460
19.3.19	<a href="#">TCustomIniFile.WriteDateTime</a>	460
19.3.20	<a href="#">TCustomIniFile.WriteFloat</a>	460
19.3.21	<a href="#">TCustomIniFile.WriteTime</a>	460
19.3.22	<a href="#">TCustomIniFile.WriteBinaryStream</a>	461
19.3.23	<a href="#">TCustomIniFile.ReadSection</a>	461
19.3.24	<a href="#">TCustomIniFile.ReadSections</a>	461
19.3.25	<a href="#">TCustomIniFile.ReadSectionValues</a>	462
19.3.26	<a href="#">TCustomIniFile.EraseSection</a>	462
19.3.27	<a href="#">TCustomIniFile.DeleteKey</a>	462
19.3.28	<a href="#">TCustomIniFile.UpdateFile</a>	462
19.3.29	<a href="#">TCustomIniFile.ValueExists</a>	463
19.3.30	<a href="#">TCustomIniFile.FileName</a>	463
19.3.31	<a href="#">TCustomIniFile.EscapeLineFeeds</a>	463
19.3.32	<a href="#">TCustomIniFile.CaseSensitive</a>	463
19.3.33	<a href="#">TCustomIniFile.StripQuotes</a>	464
19.4	<a href="#">THashedStringList</a>	464
19.4.1	<a href="#">Description</a>	464
19.4.2	<a href="#">Method overview</a>	464
19.4.3	<a href="#">THashedStringList.Create</a>	464
19.4.4	<a href="#">THashedStringList.Destroy</a>	464
19.4.5	<a href="#">THashedStringList.IndexOf</a>	465
19.4.6	<a href="#">THashedStringList.IndexOfName</a>	465
19.5	<a href="#">TIniFile</a>	465
19.5.1	<a href="#">Description</a>	465
19.5.2	<a href="#">Method overview</a>	465
19.5.3	<a href="#">Property overview</a>	466
19.5.4	<a href="#">TIniFile.Create</a>	466
19.5.5	<a href="#">TIniFile.Destroy</a>	466
19.5.6	<a href="#">TIniFile.ReadString</a>	466

19.5.7	TIniFile.WriteString	467
19.5.8	TIniFile.ReadSection	467
19.5.9	TIniFile.ReadSectionRaw	467
19.5.10	TIniFile.ReadSections	467
19.5.11	TIniFile.ReadSectionValues	468
19.5.12	TIniFile.EraseSection	468
19.5.13	TIniFile.DeleteKey	468
19.5.14	TIniFile.UpdateFile	468
19.5.15	TIniFile.Stream	469
19.5.16	TIniFile.CacheUpdates	469
19.6	TIniFileKey	469
19.6.1	Description	469
19.6.2	Method overview	469
19.6.3	Property overview	469
19.6.4	TIniFileKey.Create	470
19.6.5	TIniFileKey.Ident	470
19.6.6	TIniFileKey.Value	470
19.7	TIniFileKeyList	470
19.7.1	Description	470
19.7.2	Method overview	470
19.7.3	Property overview	471
19.7.4	TIniFileKeyList.Destroy	471
19.7.5	TIniFileKeyList.Clear	471
19.7.6	TIniFileKeyList.Items	471
19.8	TIniFileSection	471
19.8.1	Description	471
19.8.2	Method overview	472
19.8.3	Property overview	472
19.8.4	TIniFileSection.Empty	472
19.8.5	TIniFileSection.Create	472
19.8.6	TIniFileSection.Destroy	472
19.8.7	TIniFileSection.Name	472
19.8.8	TIniFileSection.KeyList	473
19.9	TIniFileSectionList	473
19.9.1	Description	473
19.9.2	Method overview	473
19.9.3	Property overview	473
19.9.4	TIniFileSectionList.Destroy	473
19.9.5	TIniFileSectionList.Clear	474
19.9.6	TIniFileSectionList.Items	474

19.10 TMemIniFile . . . . .	474
19.10.1 Description . . . . .	474
19.10.2 Method overview . . . . .	474
19.10.3 TMemIniFile.Create . . . . .	474
19.10.4 TMemIniFile.Clear . . . . .	475
19.10.5 TMemIniFile.GetStrings . . . . .	475
19.10.6 TMemIniFile.Rename . . . . .	475
19.10.7 TMemIniFile.SetStrings . . . . .	475
<b>20 Reference for unit 'iostream' . . . . .</b>	<b>477</b>
20.1 Used units . . . . .	477
20.2 Overview . . . . .	477
20.3 Constants, types and variables . . . . .	477
20.3.1 Types . . . . .	477
20.4 EIOStreamError . . . . .	478
20.4.1 Description . . . . .	478
20.5 TIOStream . . . . .	478
20.5.1 Description . . . . .	478
20.5.2 Method overview . . . . .	478
20.5.3 TIOStream.Create . . . . .	478
20.5.4 TIOStream.Read . . . . .	478
20.5.5 TIOStream.Write . . . . .	479
20.5.6 TIOStream.Seek . . . . .	479
<b>21 Reference for unit 'libtar' . . . . .</b>	<b>480</b>
21.1 Used units . . . . .	480
21.2 Overview . . . . .	480
21.3 Constants, types and variables . . . . .	480
21.3.1 Constants . . . . .	480
21.3.2 Types . . . . .	481
21.4 Procedures and functions . . . . .	483
21.4.1 ClearDirRec . . . . .	483
21.4.2 ConvertFilename . . . . .	483
21.4.3 FileTimeGMT . . . . .	483
21.4.4 PermissionString . . . . .	483
21.5 TTarArchive . . . . .	484
21.5.1 Description . . . . .	484
21.5.2 Method overview . . . . .	484
21.5.3 TTarArchive.Create . . . . .	484
21.5.4 TTarArchive.Destroy . . . . .	484
21.5.5 TTarArchive.Reset . . . . .	484

21.5.6	<a href="#">TTarArchive.FindNext</a>	485
21.5.7	<a href="#">TTarArchive.ReadFile</a>	485
21.5.8	<a href="#">TTarArchive.GetFilePos</a>	485
21.5.9	<a href="#">TTarArchive.SetFilePos</a>	486
21.6	<a href="#">TTarWriter</a>	486
21.6.1	<a href="#">Description</a>	486
21.6.2	<a href="#">Method overview</a>	486
21.6.3	<a href="#">Property overview</a>	486
21.6.4	<a href="#">TTarWriter.Create</a>	486
21.6.5	<a href="#">TTarWriter.Destroy</a>	487
21.6.6	<a href="#">TTarWriter.AddFile</a>	487
21.6.7	<a href="#">TTarWriter.AddStream</a>	487
21.6.8	<a href="#">TTarWriter.AddString</a>	488
21.6.9	<a href="#">TTarWriter.AddDir</a>	488
21.6.10	<a href="#">TTarWriter.AddSymbolicLink</a>	488
21.6.11	<a href="#">TTarWriter.AddLink</a>	489
21.6.12	<a href="#">TTarWriter.AddVolumeHeader</a>	489
21.6.13	<a href="#">TTarWriter.Finalize</a>	489
21.6.14	<a href="#">TTarWriter.Permissions</a>	489
21.6.15	<a href="#">TTarWriter.UID</a>	490
21.6.16	<a href="#">TTarWriter.GID</a>	490
21.6.17	<a href="#">TTarWriter.UserName</a>	490
21.6.18	<a href="#">TTarWriter.GroupName</a>	490
21.6.19	<a href="#">TTarWriter.Mode</a>	491
21.6.20	<a href="#">TTarWriter.Magic</a>	491
<b>22</b>	<b><a href="#">Reference for unit 'Pipes'</a></b>	<b>492</b>
22.1	<a href="#">Used units</a>	492
22.2	<a href="#">Overview</a>	492
22.3	<a href="#">Constants, types and variables</a>	492
22.3.1	<a href="#">Constants</a>	492
22.4	<a href="#">Procedures and functions</a>	492
22.4.1	<a href="#">CreatePipeHandles</a>	492
22.4.2	<a href="#">CreatePipeStreams</a>	493
22.5	<a href="#">EPipeCreation</a>	493
22.5.1	<a href="#">Description</a>	493
22.6	<a href="#">EPipeError</a>	493
22.6.1	<a href="#">Description</a>	493
22.7	<a href="#">EPipeSeek</a>	493
22.7.1	<a href="#">Description</a>	493

22.8	TInputPipeStream . . . . .	493
22.8.1	Description . . . . .	493
22.8.2	Method overview . . . . .	494
22.8.3	Property overview . . . . .	494
22.8.4	TInputPipeStream.Write . . . . .	494
22.8.5	TInputPipeStream.Seek . . . . .	494
22.8.6	TInputPipeStream.Read . . . . .	495
22.8.7	TInputPipeStream.NumBytesAvailable . . . . .	495
22.9	TOutputPipeStream . . . . .	495
22.9.1	Description . . . . .	495
22.9.2	Method overview . . . . .	495
22.9.3	TOutputPipeStream.Seek . . . . .	495
22.9.4	TOutputPipeStream.Read . . . . .	496
<b>23</b>	<b>Reference for unit 'pooledmm'</b>	<b>497</b>
23.1	Used units . . . . .	497
23.2	Overview . . . . .	497
23.3	Constants, types and variables . . . . .	497
23.3.1	Types . . . . .	497
23.4	TNonFreePooledMemManager . . . . .	498
23.4.1	Description . . . . .	498
23.4.2	Method overview . . . . .	498
23.4.3	Property overview . . . . .	498
23.4.4	TNonFreePooledMemManager.Clear . . . . .	498
23.4.5	TNonFreePooledMemManager.Create . . . . .	498
23.4.6	TNonFreePooledMemManager.Destroy . . . . .	499
23.4.7	TNonFreePooledMemManager.NewItem . . . . .	499
23.4.8	TNonFreePooledMemManager.EnumerateItems . . . . .	499
23.4.9	TNonFreePooledMemManager.ItemSize . . . . .	499
23.5	TPooledMemManager . . . . .	500
23.5.1	Description . . . . .	500
23.5.2	Method overview . . . . .	500
23.5.3	Property overview . . . . .	500
23.5.4	TPooledMemManager.Clear . . . . .	500
23.5.5	TPooledMemManager.Create . . . . .	500
23.5.6	TPooledMemManager.Destroy . . . . .	501
23.5.7	TPooledMemManager.MinimumFreeCount . . . . .	501
23.5.8	TPooledMemManager.MaximumFreeCountRatio . . . . .	501
23.5.9	TPooledMemManager.Count . . . . .	501
23.5.10	TPooledMemManager.FreeCount . . . . .	502

23.5.11 TPooledMemManager.AllocatedCount . . . . .	502
23.5.12 TPooledMemManager.FreedCount . . . . .	502
<b>24 Reference for unit 'process' . . . . .</b>	<b>503</b>
24.1 Used units . . . . .	503
24.2 Overview . . . . .	503
24.3 Constants, types and variables . . . . .	503
24.3.1 Types . . . . .	503
24.3.2 Variables . . . . .	505
24.4 Procedures and functions . . . . .	506
24.4.1 CommandToList . . . . .	506
24.4.2 DetectXTerm . . . . .	506
24.5 EProcess . . . . .	506
24.5.1 Description . . . . .	506
24.6 TProcess . . . . .	506
24.6.1 Description . . . . .	506
24.6.2 Method overview . . . . .	507
24.6.3 Property overview . . . . .	508
24.6.4 TProcess.Create . . . . .	508
24.6.5 TProcess.Destroy . . . . .	509
24.6.6 TProcess.Execute . . . . .	509
24.6.7 TProcess.CloseInput . . . . .	509
24.6.8 TProcess.CloseOutput . . . . .	510
24.6.9 TProcess.CloseStderr . . . . .	510
24.6.10 TProcess.Resume . . . . .	510
24.6.11 TProcess.Suspend . . . . .	510
24.6.12 TProcess.Terminate . . . . .	511
24.6.13 TProcess.WaitOnExit . . . . .	511
24.6.14 TProcess.WindowRect . . . . .	511
24.6.15 TProcess.Handle . . . . .	511
24.6.16 TProcess.ProcessHandle . . . . .	512
24.6.17 TProcess.ThreadHandle . . . . .	512
24.6.18 TProcess.ProcessID . . . . .	512
24.6.19 TProcess.ThreadID . . . . .	513
24.6.20 TProcess.Input . . . . .	513
24.6.21 TProcess.Output . . . . .	513
24.6.22 TProcess.Stderr . . . . .	514
24.6.23 TProcess.ExitStatus . . . . .	514
24.6.24 TProcess.InheritHandles . . . . .	514
24.6.25 TProcess.OnForkEvent . . . . .	515



24.6.26 TProcess.Active . . . . .	515
24.6.27 TProcess.ApplicationName . . . . .	515
24.6.28 TProcess.CommandLine . . . . .	515
24.6.29 TProcess.Executable . . . . .	516
24.6.30 TProcess.Parameters . . . . .	516
24.6.31 TProcess.ConsoleTitle . . . . .	517
24.6.32 TProcess.CurrentDirectory . . . . .	517
24.6.33 TProcess.Desktop . . . . .	518
24.6.34 TProcess.Environment . . . . .	518
24.6.35 TProcess.Options . . . . .	518
24.6.36 TProcess.Priority . . . . .	519
24.6.37 TProcess.StartupOptions . . . . .	520
24.6.38 TProcess.Running . . . . .	520
24.6.39 TProcess.ShowWindow . . . . .	520
24.6.40 TProcess.WindowColumns . . . . .	521
24.6.41 TProcess.WindowHeight . . . . .	521
24.6.42 TProcess.WindowLeft . . . . .	522
24.6.43 TProcess.WindowRows . . . . .	522
24.6.44 TProcess.WindowTop . . . . .	522
24.6.45 TProcess.WindowWidth . . . . .	522
24.6.46 TProcess.FillAttribute . . . . .	523
24.6.47 TProcess.XTermProgram . . . . .	523
<b>25 Reference for unit 'rttiutils'</b>	<b>524</b>
25.1 Used units . . . . .	524
25.2 Overview . . . . .	524
25.3 Constants, types and variables . . . . .	524
25.3.1 Constants . . . . .	524
25.3.2 Types . . . . .	524
25.3.3 Variables . . . . .	525
25.4 Procedures and functions . . . . .	525
25.4.1 CreateStoredItem . . . . .	525
25.4.2 ParseStoredItem . . . . .	526
25.4.3 UpdateStoredList . . . . .	526
25.5 TPropInfoList . . . . .	526
25.5.1 Description . . . . .	526
25.5.2 Method overview . . . . .	527
25.5.3 Property overview . . . . .	527
25.5.4 TPropInfoList.Create . . . . .	527
25.5.5 TPropInfoList.Destroy . . . . .	527

25.5.6	TPropInfoList.Contains	527
25.5.7	TPropInfoList.Find	528
25.5.8	TPropInfoList.Delete	528
25.5.9	TPropInfoList.Intersect	528
25.5.10	TPropInfoList.Count	528
25.5.11	TPropInfoList.Items	529
25.6	TPropsStorage	529
25.6.1	Description	529
25.6.2	Method overview	529
25.6.3	Property overview	529
25.6.4	TPropsStorage.StoreAnyProperty	529
25.6.5	TPropsStorage.LoadAnyProperty	530
25.6.6	TPropsStorage.StoreProperties	530
25.6.7	TPropsStorage.LoadProperties	530
25.6.8	TPropsStorage.LoadObjectsProps	531
25.6.9	TPropsStorage.StoreObjectsProps	531
25.6.10	TPropsStorage.AObject	532
25.6.11	TPropsStorage.Prefix	532
25.6.12	TPropsStorage.Section	532
25.6.13	TPropsStorage.OnReadString	533
25.6.14	TPropsStorage.OnWriteString	533
25.6.15	TPropsStorage.OnEraseSection	533
<b>26</b>	<b>Reference for unit 'simpleipc'</b>	<b>534</b>
26.1	Used units	534
26.2	Overview	534
26.3	Constants, types and variables	534
26.3.1	Resource strings	534
26.3.2	Constants	535
26.3.3	Types	535
26.3.4	Variables	536
26.4	EIPCErrors	536
26.4.1	Description	536
26.5	TIPCCClientComm	536
26.5.1	Description	536
26.5.2	Method overview	536
26.5.3	Property overview	536
26.5.4	TIPCCClientComm.Create	537
26.5.5	TIPCCClientComm.Connect	537
26.5.6	TIPCCClientComm.Disconnect	537

26.5.7	TIPCClientComm.ServerRunning	538
26.5.8	TIPCClientComm.SendMessage	538
26.5.9	TIPCClientComm.Owner	538
26.6	TIPCServerComm	538
26.6.1	Description	538
26.6.2	Method overview	539
26.6.3	Property overview	539
26.6.4	TIPCServerComm.Create	539
26.6.5	TIPCServerComm.StartServer	539
26.6.6	TIPCServerComm.StopServer	539
26.6.7	TIPCServerComm.PeekMessage	540
26.6.8	TIPCServerComm.ReadMessage	540
26.6.9	TIPCServerComm.Owner	540
26.6.10	TIPCServerComm.InstanceID	541
26.7	TSimpleIPC	541
26.7.1	Description	541
26.7.2	Property overview	541
26.7.3	TSimpleIPC.Active	541
26.7.4	TSimpleIPC.ServerID	541
26.8	TSimpleIPCClient	542
26.8.1	Description	542
26.8.2	Method overview	542
26.8.3	Property overview	542
26.8.4	TSimpleIPCClient.Create	542
26.8.5	TSimpleIPCClient.Destroy	542
26.8.6	TSimpleIPCClient.Connect	543
26.8.7	TSimpleIPCClient.Disconnect	543
26.8.8	TSimpleIPCClient.ServerRunning	543
26.8.9	TSimpleIPCClient.SendMessage	544
26.8.10	TSimpleIPCClient.SendStringMessage	544
26.8.11	TSimpleIPCClient.SendStringMessageFmt	544
26.8.12	TSimpleIPCClient.ServerInstance	544
26.9	TSimpleIPCServer	545
26.9.1	Description	545
26.9.2	Method overview	545
26.9.3	Property overview	545
26.9.4	TSimpleIPCServer.Create	545
26.9.5	TSimpleIPCServer.Destroy	546
26.9.6	TSimpleIPCServer.StartServer	546
26.9.7	TSimpleIPCServer.StopServer	546

26.9.8	<a href="#">TSimpleIPCServer.PeekMessage</a>	546
26.9.9	<a href="#">TSimpleIPCServer.GetMessageData</a>	547
26.9.10	<a href="#">TSimpleIPCServer.StringMessage</a>	547
26.9.11	<a href="#">TSimpleIPCServer.MsgType</a>	547
26.9.12	<a href="#">TSimpleIPCServer.MsgData</a>	548
26.9.13	<a href="#">TSimpleIPCServer.InstanceID</a>	548
26.9.14	<a href="#">TSimpleIPCServer.Global</a>	548
26.9.15	<a href="#">TSimpleIPCServer.OnMessage</a>	548
<b>27</b>	<b>Reference for unit 'streamcoll'</b>	<b>549</b>
27.1	<a href="#">Used units</a>	549
27.2	<a href="#">Overview</a>	549
27.3	<a href="#">Procedures and functions</a>	549
27.3.1	<a href="#">ColReadBoolean</a>	549
27.3.2	<a href="#">ColReadCurrency</a>	550
27.3.3	<a href="#">ColReadDateTime</a>	550
27.3.4	<a href="#">ColReadFloat</a>	550
27.3.5	<a href="#">ColReadInteger</a>	550
27.3.6	<a href="#">ColReadString</a>	551
27.3.7	<a href="#">ColWriteBoolean</a>	551
27.3.8	<a href="#">ColWriteCurrency</a>	551
27.3.9	<a href="#">ColWriteDateTime</a>	551
27.3.10	<a href="#">ColWriteFloat</a>	552
27.3.11	<a href="#">ColWriteInteger</a>	552
27.3.12	<a href="#">ColWriteString</a>	552
27.4	<a href="#">EStreamColl</a>	552
27.4.1	<a href="#">Description</a>	552
27.5	<a href="#">TStreamCollection</a>	552
27.5.1	<a href="#">Description</a>	552
27.5.2	<a href="#">Method overview</a>	553
27.5.3	<a href="#">Property overview</a>	553
27.5.4	<a href="#">TStreamCollection.LoadFromStream</a>	553
27.5.5	<a href="#">TStreamCollection.SaveToStream</a>	553
27.5.6	<a href="#">TStreamCollection.Streaming</a>	553
27.6	<a href="#">TStreamCollectionItem</a>	554
27.6.1	<a href="#">Description</a>	554
<b>28</b>	<b>Reference for unit 'streamex'</b>	<b>555</b>
28.1	<a href="#">Used units</a>	555
28.2	<a href="#">Overview</a>	555
28.3	<a href="#">TBidirBinaryObjectReader</a>	555

28.3.1	Description	555
28.3.2	Property overview	555
28.3.3	TBidirBinaryObjectReader.Position	555
28.4	TBidirBinaryObjectWriter	556
28.4.1	Description	556
28.4.2	Property overview	556
28.4.3	TBidirBinaryObjectWriter.Position	556
28.5	TDelphiReader	556
28.5.1	Description	556
28.5.2	Method overview	556
28.5.3	Property overview	557
28.5.4	TDelphiReader.GetDriver	557
28.5.5	TDelphiReader.ReadStr	557
28.5.6	TDelphiReader.Read	557
28.5.7	TDelphiReader.Position	557
28.6	TDelphiWriter	558
28.6.1	Description	558
28.6.2	Method overview	558
28.6.3	Property overview	558
28.6.4	TDelphiWriter.GetDriver	558
28.6.5	TDelphiWriter.FlushBuffer	558
28.6.6	TDelphiWriter.Write	558
28.6.7	TDelphiWriter.WriteStr	559
28.6.8	TDelphiWriter.WriteValue	559
28.6.9	TDelphiWriter.Position	559
<b>29</b>	<b>Reference for unit 'StreamIO'</b>	<b>560</b>
29.1	Used units	560
29.2	Overview	560
29.3	Procedures and functions	560
29.3.1	AssignStream	560
29.3.2	GetStream	561
<b>30</b>	<b>Reference for unit 'syncobjs'</b>	<b>562</b>
30.1	Used units	562
30.2	Overview	562
30.3	Constants, types and variables	562
30.3.1	Constants	562
30.3.2	Types	562
30.4	TCriticalSection	563
30.4.1	Description	563

30.4.2	Method overview	563
30.4.3	TCriticalSection.Acquire	564
30.4.4	TCriticalSection.Release	564
30.4.5	TCriticalSection.Enter	564
30.4.6	TCriticalSection.TryEnter	564
30.4.7	TCriticalSection.Leave	565
30.4.8	TCriticalSection.Create	565
30.4.9	TCriticalSection.Destroy	565
30.5	TEventObject	565
30.5.1	Description	565
30.5.2	Method overview	566
30.5.3	Property overview	566
30.5.4	TEventObject.Create	566
30.5.5	TEventObject.destroy	566
30.5.6	TEventObject.ResetEvent	566
30.5.7	TEventObject.SetEvent	567
30.5.8	TEventObject.WaitFor	567
30.5.9	TEventObject.ManualReset	567
30.6	THandleObject	567
30.6.1	Description	567
30.6.2	Method overview	568
30.6.3	Property overview	568
30.6.4	THandleObject.destroy	568
30.6.5	THandleObject.Handle	568
30.6.6	THandleObject.LastError	568
30.7	TSimpleEvent	568
30.7.1	Description	568
30.7.2	Method overview	569
30.7.3	TSimpleEvent.Create	569
30.8	TSynchroObject	569
30.8.1	Description	569
30.8.2	Method overview	569
30.8.3	TSynchroObject.Acquire	569
30.8.4	TSynchroObject.Release	569
<b>31</b>	<b>Reference for unit 'URIParser'</b>	<b>571</b>
31.1	Overview	571
31.2	Constants, types and variables	571
31.2.1	Types	571
31.3	Procedures and functions	571

31.3.1	EncodeURI	571
31.3.2	FilenameToURI	572
31.3.3	IsAbsoluteURI	572
31.3.4	ParseURI	572
31.3.5	ResolveRelativeURI	573
31.3.6	URIToFilename	573
<b>32</b>	<b>Reference for unit 'zstream'</b>	<b>574</b>
32.1	Used units	574
32.2	Overview	574
32.3	Constants, types and variables	574
32.3.1	Types	574
32.4	Ecompressionerror	575
32.4.1	Description	575
32.5	Edecompressionerror	575
32.5.1	Description	575
32.6	Egzfileerror	575
32.6.1	Description	575
32.7	Ezliberror	575
32.7.1	Description	575
32.8	Tcompressionstream	575
32.8.1	Description	575
32.8.2	Method overview	576
32.8.3	Tcompressionstream.create	576
32.8.4	Tcompressionstream.destroy	576
32.8.5	Tcompressionstream.write	576
32.8.6	Tcompressionstream.flush	577
32.8.7	Tcompressionstream.get_compressionrate	577
32.9	Tcustomzlibstream	577
32.9.1	Description	577
32.9.2	Method overview	577
32.9.3	Tcustomzlibstream.create	577
32.9.4	Tcustomzlibstream.destroy	578
32.10	Tdecompressionstream	578
32.10.1	Description	578
32.10.2	Method overview	578
32.10.3	Tdecompressionstream.create	578
32.10.4	Tdecompressionstream.destroy	579
32.10.5	Tdecompressionstream.read	579
32.10.6	Tdecompressionstream.seek	579

32.10.7 Tdecompressionstream.get_compressionrate . . . . .	580
32.11 TGZFileStream . . . . .	580
32.11.1 Description . . . . .	580
32.11.2 Method overview . . . . .	580
32.11.3 TGZFileStream.create . . . . .	580
32.11.4 TGZFileStream.read . . . . .	581
32.11.5 TGZFileStream.write . . . . .	581
32.11.6 TGZFileStream.seek . . . . .	581
32.11.7 TGZFileStream.destroy . . . . .	582



## About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the FCL (Free Component Library).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

**Declaration** The exact declaration of the function.

**Description** What does the procedure exactly do ?

**Errors** What errors can occur.

**See Also** Cross references to other related functions/commands.

## 0.1 Overview

The Free Component Library is a series of units that implement various classes and non-visual components for use with Free Pascal. They are building blocks for non-visual and visual programs, such as designed in Lazarus.

The `TDataSet` descendents have been implemented in a way that makes them compatible to the Delphi implementation of these units. There are other units that have counterparts in Delphi, but most of them are unique to Free Pascal.

# Chapter 1

## Reference for unit 'ascii85'

### 1.1 Used units

Table 1.1: Used units by unit 'ascii85'

Name	Page
Classes	??
System	??
sysutils	??

### 1.2 Overview

The `ascii85` provides an ASCII 85 or base 85 decoding algorithm. It is class and stream based: the `TASCII85DecoderStream` ([58](#)) stream can be used to decode any stream with ASCII85 encoded data.

Currently, no ASCII85 encoder stream is available.

It's usage and purpose is similar to the `IDEA` ([437](#)) or `base64` ([79](#)) units.

### 1.3 Constants, types and variables

#### 1.3.1 Types

```
TASCII85State = (ascInitial, ascOneEncodedChar, ascTwoEncodedChars,  
                 ascThreeEncodedChars, ascFourEncodedChars,  
                 ascNoEncodedChar, ascPrefix)
```

Table 1.2: Enumeration values for type TASCII85State

Value	Explanation
ascFourEncodedChars	Four encoded characters in buffer.
ascInitial	Initial state
ascNoEncodedChar	No encoded characters in buffer.
ascOneEncodedChar	One encoded character in buffer.
ascPrefix	Prefix processing
ascThreeEncodedChars	Three encoded characters in buffer.
ascTwoEncodedChars	Two encoded characters in buffer.

TASCII85State is for internal use, it contains the current state of the decoder.

## 1.4 TASCII85DecoderStream

### 1.4.1 Description

TASCII85DecoderStream is a read-only stream: it takes an input stream with ASCII 85 encoded data, and decodes the data as it is read. To this end, it overrides the TStream.Read (??) method.

The stream cannot be written to, trying to write to the stream will result in an exception.

### 1.4.2 Method overview

Page	Property	Description
<a href="#">59</a>	Close	Close decoder
<a href="#">59</a>	ClosedP	Check if the state is correct
<a href="#">58</a>	Create	Create new ASCII 85 decoder stream
<a href="#">59</a>	Decode	Decode source byte
<a href="#">59</a>	Destroy	Clean up instance
<a href="#">60</a>	Read	Read data from stream
<a href="#">60</a>	Seek	Set stream position

### 1.4.3 Property overview

Page	Property	Access	Description
<a href="#">60</a>	BExpectBoundary	rw	Expect character

### 1.4.4 TASCII85DecoderStream.Create

Synopsis: Create new ASCII 85 decoder stream

Declaration: constructor Create(aStream: TStream)

Visibility: published

Description: Create instantiates a new TASCII85DecoderStream instance, and sets aStream as the source stream.

See also: TASCII85DecoderStream.Destroy (??)

### 1.4.5 TASCII85DecoderStream.Decode

Synopsis: Decode source byte

Declaration: `procedure Decode(aInput: Byte)`

Visibility: published

Description: `Decode` decodes a source byte, and transfers it to the buffer. It is an internal routine and should not be used directly.

See also: `TASCII85DecoderStream.Close` (??)

### 1.4.6 TASCII85DecoderStream.Close

Synopsis: Close decoder

Declaration: `procedure Close`

Visibility: published

Description: `Close` closes the decoder mechanism: it checks if all data was read and performs a check to see whether all input data was consumed.

Errors: If the input stream was invalid, an `EConvertError` exception is raised.

See also: `TASCII85DecoderStream.ClosedP` (??), `TASCII85DecoderStream.Read` (??), `TASCII85DecoderStream.Destroy` (??)

### 1.4.7 TASCII85DecoderStream.ClosedP

Synopsis: Check if the state is correct

Declaration: `function ClosedP : Boolean`

Visibility: published

Description: `ClosedP` checks if the decoder state is one of `ascInitial`, `ascNoEncodedChar`, `ascPrefix`, and returns `True` if it is.

See also: `TASCII85DecoderStream.Close` (??), `TASCII85DecoderStream.BExpectBoundary` (??)

### 1.4.8 TASCII85DecoderStream.Destroy

Synopsis: Clean up instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` closes the input stream using `Close` (??) and cleans up the `TASCII85DecoderStream` instance from memory.

Errors: In case the input stream was invalid, an exception may occur.

See also: `TASCII85DecoderStream.Close` (??)

### 1.4.9 TASCII85DecoderStream.Read

Synopsis: Read data from stream

Declaration: `function Read(var aBuffer;aCount: LongInt) : LongInt; Override`

Visibility: public

Description: Read attempts to read `aCount` bytes from the stream and places them in `aBuffer`. It reads only as much data as is available. The actual number of read bytes is returned.

The read method reads as much data from the input stream as needed to get to `aCount` bytes, in general this will be `aCount*5/4` bytes.

### 1.4.10 TASCII85DecoderStream.Seek

Synopsis: Set stream position

Declaration: `function Seek(aOffset: LongInt;aOrigin: Word) : LongInt; Override`  
`function Seek(const aOffset: Int64;aOrigin: TSeekOrigin) : Int64`  
`; Override; Overload`

Visibility: public

Description: Seek sets the stream position. It only allows to set the position to the current position of this file, and returns then the current position. All other arguments will result in an `EReadError` exception.

Errors: In case the arguments are different from `soCurrent` and 0, an `EReadError` exception will be raised.

See also: `TASCII85DecoderStream.Read` (??)

### 1.4.11 TASCII85DecoderStream.BExpectBoundary

Synopsis: Expect character

Declaration: `Property BExpectBoundary : Boolean`

Visibility: published

Access: Read,Write

Description: `BExpectBoundary` is `True` if a encoded data boundary is to be expected ("`>`").

See also: `ClosedP` (??)

## 1.5 TASCII85EncoderStream

### 1.5.1 Description

`TASCII85EncoderStream` is the counterpart to the `TASCII85DecoderStream` (58) decoder stream: what `TASCII85EncoderStream` encodes, can be decoded by `TASCII85DecoderStream` (58).

The encoder stream works using a destination stream: whatever data is written to the encoder stream is encoded and written to the destination stream. The stream must be passed on in the constructor.

Note that all encoded data is only written to the destination stream when the encoder stream is destroyed.

See also: `TASCII85EncoderStream.create` (??), `TASCII85DecoderStream` (58)

### 1.5.2 Method overview

Page	Property	Description
<a href="#">61</a>	Create	Create a new instance of <code>TASCII85EncoderStream</code>
<a href="#">61</a>	Destroy	Flushed the data to the output stream and cleans up the encoder instance.
<a href="#">61</a>	Write	Write data encoded to the destination stream

### 1.5.3 Property overview

Page	Property	Access	Description
<a href="#">62</a>	Boundary	r	Is a boundary delineator written before and after the data
<a href="#">62</a>	Width	r	Width of the lines written to the data stream

### 1.5.4 TASCII85EncoderStream.Create

Synopsis: Create a new instance of `TASCII85EncoderStream`

Declaration: `constructor Create(ADest: TStream; AWidth: Integer; ABoundary: Boolean)`

Visibility: `public`

Description: `Create` creates a new instance of `TASCII85EncoderStream`. It stores `ADest` as the destination stream for the encoded data. The `Width` parameter indicates the width of the lines that are written by the encoder: after this amount of characters, a linefeed is put in the data stream. If `ABoundary` is `True` then a boundary delineator is written to the stream before and after the data.

See also: `TASCII85EncoderStream` ([60](#)), `Width` ([??](#)), `Boundary` ([??](#))

### 1.5.5 TASCII85EncoderStream.Destroy

Synopsis: Flushed the data to the output stream and cleans up the encoder instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` writes the data remaining in the internal buffer to the destination stream (possibly followed by a boundary delineator) and then destroys the encoder instance.

See also: `TASCII85EncoderStream.Write` ([??](#)), `TASCII85EncoderStream.Boundary` ([??](#))

### 1.5.6 TASCII85EncoderStream.Write

Synopsis: Write data encoded to the destination stream

Declaration: `function Write(const aBuffer; aCount: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` encodes the `aCount` bytes of data in `aBuffer` and writes the encoded data to the destination stream.

Not all data is written immediately to the destination stream. Only after the encoding stream is destroyed will the destination stream contain the full data.

See also: `TASCII85EncoderStream.Destroy` ([??](#))

### 1.5.7 TASCII85EncoderStream.Width

Synopsis: Width of the lines written to the data stream

Declaration: `Property Width : Integer`

Visibility: `public`

Access: `Read`

Description: `Width` is the width of the lines of encoded data written to the stream. After `Width` lines, a line ending will be written to the stream. The value is passed to the constructor and cannot be changed afterwards.

See also: `Boundary (??)`, `Create (??)`

### 1.5.8 TASCII85EncoderStream.Boundary

Synopsis: Is a boundary delineator written before and after the data

Declaration: `Property Boundary : Boolean`

Visibility: `public`

Access: `Read`

Description: `Boundary` indicates whether the stream will write a boundary delineator before and after the encoded data. It is passed to the constructor and cannot be changed.

See also: `Width (??)`, `Create (??)`

## 1.6 TASCII85RingBuffer

### 1.6.1 Description

`TASCII85RingBuffer` is an internal buffer class: it maintains a memory buffer of 1Kb, for faster reading of the stream. It should not be necessary to instantiate an instance of this class, the `TASCII85DecoderStream` ([58](#)) decoder stream will create an instance of this class automatically.

See also: `TASCII85DecoderStream` ([58](#))

### 1.6.2 Method overview

Page	Property	Description
<a href="#">63</a>	<code>Read</code>	Read data from the internal buffer
<a href="#">63</a>	<code>Write</code>	Write data to the internal buffer

### 1.6.3 Property overview

Page	Property	Access	Description
<a href="#">63</a>	<code>FillCount</code>	<code>r</code>	Number of bytes in buffer
<a href="#">63</a>	<code>Size</code>	<code>r</code>	Size of buffer

### 1.6.4 TASCII85RingBuffer.Write

Synopsis: Write data to the internal buffer

Declaration: `procedure Write(const aBuffer; aSize: Cardinal)`

Visibility: published

Description: `Write` writes `aSize` bytes from `aBuffer` to the internal memory buffer. Only as much bytes are written as will fit in the buffer.

See also: `TASCII85RingBuffer.FillCount` (??), `TASCII85RingBuffer.Read` (??), `TASCII85RingBuffer.Size` (??)

### 1.6.5 TASCII85RingBuffer.Read

Synopsis: Read data from the internal buffer

Declaration: `function Read(var aBuffer; aSize: Cardinal) : Cardinal`

Visibility: published

Description: `Read` will read `aSize` bytes from the internal buffer and writes them to `aBuffer`. If not enough bytes are available, only as much bytes as available will be written. The function returns the number of bytes transferred.

See also: `TASCII85RingBuffer.FillCount` (??), `TASCII85RingBuffer.Write` (??), `TASCII85RingBuffer.Size` (??)

### 1.6.6 TASCII85RingBuffer.FillCount

Synopsis: Number of bytes in buffer

Declaration: `Property FillCount : Cardinal`

Visibility: published

Access: Read

Description: `FillCount` is the available amount of bytes in the buffer.

See also: `TASCII85RingBuffer.Write` (??), `TASCII85RingBuffer.Read` (??), `TASCII85RingBuffer.Size` (??)

### 1.6.7 TASCII85RingBuffer.Size

Synopsis: Size of buffer

Declaration: `Property Size : Cardinal`

Visibility: published

Access: Read

Description: `Size` is the total size of the memory buffer. This is currently hardcoded to 1024Kb.

See also: `TASCII85RingBuffer.FillCount` (??)



## Chapter 2

# Reference for unit 'AVL\_Tree'

### 2.1 Used units

Table 2.1: Used units by unit 'AVL\_Tree'

Name	Page
Classes	??
System	??
sysutils	??

### 2.2 Overview

The `avl_tree` unit implements a general-purpose AVL (balanced) tree class: the `TAVLTree` (64) class and it's associated data node class `TAVLTreeNode` (73).

### 2.3 TAVLTree

#### 2.3.1 Description

`TAVLTree` maintains a balanced AVL tree. The tree consists of `TAVLTreeNode` (73) nodes, each of which has a `Data` pointer associated with it. The `TAVLTree` component offers methods to balance and search the tree.

By default, the list is searched with a simple pointer comparison algorithm, but a custom search mechanism can be specified in the `OnCompare` (??) property.

See also: `TAVLTreeNode` (73)

### 2.3.2 Method overview

Page	Property	Description
69	Add	Add a new node to the tree
70	Clear	Clears the tree
71	ConsistencyCheck	Check the consistency of the tree
72	Create	Create a new instance of <code>TAVLTree</code>
69	Delete	Delete a node from the tree
72	Destroy	Destroy the <code>TAVLTree</code> instance
65	Find	Find a data item in the tree.
67	FindHighest	Find the highest (rightmost) node in the tree.
66	FindKey	Find a data item in the tree using alternate compare mechanism
67	FindLeftMost	Find the node most left to a specified data node
68	FindLeftMostKey	Find the node most left to a specified key node
68	FindLeftMostSameKey	Find the node most left to a specified node with the same data
66	FindLowest	Find the lowest (leftmost) node in the tree.
67	FindNearest	Find the node closest to the data in the tree
67	FindPointer	Search for a data pointer
66	FindPrecessor	
68	FindRightMost	Find the node most right to a specified node
68	FindRightMostKey	Find the node most right to a specified key node
69	FindRightMostSameKey	Find the node most right of a specified node with the same data
66	FindSuccessor	Find successor to node
71	FreeAndClear	Clears the tree and frees nodes
71	FreeAndDelete	Delete a node from the tree and destroy it
73	GetEnumerator	Get an enumerator for the tree.
70	MoveDataLeftMost	Move data to the nearest left element
70	MoveDataRightMost	Move data to the nearest right element
69	Remove	Remove a data item from the list.
70	RemovePointer	Remove a pointer item from the list.
72	ReportAsString	Return the tree report as a string
72	SetNodeManager	Set the node instance manager to use
71	WriteReportToStream	Write the contents of the tree consistency check to the stream

### 2.3.3 Property overview

Page	Property	Access	Description
73	Count	r	Number of nodes in the tree.
73	OnCompare	rw	Compare function used when comparing nodes

### 2.3.4 TAVLTree.Find

Synopsis: Find a data item in the tree.

Declaration: `function Find(Data: Pointer) : TAVLTreeNode`

Visibility: `public`

Description: `Find` uses the default `OnCompare` (??) comparing function to find the `Data` pointer in the tree. It returns the `TAVLTreeNode` instance that results in a successful compare with the `Data` pointer, or `Nil` if none is found.

The default `OnCompare` function compares the actual pointers, which means that by default `Find` will give the same result as `FindPointer` (??).

See also: OnCompare (??), FindKey (??)

### 2.3.5 TAVLTree.FindKey

Synopsis: Find a data item in the tree using alternate compare mechanism

Declaration: `function FindKey(Key: Pointer; OnCompareKeyWithData: TListSortCompare)  
: TAVLTreeNode`

Visibility: public

Description: `FindKey` uses the specified `OnCompareKeyWithData` comparing function to find the `Key` pointer in the tree. It returns the `TAVLTreeNode` instance that matches the `Data` pointer, or `Nil` if none is found.

See also: OnCompare (??), Find (??)

### 2.3.6 TAVLTree.FindSuccessor

Synopsis: Find successor to node

Declaration: `function FindSuccessor(ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindSuccessor` returns the successor to `ANode`: this is the leftmost node in the right subtree, or the leftmost node above the node `ANode`. This can of course be `Nil`.

This method is used when a node must be inserted at the rightmost position.

See also: `TAVLTree.FindPrecessor (??)`, `TAVLTree.MoveDataRightMost (??)`

### 2.3.7 TAVLTree.FindPrecessor

Synopsis:

Declaration: `function FindPrecessor(ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindPrecessor` returns the successor to `ANode`: this is the rightmost node in the left subtree, or the rightmost node above the node `ANode`. This can of course be `Nil`.

This method is used when a node must be inserted at the leftmost position.

See also: `TAVLTree.FindSuccessor (??)`, `TAVLTree.MoveDataLeftMost (??)`

### 2.3.8 TAVLTree.FindLowest

Synopsis: Find the lowest (leftmost) node in the tree.

Declaration: `function FindLowest : TAVLTreeNode`

Visibility: public

Description: `FindLowest` returns the leftmost node in the tree, i.e. the node which is reached when descending from the rootnode via the left (??) subtrees.

See also: `FindHighest (??)`

### 2.3.9 TAVLTree.FindHighest

Synopsis: Find the highest (rightmost) node in the tree.

Declaration: `function FindHighest : TAVLTreeNode`

Visibility: public

Description: `FindHighest` returns the rightmost node in the tree, i.e. the node which is reached when descending from the rootnode via the Right (??) subtrees.

See also: `FindLowest (??)`

### 2.3.10 TAVLTree.FindNearest

Synopsis: Find the node closest to the data in the tree

Declaration: `function FindNearest(Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindNearest` searches the node in the data tree that is closest to the specified `Data`. If `Data` appears in the tree, then its node is returned.

See also: `FindHighest (??)`, `FindLowest (??)`, `Find (??)`, `FindKey (??)`

### 2.3.11 TAVLTree.FindPointer

Synopsis: Search for a data pointer

Declaration: `function FindPointer(Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindPointer` searches for a node where the actual data pointer equals `Data`. This is a more fine search than `find (??)`, where a custom compare function can be used.

The default `OnCompare (??)` compares the data pointers, so the default `Find` will return the same node as `FindPointer`

See also: `TAVLTree.Find (??)`, `TAVLTree.FindKey (??)`

### 2.3.12 TAVLTree.FindLeftMost

Synopsis: Find the node most left to a specified data node

Declaration: `function FindLeftMost(Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindLeftMost` finds the node most left from the `Data` node. It starts at the preceding node for `Data` and tries to move as far right in the tree as possible.

This operation corresponds to finding the previous item in a list.

See also: `TAVLTree.FindRightMost (??)`, `TAVLTree.FindLeftMostKey (??)`, `TAVLTree.FindRightMostKey (??)`

### 2.3.13 TAVLTree.FindRightMost

Synopsis: Find the node most right to a specified node

Declaration: `function FindRightMost (Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindRightMost` finds the node most right from the `Data` node. It starts at the succeeding node for `Data` and tries to move as far left in the tree as possible.

This operation corresponds to finding the next item in a list.

See also: `TAVLTree.FindLeftMost (??)`, `TAVLTree.FindLeftMostKey (??)`, `TAVLTree.FindRightMostKey (??)`

### 2.3.14 TAVLTree.FindLeftMostKey

Synopsis: Find the node most left to a specified key node

Declaration: `function FindLeftMostKey (Key: Pointer;  
OnCompareKeyWithData: TListSortCompare)  
: TAVLTreeNode`

Visibility: public

Description: `FindLeftMostKey` finds the node most left from the node associated with `Key`. It starts at the preceding node for `Key` and tries to move as far left in the tree as possible.

See also: `TAVLTree.FindLeftMost (??)`, `TAVLTree.FindRightMost (??)`, `TAVLTree.FindRightMostKey (??)`

### 2.3.15 TAVLTree.FindRightMostKey

Synopsis: Find the node most right to a specified key node

Declaration: `function FindRightMostKey (Key: Pointer;  
OnCompareKeyWithData: TListSortCompare)  
: TAVLTreeNode`

Visibility: public

Description: `FindRightMostKey` finds the node most left from the node associated with `Key`. It starts at the succeeding node for `Key` and tries to move as far right in the tree as possible.

See also: `TAVLTree.FindLeftMost (??)`, `TAVLTree.FindRightMost (??)`, `TAVLTree.FindLeftMostKey (??)`

### 2.3.16 TAVLTree.FindLeftMostSameKey

Synopsis: Find the node most left to a specified node with the same data

Declaration: `function FindLeftMostSameKey (ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindLeftMostSameKey` finds the node most left from and with the same data as the specified node `ANode`.

See also: `TAVLTree.FindLeftMost (??)`, `TAVLTree.FindLeftMostKey (??)`, `TAVLTree.FindRightMostSameKey (??)`

### 2.3.17 TAVLTree.FindRightMostSameKey

Synopsis: Find the node most right of a specified node with the same data

Declaration: `function FindRightMostSameKey (ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindRightMostSameKey` finds the node most right from and with the same data as the specified node `ANode`.

See also: `TAVLTree.FindRightMost (??)`, `TAVLTree.FindRightMostKey (??)`, `TAVLTree.FindLeftMostSameKey (??)`

### 2.3.18 TAVLTree.Add

Synopsis: Add a new node to the tree

Declaration: `procedure Add (ANode: TAVLTreeNode)`  
`function Add (Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `Add` adds a new `Data` or `Node` to the tree. It inserts the node so that the tree is maximally balanced by rebalancing the tree after the insert. In case a data pointer is added to the tree, then the node that was created is returned.

See also: `TAVLTree.Delete (??)`, `TAVLTree.Remove (??)`

### 2.3.19 TAVLTree.Delete

Synopsis: Delete a node from the tree

Declaration: `procedure Delete (ANode: TAVLTreeNode)`

Visibility: public

Description: `Delete` removes the node from the tree. The node is not freed, but is passed to a `TAVLTreeNode-MemManager (75)` instance for future reuse. The data that the node represents is also not freed. The tree is rebalanced after the node was deleted.

See also: `TAVLTree.Remove (??)`, `TAVLTree.RemovePointer (??)`, `TAVLTree.Clear (??)`

### 2.3.20 TAVLTree.Remove

Synopsis: Remove a data item from the list.

Declaration: `procedure Remove (Data: Pointer)`

Visibility: public

Description: `Remove` finds the node associated with `Data` using `find (??)` and, if found, deletes it from the tree. Only the first occurrence of `Data` will be removed.

See also: `TAVLTree.Delete (??)`, `TAVLTree.RemovePointer (??)`, `TAVLTree.Clear (??)`, `TAVLTree.Find (??)`

### 2.3.21 TAVLTree.RemovePointer

Synopsis: Remove a pointer item from the list.

Declaration: `procedure RemovePointer(Data: Pointer)`

Visibility: `public`

Description: `Remove` uses `FindPointer` (??) to find the node associated with the pointer `Data` and, if found, deletes it from the tree. Only the first occurrence of `Data` will be removed.

See also: `TAVLTree.Remove` (??), `TAVLTree.Delete` (??), `TAVLTree.Clear` (??)

### 2.3.22 TAVLTree.MoveDataLeftMost

Synopsis: Move data to the nearest left element

Declaration: `procedure MoveDataLeftMost(var ANode: TAVLTreeNode)`

Visibility: `public`

Description: `MoveDataLeftMost` moves the data from the node `ANode` to the nearest left location relative to `ANode`. It returns the new node where the data is positioned. The data from the former left node will be switched to `ANode`.

This operation corresponds to switching the current with the previous element in a list.

See also: `TAVLTree.MoveDataRightMost` (??)

### 2.3.23 TAVLTree.MoveDataRightMost

Synopsis: Move data to the nearest right element

Declaration: `procedure MoveDataRightMost(var ANode: TAVLTreeNode)`

Visibility: `public`

Description: `MoveDataRightMost` moves the data from the node `ANode` to the rightmost location relative to `ANode`. It returns the new node where the data is positioned. The data from the former rightmost node will be switched to `ANode`.

This operation corresponds to switching the current with the next element in a list.

See also: `TAVLTree.MoveDataLeftMost` (??)

### 2.3.24 TAVLTree.Clear

Synopsis: Clears the tree

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` deletes all nodes from the tree. The nodes themselves are not freed, and the data pointer in the nodes is also not freed.

If the node's data must be freed as well, use `TAVLTree.FreeAndClear` (??) instead.

See also: `TAVLTree.FreeAndClear` (??), `TAVLTree.Delete` (??)

### 2.3.25 TAVLTree.FreeAndClear

Synopsis: Clears the tree and frees nodes

Declaration: `procedure FreeAndClear`

Visibility: public

Description: `FreeAndClear` deletes all nodes from the tree. The data pointer in the nodes is assumed to be an object, and is freed prior to deleting the node from the tree.

See also: `TAVLTree.Clear (??)`, `TAVLTree.Delete (??)`, `TAVLTree.FreeAndDelete (??)`

### 2.3.26 TAVLTree.FreeAndDelete

Synopsis: Delete a node from the tree and destroy it

Declaration: `procedure FreeAndDelete (ANode: TAVLTreeNode)`

Visibility: public

Description: `FreeAndDelete` deletes a node from the tree, and destroys the data pointer: The data pointer in the nodes is assumed to be an object, and is freed by calling its destructor.

See also: `TAVLTree.Clear (??)`, `TAVLTree.Delete (??)`, `TAVLTree.FreeAndClear (??)`

### 2.3.27 TAVLTree.ConsistencyCheck

Synopsis: Check the consistency of the tree

Declaration: `function ConsistencyCheck : Integer`

Visibility: public

Description: `ConsistencyCheck` checks the correctness of the tree. It returns 0 if the tree is internally consistent, and a negative number if the tree contains an error somewhere.

- 1The Count property doesn't match the actual node count
- 2A left node does not point to the correct parent
- 3A left node is larger than parent node
- 4A right node does not point to the correct parent
- 5A right node is less than parent node
- 6The balance of a node is not calculated correctly

See also: `TAVLTree.WriteReportToStream (??)`

### 2.3.28 TAVLTree.WriteReportToStream

Synopsis: Write the contents of the tree consistency check to the stream

Declaration: `procedure WriteReportToStream (s: TStream; var StreamSize: Int64)`

Visibility: public

Description: `WriteReportToStream` writes a visual representation of the tree to the stream S. The total number of written bytes is returned in `StreamSize`. This method is only useful for debugging purposes.

See also: `TAVLTree.ConsistencyCheck (??)`



### 2.3.29 TAVLTree.ReportAsString

Synopsis: Return the tree report as a string

Declaration: `function ReportAsString : String`

Visibility: public

Description: `ReportAsString` calls `WriteReportToStream` (??) and returns the stream data as a string.

See also: `TAVLTree.WriteReportToStream` (??)

### 2.3.30 TAVLTree.SetNodeManager

Synopsis: Set the node instance manager to use

Declaration: `procedure SetNodeManager (NewMgr: TBaseAVLTreeNodeManager;  
AutoFree: Boolean)`

Visibility: public

Description: `SetNodeManager` sets the node manager instance used by the tree to `newmgr`. It should be called before any nodes are added to the tree. The `TAVLTree` instance will not destroy the nodemanager, thus the same instance of the tree node manager can be used to manager the nodes of multiple `TAVLTree` instances.

By default, a single instance of `TAVLTreeNodeMemManager` (75) is used to manage the nodes of all `TAVLTree` instances.

See also: `TBaseAVLTreeNodeManager` (77), `TAVLTreeNodeMemManager` (75)

### 2.3.31 TAVLTree.Create

Synopsis: Create a new instance of `TAVLTree`

Declaration: `constructor Create (OnCompareMethod: TListSortCompare)  
constructor Create`

Visibility: public

Description: `Create` initializes a new instance of `TAVLTree` (64). An alternate `OnCompare` (??) can be provided: the default `OnCompare` method compares the 2 data pointers of a node.

See also: `OnCompare` (??)

### 2.3.32 TAVLTree.Destroy

Synopsis: Destroy the `TAVLTree` instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` clears the nodes (the node data is not freed) and then destroys the `TAVLTree` instance.

See also: `TAVLTree.Create` (??), `TAVLTree.Clean` (??)

### 2.3.33 TAVLTree.GetEnumerator

Synopsis: Get an enumerator for the tree.

Declaration: `function GetEnumerator : TAVLTreeNodeEnumerator`

Visibility: public

Description: `GetEnumerator` returns an instance of the standard tree node enumerator `TAVLTreeNodeEnumerator` (74).

See also: `TAVLTreeNodeEnumerator` (74)

### 2.3.34 TAVLTree.OnCompare

Synopsis: Compare function used when comparing nodes

Declaration: `Property OnCompare : TListSortCompare`

Visibility: public

Access: Read,Write

Description: `OnCompare` is the comparing function used when the data of 2 nodes must be compared. By default, the function simply compares the 2 data pointers. A different function can be specified on creation.

See also: `TAVLTree.Create` (??)

### 2.3.35 TAVLTree.Count

Synopsis: Number of nodes in the tree.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` is the number of nodes in the tree.

## 2.4 TAVLTreeNode

### 2.4.1 Description

`TAVLTreeNode` represents a single node in the AVL tree. It contains references to the other nodes in the tree, and provides a `Data` (??) pointer which can be used to store the data, associated with the node.

See also: `TAVLTree` (64), `TAVLTreeNode.Data` (??)

### 2.4.2 Method overview

Page	Property	Description
74	<code>Clear</code>	Clears the node's data
74	<code>TreeDepth</code>	Level of the node in the tree below

### 2.4.3 TAVLTreeNode.Clear

Synopsis: Clears the node's data

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` clears all pointers and references in the node. It does not free the memory pointed to by these references.

### 2.4.4 TAVLTreeNode.TreeDepth

Synopsis: Level of the node in the tree below

Declaration: `function TreeDepth : Integer`

Visibility: `public`

Description: `TreeDepth` is the height of the node: this is the largest height of the left or right nodes, plus 1. If no nodes appear below this node (`left` and `Right` are `Nil`), the depth is 1.

See also: `Balance` (??)

## 2.5 TAVLTreeNodeEnumerator

### 2.5.1 Description

`TAVLTreeNodeEnumerator` is a class which implements the enumerator interface for the `TAVLTree` (64). It enumerates all the nodes in the tree.

See also: `TAVLTree` (64)

### 2.5.2 Method overview

Page	Property	Description
<a href="#">74</a>	<code>Create</code>	Create a new instance of <code>TAVLTreeNodeEnumerator</code>
<a href="#">75</a>	<code>MoveNext</code>	Move to next node in the tree.

### 2.5.3 Property overview

Page	Property	Access	Description
<a href="#">75</a>	<code>Current</code>	<code>r</code>	Current node in the tree

### 2.5.4 TAVLTreeNodeEnumerator.Create

Synopsis: Create a new instance of `TAVLTreeNodeEnumerator`

Declaration: `constructor Create(Tree: TAVLTree)`

Visibility: `public`

Description: `Create` creates a new instance of `TAVLTreeNodeEnumerator` and saves the `Tree` argument for later use in the enumerator.

## 2.5.5 TAVLTreeNodeEnumerator.MoveNext

Synopsis: Move to next node in the tree.

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` will return the lowest node in the tree to start with, and for all other calls returns the successor node of the current node with `TAVLTree.FindSuccessor` (??).

See also: `TAVLTree.FindSuccessor` (??)

## 2.5.6 TAVLTreeNodeEnumerator.Current

Synopsis: Current node in the tree

Declaration: `Property Current : TAVLTreeNode`

Visibility: public

Access: Read

Description: `Current` is the current node in the enumeration.

See also: `TAVLTreeNodeEnumerator.MoveNext` (??)

## 2.6 TAVLTreeNodeMemManager

### 2.6.1 Description

`TAVLTreeNodeMemManager` is an internal object used by the `avl_tree` unit. Normally, no instance of this object should be created: An instance is created by the unit initialization code, and freed when the unit is finalized.

See also: `TAVLTreeNode` (73), `TAVLTree` (64)

### 2.6.2 Method overview

Page	Property	Description
<a href="#">76</a>	<code>Clear</code>	Frees all unused nodes
<a href="#">76</a>	<code>Create</code>	Create a new instance of <code>TAVLTreeNodeMemManager</code>
<a href="#">76</a>	<code>Destroy</code>	
<a href="#">76</a>	<code>DisposeNode</code>	Return a node to the free list
<a href="#">76</a>	<code>NewNode</code>	Create a new <code>TAVLTreeNode</code> instance

### 2.6.3 Property overview

Page	Property	Access	Description
<a href="#">77</a>	<code>Count</code>	r	Number of nodes in the list.
<a href="#">77</a>	<code>MaximumFreeNodeRatio</code>	rw	Maximum amount of free nodes in the list
<a href="#">77</a>	<code>MinimumFreeNode</code>	rw	Minimum amount of free nodes to be kept.

### 2.6.4 TAVLTreeNodeMemManager.DisposeNode

Synopsis: Return a node to the free list

Declaration: `procedure DisposeNode (ANode: TAVLTreeNode); Override`

Visibility: public

Description: `DisposeNode` is used to put the node `ANode` in the list of free nodes, or optionally destroy it if the free list is full. After a call to `DisposeNode`, `ANode` must be considered invalid.

See also: `TAVLTreeNodeMemManager.NewNode` (??)

### 2.6.5 TAVLTreeNodeMemManager.NewNode

Synopsis: Create a new `TAVLTreeNode` instance

Declaration: `function NewNode : TAVLTreeNode; Override`

Visibility: public

Description: `NewNode` returns a new `TAVLTreeNode` (73) instance. If there is a node in the free list, it are returned. If no more free nodes are present, a new node is created.

See also: `TAVLTreeNodeMemManager.DisposeNode` (??)

### 2.6.6 TAVLTreeNodeMemManager.Clear

Synopsis: Frees all unused nodes

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` removes all unused nodes from the list and frees them.

See also: `TAVLTreeNodeMemManager.MinimumFreeNode` (??), `TAVLTreeNodeMemManager.MaximumFreeNodeRatio` (??)

### 2.6.7 TAVLTreeNodeMemManager.Create

Synopsis: Create a new instance of `TAVLTreeNodeMemManager`

Declaration: `constructor Create`

Visibility: public

Description: `Create` initializes a new instance of `TAVLTreeNodeMemManager`.

See also: `TAVLTreeNodeMemManager.Destroy` (??)

### 2.6.8 TAVLTreeNodeMemManager.Destroy

Synopsis:

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` calls `clear` to clean up the free node list and then calls the inherited `destroy`.

See also: `TAVLTreeNodeMemManager.Create` (??)

## 2.6.9 TAVLTreeNodeMemManager.MinimumFreeNode

Synopsis: Minimum amount of free nodes to be kept.

Declaration: `Property MinimumFreeNode : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `MinimumFreeNode` is the minimum amount of nodes that must be kept in the free nodes list.

See also: `TAVLTreeNodeMemManager.MaximumFreeNodeRatio` (??)

## 2.6.10 TAVLTreeNodeMemManager.MaximumFreeNodeRatio

Synopsis: Maximum amount of free nodes in the list

Declaration: `Property MaximumFreeNodeRatio : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `MaximumFreeNodeRatio` is the maximum amount of free nodes that should be kept in the list: if a node is disposed of, then the ratio of the free nodes versus the total amount of nodes is checked, and if it is less than the `MaximumFreeNodeRatio` ratio but larger than the minimum amount of free nodes, then the node is disposed of instead of added to the free list.

See also: `TAVLTreeNodeMemManager.Count` (??), `TAVLTreeNodeMemManager.MinimumFreeNode` (??)

## 2.6.11 TAVLTreeNodeMemManager.Count

Synopsis: Number of nodes in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: `Count` is the total number of nodes in the list, used or not.

See also: `TAVLTreeNodeMemManager.MinimumFreeNode` (??), `TAVLTreeNodeMemManager.MaximumFreeNodeRatio` (??)

## 2.7 TBaseAVLTreeNodeManager

### 2.7.1 Description

`TBaseAVLTreeNodeManager` is an abstract class from which a descendent can be created that manages creating and disposing of tree nodes (instances of `TAVLTreeNode` (73)) for a `TAVLTree` (64) tree instance. No instance of this class should be created, it is a purely abstract class. The default descendant of this class used by an `TAVLTree` instance is `TAVLTreeNodeMemManager` (75).

The `TAVLTree.SetNodeManager` (??) method can be used to set the node manager that a `TAVLTree` instance should use.

See also: `TAVLTreeNodeMemManager` (75), `TAVLTree.SetNodeManager` (??), `TAVLTreeNode` (73)

### 2.7.2 Method overview

Page	Property	Description
<a href="#">78</a>	DisposeNode	Called when the AVL tree no longer needs node
<a href="#">78</a>	NewNode	Called when the AVL tree needs a new node

### 2.7.3 TBaseAVLTreeNodeManager.DisposeNode

Synopsis: Called when the AVL tree no longer needs node

Declaration: `procedure DisposeNode (ANode: TAVLTreeNode); Virtual; Abstract`

Visibility: `public`

Description: `DisposeNode` is called by `TAVLTree` ([64](#)) when it no longer needs a `TAVLTreeNode` ([73](#)) instance. The manager may decide to re-use the instance for later use instead of destroying it.

See also: `TBaseAVLTreeNodeManager.NewNode` ([??](#)), `TAVLTree.Delete` ([??](#)), `TAVLTreeNode` ([73](#))

### 2.7.4 TBaseAVLTreeNodeManager.NewNode

Synopsis: Called when the AVL tree needs a new node

Declaration: `function NewNode : TAVLTreeNode; Virtual; Abstract`

Visibility: `public`

Description: `NewNode` is called by `TAVLTree` ([64](#)) when it needs a new node in `TAVLTree.Add` ([??](#)). It must be implemented by descendants to return a new `TAVLTreeNode` ([73](#)) instance.

See also: `TBaseAVLTreeNodeManager.DisposeNode` ([??](#)), `TAVLTree.Add` ([??](#)), `TAVLTreeNode` ([73](#))

## Chapter 3

# Reference for unit 'base64'

### 3.1 Used units

Table 3.1: Used units by unit 'base64'

Name	Page
Classes	??
System	??
sysutils	??

### 3.2 Overview

`base64` implements base64 encoding (as used for instance in MIME encoding) based on streams. it implements 2 streams which encode or decode anything written or read from it. The source or the destination of the encoded data is another stream. 2 classes are implemented for this: `TBase64EncodingStream` ([83](#)) for encoding, and `TBase64DecodingStream` ([80](#)) for decoding.

The streams are designed as plug-in streams, which can be placed between other streams, to provide base64 encoding and decoding on-the-fly...

### 3.3 Constants, types and variables

#### 3.3.1 Types

```
TBase64DecodingMode = (bdmStrict, bdMIME)
```

Table 3.2: Enumeration values for type `TBase64DecodingMode`

Value	Explanation
<code>bdmMIME</code>	MIME encoding
<code>bdmStrict</code>	Strict encoding



`TBase64DecodingMode` determines the decoding algorithm used by `TBase64DecodingStream` (80). There are 2 modes:

**bdmStrict** Strict mode, which follows RFC3548 and rejects any characters outside of base64 alphabet. In this mode only up to two '=' characters are accepted at the end. It requires the input to have a `Size` being a multiple of 4, otherwise an `EBase64DecodingException` (80) exception is raised.

**bdmMime** MIME mode, which follows RFC2045 and ignores any characters outside of base64 alphabet. In this mode any '=' is seen as the end of string, it handles apparently truncated input streams gracefully.

## 3.4 Procedures and functions

### 3.4.1 DecodeStringBase64

Synopsis: Decodes a Base64 encoded string and returns the decoded data as a string.

Declaration: `function DecodeStringBase64(const s: String) : String`

Visibility: default

Description: `DecodeStringBase64` decodes the string `s` (containing Base 64 encoded data) returns the decoded data as a string. It uses a `TBase64DecodingStream` (80) to do this.

See also: `DecodeStringBase64` (80), `TBase64DecodingStream` (80)

### 3.4.2 EncodeStringBase64

Synopsis: Encode a string with Base64 encoding and return the result as a string.

Declaration: `function EncodeStringBase64(const s: String) : String`

Visibility: default

Description: `EncodeStringBase64` encodes the string `s` using Base 64 encoding and returns the result. It uses a `TBase64EncodingStream` (83) to do this.

See also: `DecodeStringBase64` (80), `TBase64EncodingStream` (83)

## 3.5 EBase64DecodingException

### 3.5.1 Description

`EBase64DecodeException` is raised when the stream contains errors against the encoding format. Whether or not this exception is raised depends on the mode in which the stream is decoded.

## 3.6 TBase64DecodingStream

### 3.6.1 Description

`TBase64DecodingStream` can be used to read data from a stream (the source stream) that contains Base64 encoded data. The data is read and decoded on-the-fly.

The decoding stream is read-only, and provides a limited forward-seeking capability.

See also: [TBase64EncodingStream \(83\)](#)

### 3.6.2 Method overview

Page	Property	Description
<a href="#">81</a>	Create	Create a new instance of the <code>TBase64DecodingStream</code> class
<a href="#">81</a>	Read	Read and decrypt data from the source stream
<a href="#">81</a>	Reset	Reset the stream
<a href="#">82</a>	Seek	Set stream position.

### 3.6.3 Property overview

Page	Property	Access	Description
<a href="#">82</a>	EOF	r	
<a href="#">82</a>	Mode	rw	Decoding mode

### 3.6.4 TBase64DecodingStream.Create

Synopsis: Create a new instance of the `TBase64DecodingStream` class

Declaration: `constructor Create (ASource: TStream)`  
`constructor Create (ASource: TStream; AMode: TBase64DecodingMode)`

Visibility: public

Description: `Create` creates a new instance of the `TBase64DecodingStream` class. It stores the source stream `ASource` for reading the data from.

The optional `AMode` parameter determines the mode in which the decoding will be done. If omitted, `bdmMIME` is used.

See also: [TBase64EncodingStream.Create \(??\)](#), [TBase64DecodingMode \(79\)](#)

### 3.6.5 TBase64DecodingStream.Reset

Synopsis: Reset the stream

Declaration: `procedure Reset`

Visibility: public

Description: `Reset` resets the data as if it was again on the start of the decoding stream.

Errors: None.

See also: [TBase64DecodingStream.EOF \(??\)](#), [TBase64DecodingStream.Read \(??\)](#)

### 3.6.6 TBase64DecodingStream.Read

Synopsis: Read and decrypt data from the source stream

Declaration: `function Read (var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

**Description:** Read reads encrypted data from the source stream and stores this data in `Buffer`. At most `Count` bytes will be stored in the buffer, but more bytes will be read from the source stream: the encoding algorithm multiplies the number of bytes.

The function returns the number of bytes stored in the buffer.

**Errors:** If an error occurs during the read from the source stream, an exception may occur.

**See also:** `TBase64DecodingStream.Write` (??), `TBase64DecodingStream.Seek` (??), `TStream.Read` (??)

### 3.6.7 TBase64DecodingStream.Seek

**Synopsis:** Set stream position.

**Declaration:** `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

**Visibility:** public

**Description:** `Seek` sets the position of the stream. In the `TBase64DecodingStream` class, the seek operation is forward only, it does not support backward seeks. The forward seek is emulated by reading and discarding data till the desired position is reached.

For an explanation of the parameters, see `TStream.Seek` (??)

**Errors:** In case of an unsupported operation, an `EStreamError` exception is raised.

**See also:** `TBase64DecodingStream.Read` (??), `TBase64DecodingStream.Write` (??), `TBase64EncodingStream.Seek` (??), `TStream.Seek` (??)

### 3.6.8 TBase64DecodingStream.EOF

**Synopsis:**

**Declaration:** `Property EOF : Boolean`

**Visibility:** public

**Access:** Read

**Description:**

### 3.6.9 TBase64DecodingStream.Mode

**Synopsis:** Decoding mode

**Declaration:** `Property Mode : TBase64DecodingMode`

**Visibility:** public

**Access:** Read, Write

**Description:** `Mode` is the mode in which the stream is read. It can be set when creating the stream or at any time afterwards.

**See also:** `TBase64DecodingStream` (80)

## 3.7 TBase64EncodingStream

### 3.7.1 Description

`TBase64EncodingStream` can be used to encode data using the base64 algorithm. At creation time, a destination stream is specified. Any data written to the `TBase64EncodingStream` instance will be base64 encoded, and subsequently written to the destination stream.

The `TBase64EncodingStream` stream is a write-only stream. Obviously it is also not seekable. It is meant to be included in a chain of streams.

By the nature of base64 encoding, when a buffer is written to the stream, the output stream does not yet contain all output: input must be a multiple of 3. In order to be sure that the output contains all encoded bytes, the `Flush` (??) method can be used. The destructor will automatically call `Flush`, so all data is written to the destination stream when the decodes is destroyed.

See also: `TBase64DecodingStream` (80)

### 3.7.2 Method overview

Page	Property	Description
<a href="#">83</a>	Create	Create a new instance of the <code>TBase64EncodingStream</code> class.
<a href="#">83</a>	Destroy	Remove a <code>TBase64EncodingStream</code> instance from memory
<a href="#">84</a>	Flush	Flush the remaining bytes to the output stream.
<a href="#">84</a>	Seek	Position the stream
<a href="#">84</a>	Write	Write data to the stream.

### 3.7.3 TBase64EncodingStream.Create

Synopsis: Create a new instance of the `TBase64EncodingStream` class.

Declaration: `constructor Create (ASource: TStream)`

Visibility: public

Description: `Create` instantiates a new `TBase64EncodingStream` class. The `ASource` stream is stored and used to write the encoded data to.

See also: `TBase64EncodingStream.Destroy` (??), `TBase64DecodingStream.Create` (??)

### 3.7.4 TBase64EncodingStream.Destroy

Synopsis: Remove a `TBase64EncodingStream` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` flushes any remaining output and then removes the `TBase64EncodingStream` instance from memory by calling the inherited destructor.

Errors: An exception may be raised if the destination stream no longer exists or is closed.

See also: `TBase64EncodingStream.Create` (??)

### 3.7.5 TBase64EncodingStream.Flush

Synopsis: Flush the remaining bytes to the output stream.

Declaration: `function Flush : Boolean`

Visibility: `public`

Description: `Flush` writes the remaining bytes from the internal encoding buffer to the output stream and pads the output with "=" signs. It returns `True` if padding was necessary, and `False` if not.

See also: `TBase64EncodingStream.Destroy` (??)

### 3.7.6 TBase64EncodingStream.Write

Synopsis: Write data to the stream.

Declaration: `function Write(const Buffer;Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` encodes `Count` bytes from `Buffer` using the Base64 mechanism, and then writes the encoded data to the destination stream. It returns the number of bytes from `Buffer` that were actually written. Note that this is not the number of bytes written to the destination stream: the base64 mechanism writes more bytes to the destination stream.

Errors: If there is an error writing to the destination stream, an error may occur.

See also: `TBase64EncodingStream.Seek` (??), `TBase64EncodingStream.Read` (??), `TBase64DecodingStream.Write` (??), `TStream.Write` (??)

### 3.7.7 TBase64EncodingStream.Seek

Synopsis: Position the stream

Declaration: `function Seek(Offset: LongInt;Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` always raises an `EStreamError` exception unless the arguments it received it don't change the current file pointer position. The encryption stream is not seekable.

Errors: An `EStreamError` error is raised.

See also: `TBase64EncodingStream.Read` (??), `TBase64EncodingStream.Write` (??), `TStream.Seek` (??)

## Chapter 4

# Reference for unit 'BlowFish'

### 4.1 Used units

Table 4.1: Used units by unit 'BlowFish'

Name	Page
Classes	??
System	??
sysutils	??

### 4.2 Overview

The BlowFish implements a class TBlowFish (86) to handle blowfish encryption/decryption of memory buffers, and 2 TStream (??) descendents TBlowFishDeCryptStream (87) which descrypts any data that is read from it on the fly, as well as TBlowFishEnCryptStream (88) which encrypts the data that is written to it on the fly.

### 4.3 Constants, types and variables

#### 4.3.1 Constants

`BFRounds = 16`

Number of rounds in blowfish encryption.

#### 4.3.2 Types

`PBlowFishKey = ^TBlowFishKey`

PBlowFishKey is a simple pointer to a TBlowFishKey (86) array.

`TBFBlock = Array[0..1] of LongInt`

TBFBlock is the basic data structure used by the encrypting/decrypting routines in TBlowFish (86), TBlowFishDeCryptStream (87) and TBlowFishEnCryptStream (88). It is the basic encryption/decryption block for all encrypting/decrypting: all encrypting/decrypting happens on a TBFBlock structure.

```
TBlowFishKey = Array[0..55] of Byte
```

TBlowFishKey is a data structure which keeps the encryption or decryption key for the TBlowFish (86), TBlowFishDeCryptStream (87) and TBlowFishEnCryptStream (88) classes. It should be filled with the encryption key and passed to the constructor of one of these classes.

## 4.4 EBlowFishError

### 4.4.1 Description

EBlowFishError is used by the TBlowFishStream (90), TBlowFishEncryptStream (88) and TBlowFishDecryptStream (87) classes to report errors.

See also: TBlowFishStream (90), TBlowFishEncryptStream (88), TBlowFishDecryptStream (87)

## 4.5 TBlowFish

### 4.5.1 Description

TBlowFish is a simple class that can be used to encrypt/decrypt a single TBFBlock (86) data block with the Encrypt (??) and Decrypt (??) calls. It is used internally by the TBlowFishEnCryptStream (88) and TBlowFishDeCryptStream (87) classes to encrypt or decrypt the actual data.

See also: TBlowFishEnCryptStream (88), TBlowFishDeCryptStream (87)

### 4.5.2 Method overview

Page	Property	Description
<a href="#">86</a>	Create	Create a new instance of the TBlowFish class
<a href="#">87</a>	Decrypt	Decrypt a block
<a href="#">87</a>	Encrypt	Encrypt a block

### 4.5.3 TBlowFish.Create

Synopsis: Create a new instance of the TBlowFish class

Declaration: constructor Create(Key: TBlowFishKey; KeySize: Integer)

Visibility: public

Description: Create initializes a new instance of the TBlowFish class: it stores the key Key in the internal data structures so it can be used in later calls to Encrypt (??) and Decrypt (??).

See also: Encrypt (??), Decrypt (??)

#### 4.5.4 TBlowFish.Encrypt

Synopsis: Encrypt a block

Declaration: `procedure Encrypt (var Block: TBFBlock)`

Visibility: public

Description: `Encrypt` encrypts the data in `Block` (always 8 bytes) using the key (86) specified when the `TBlowFish` instance was created.

See also: `TBlowFishKey` (86), `Decrypt` (??), `Create` (??)

#### 4.5.5 TBlowFish.Decrypt

Synopsis: Decrypt a block

Declaration: `procedure Decrypt (var Block: TBFBlock)`

Visibility: public

Description: `decrypt` decrypts the data in `Block` (always 8 bytes) using the key (86) specified when the `TBlowFish` instance was created. The data must have been encrypted with the same key and the `Encrypt` (??) call.

See also: `TBlowFishKey` (86), `Encrypt` (??), `Create` (??)

### 4.6 TBlowFishDeCryptStream

#### 4.6.1 Description

The `TBlowFishDecryptStream` provides On-the-fly Blowfish decryption: all data that is read from the source stream is decrypted before it is placed in the output buffer. The source stream must be specified when the `TBlowFishDecryptStream` instance is created. The Decryption key must also be created when the stream instance is created, and must be the same key as the one used when encrypting the data.

This is a read-only stream: it is seekable only in a forward direction, and data can only be read from it, writing is not possible. For writing data so it is encrypted, the `TBlowFishEncryptStream` (88) stream must be used.

See also: `Create` (??), `TBlowFishEncryptStream` (88)

#### 4.6.2 Method overview

Page	Property	Description
<a href="#">87</a>	Read	Read data from the stream
<a href="#">88</a>	Seek	Set the stream position.

#### 4.6.3 TBlowFishDeCryptStream.Read

Synopsis: Read data from the stream

Declaration: `function Read (var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public



**Description:** Read reads `Count` bytes from the source stream, decrypts them using the key provided when the `TBlowFishDeCryptStream` instance was created, and writes the decrypted data to `Buffer`

See also: [Create \(??\)](#), [TBlowFishEncryptStream \(88\)](#)

### 4.6.4 TBlowFishDeCryptStream.Seek

**Synopsis:** Set the stream position.

**Declaration:** `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

**Visibility:** public

**Description:** `Seek` emulates a forward seek by reading and discarding data. The discarded data is lost. Since it is a forward seek, this means that only `soFromCurrent` can be specified for `Origin` with a positive (or zero) `Offset` value. All other values will result in an exception. The function returns the new position in the stream.

**Errors:** If any other combination of `Offset` and `Origin` than the allowed combination is specified, then an `EBlowFishError (86)` exception will be raised.

See also: [Read \(??\)](#), [EBlowFishError \(86\)](#)

## 4.7 TBlowFishEncryptStream

### 4.7.1 Description

The `TBlowFishEncryptStream` provides On-the-fly Blowfish encryption: all data that is written to it is encrypted and then written to a destination stream, which must be specified when the `TBlowFishEncryptStream` instance is created. The encryption key must also be created when the stream instance is created.

This is a write-only stream: it is not seekable, and data can only be written to it, reading is not possible. For reading encrypted data, the `TBlowFishDeCryptStream (87)` stream must be used.

See also: [Create \(??\)](#), [TBlowFishDeCryptStream \(87\)](#)

### 4.7.2 Method overview

Page	Property	Description
<a href="#">88</a>	<code>Destroy</code>	Free the <code>TBlowFishEncryptStream</code>
<a href="#">89</a>	<code>Flush</code>	Flush the encryption buffer
<a href="#">89</a>	<code>Seek</code>	Set the position in the stream
<a href="#">89</a>	<code>Write</code>	Write data to the stream

### 4.7.3 TBlowFishEncryptStream.Destroy

**Synopsis:** Free the `TBlowFishEncryptStream`

**Declaration:** `destructor Destroy; Override`

**Visibility:** public

**Description:** `Destroy` flushes the encryption buffer, and writes it to the destination stream. After that the inherited destructor is called to clean up the `TBlowFishEncryptStream` instance.

See also: `Flush (??)`, `Create (??)`

#### 4.7.4 TBlowFishEncryptStream.Write

**Synopsis:** Write data to the stream

**Declaration:** `function Write(const Buffer;Count: LongInt) : LongInt; Override`

**Visibility:** public

**Description:** `Write` will encrypt and write `Count` bytes from `Buffer` to the destination stream. The function returns the actual number of bytes written. The data is not encrypted in-place, but placed in a special buffer for encryption.

Data is always written 4 bytes at a time, since this is the amount of bytes required by the Blowfish algorithm. If no multiple of 4 was written to the destination stream, the `Flush (??)` mechanism can be used to write the remaining bytes.

See also: `TBlowFishEncryptStream.Read (??)`

#### 4.7.5 TBlowFishEncryptStream.Seek

**Synopsis:** Set the position in the stream

**Declaration:** `function Seek(const Offset: Int64;Origin: TSeekOrigin) : Int64; Override`

**Visibility:** public

**Description:** `Read` will raise an `EBlowFishError` exception: `TBlowFishEncryptStream` is a write-only stream, and cannot be positioned.

**Errors:** Calling this function always results in an `EBlowFishError (86)` exception.

See also: `TBlowFishEncryptStream.Write (??)`

#### 4.7.6 TBlowFishEncryptStream.Flush

**Synopsis:** Flush the encryption buffer

**Declaration:** `procedure Flush`

**Visibility:** public

**Description:** `Flush` writes the remaining data in the encryption buffer to the destination stream.

For efficiency, data is always written 4 bytes at a time, since this is the amount of bytes required by the Blowfish algorithm. If no multiple of 4 was written to the destination stream, the `Flush` mechanism can be used to write the remaining bytes.

`Flush` is called automatically when the stream is destroyed, so there is no need to call it after all data was written and the stream is no longer needed.

See also: `Write (??)`, `TBFBlock (86)`

## 4.8 TBlowFishStream

### 4.8.1 Description

TBlowFishStream is an abstract class which is used as a parent class for TBlowFishEncryptStream (88) and TBlowFishDecryptStream (87). It simply provides a constructor and storage for a TBlowFish (86) instance and for the source or destination stream.

Do not create an instance of TBlowFishStream directly. Instead create one of the descendent classes TBlowFishEncryptStream or TBlowFishDecryptStream.

See also: TBlowFishEncryptStream (88), TBlowFishDecryptStream (87), TBlowFish (86)

### 4.8.2 Method overview

Page	Property	Description
<a href="#">90</a>	Create	Create a new instance of the TBlowFishStream class
<a href="#">90</a>	Destroy	Destroy the TBlowFishStream instance.

### 4.8.3 Property overview

Page	Property	Access	Description
<a href="#">91</a>	BlowFish	r	Blowfish instance used when encrypting/decrypting

### 4.8.4 TBlowFishStream.Create

Synopsis: Create a new instance of the TBlowFishStream class

Declaration: constructor Create(AKey: TBlowFishKey; AKeySize: Byte; Dest: TStream)  
 constructor Create(const KeyPhrase: String; Dest: TStream)

Visibility: public

Description: Create initializes a new instance of TBlowFishStream, and creates an internal instance of TBlowFish (86) using AKey and AKeySize. The Dest stream is stored so the descendent classes can refer to it.

Do not create an instance of TBlowFishStream directly. Instead create one of the descendent classes TBlowFishEncryptStream or TBlowFishDecryptStream.

The overloaded version with the KeyPhrase string argument is used for easy access: it computes the blowfish key from the given string.

See also: TBlowFishEncryptStream (88), TBlowFishDecryptStream (87), TBlowFish (86)

### 4.8.5 TBlowFishStream.Destroy

Synopsis: Destroy the TBlowFishStream instance.

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy cleans up the internal TBlowFish (86) instance.

See also: Create (??), TBlowFish (86)

#### 4.8.6 TBlowFishStream.BlowFish

Synopsis: Blowfish instance used when encrypting/decrypting

Declaration: `Property BlowFish : TBlowFish`

Visibility: `public`

Access: `Read`

Description: `BlowFish` is the `TBlowFish` (86) instance which is created when the `TBlowFishStream` class is initialized. Normally it should not be used directly, it's intended for access by the descendent classes `TBlowFishEncryptStream` (88) and `TBlowFishDecryptStream` (87).

See also: `TBlowFishEncryptStream` (88), `TBlowFishDecryptStream` (87), `TBlowFish` (86)

## Chapter 5

# Reference for unit 'bufstream'

### 5.1 Used units

Table 5.1: Used units by unit 'bufstream'

Name	Page
Classes	??
System	??
sysutils	??

### 5.2 Overview

BufStream implements two one-way buffered streams: the streams store all data from (or for) the source stream in a memory buffer, and only flush the buffer when it's full (or refill it when it's empty). The buffer size can be specified at creation time. 2 streams are implemented: TReadBufStream (95) which is for reading only, and TWriteBufStream (96) which is for writing only.

Buffered streams can help in speeding up read or write operations, especially when a lot of small read/write operations are done: it avoids doing a lot of operating system calls.

### 5.3 Constants, types and variables

#### 5.3.1 Constants

`DefaultBufferCapacity : Integer = 16`

If no buffer size is specified when the stream is created, then this size is used.

### 5.4 TBufStream

#### 5.4.1 Description

TBufStream is the common ancestor for the TReadBufStream (95) and TWriteBufStream (96) streams. It completely handles the buffer memory management and position management. An in-

stance of `TBufStream` should never be created directly. It also keeps the instance of the source stream.

See also: `TReadBufStream` (95), `TWriteBufStream` (96)

### 5.4.2 Method overview

Page	Property	Description
<a href="#">93</a>	Create	Create a new <code>TBufStream</code> instance.
<a href="#">93</a>	Destroy	Destroys the <code>TBufStream</code> instance

### 5.4.3 Property overview

Page	Property	Access	Description
<a href="#">94</a>	Buffer	r	The current buffer
<a href="#">94</a>	BufferPos	r	Current buffer position.
<a href="#">94</a>	BufferSize	r	Amount of data in the buffer
<a href="#">94</a>	Capacity	rw	Current buffer capacity

### 5.4.4 TBufStream.Create

Synopsis: Create a new `TBufStream` instance.

Declaration: `constructor Create(ASource: TStream; ACapacity: Integer)`  
`constructor Create(ASource: TStream)`

Visibility: public

Description: `Create` creates a new `TBufStream` instance. A buffer of size `ACapacity` is allocated, and the `ASource` source (or destination) stream is stored. If no capacity is specified, then `DefaultBufferCapacity` (92) is used as the capacity.

An instance of `TBufStream` should never be instantiated directly. Instead, an instance of `TReadBufStream` (95) or `TWriteBufStream` (96) should be created.

Errors: If not enough memory is available for the buffer, then an exception may be raised.

See also: `TBufStream.Destroy` (??), `TReadBufStream` (95), `TWriteBufStream` (96)

### 5.4.5 TBufStream.Destroy

Synopsis: Destroys the `TBufStream` instance

Declaration: `destructor Destroy;` `Override`

Visibility: public

Description: `Destroy` destroys the instance of `TBufStream`. It flushes the buffer, deallocates it, and then destroys the `TBufStream` instance.

See also: `TBufStream.Create` (??), `TReadBufStream` (95), `TWriteBufStream` (96)

### 5.4.6 TBufStream.Buffer

Synopsis: The current buffer

Declaration: `Property Buffer : Pointer`

Visibility: public

Access: Read

Description: `Buffer` is a pointer to the actual buffer in use.

See also: `TBufStream.Create (??)`, `TBufStream.Capacity (??)`, `TBufStream.BufferSize (??)`

### 5.4.7 TBufStream.Capacity

Synopsis: Current buffer capacity

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read, Write

Description: `Capacity` is the amount of memory the buffer occupies. To change the buffer size, the capacity can be set. Note that the capacity cannot be set to a value that is less than the current buffer size, i.e. the current amount of data in the buffer.

See also: `TBufStream.Create (??)`, `TBufStream.Buffer (??)`, `TBufStream.BufferSize (??)`, `TBufStream.BufferPos (??)`

### 5.4.8 TBufStream.BufferPos

Synopsis: Current buffer position.

Declaration: `Property BufferPos : Integer`

Visibility: public

Access: Read

Description: `BufPos` is the current stream position in the buffer. Depending on whether the stream is used for reading or writing, data will be read from this position, or will be written at this position in the buffer.

See also: `TBufStream.Create (??)`, `TBufStream.Buffer (??)`, `TBufStream.BufferSize (??)`, `TBufStream.Capacity (??)`

### 5.4.9 TBufStream.BufferSize

Synopsis: Amount of data in the buffer

Declaration: `Property BufferSize : Integer`

Visibility: public

Access: Read

Description: `BufferSize` is the actual amount of data in the buffer. This is always less than or equal to the `Capacity (??)`.

See also: `TBufStream.Create (??)`, `TBufStream.Buffer (??)`, `TBufStream.BufferPos (??)`, `TBufStream.Capacity (??)`

## 5.5 TReadBufStream

### 5.5.1 Description

`TReadBufStream` is a read-only buffered stream. It implements the needed methods to read data from the buffer and fill the buffer with additional data when needed.

The stream provides limited forward-seek possibilities.

See also: `TBufStream` (92), `TWriteBufStream` (96)

### 5.5.2 Method overview

Page	Property	Description
<a href="#">95</a>	Read	Reads data from the stream
<a href="#">95</a>	Seek	Set location in the buffer

### 5.5.3 TReadBufStream.Seek

Synopsis: Set location in the buffer

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: public

Description: `Seek` sets the location in the buffer. Currently, only a forward seek is allowed. It is emulated by reading and discarding data. For an explanation of the parameters, see `TStream.Seek`" (??)

The seek method needs enhancement to enable it to do a full-featured seek. This may be implemented in a future release of Free Pascal.

Errors: In case an illegal seek operation is attempted, an exception is raised.

See also: `TWriteBufStream.Seek` (??), `TReadBufStream.Read` (??), `TReadBufStream.Write` (??)

### 5.5.4 TReadBufStream.Read

Synopsis: Reads data from the stream

Declaration: `function Read(var ABuffer; ACount: LongInt) : Integer; Override`

Visibility: public

Description: `Read` reads at most `ACount` bytes from the stream and places them in `Buffer`. The number of actually read bytes is returned.

`TReadBufStream` first reads whatever data is still available in the buffer, and then refills the buffer, after which it continues to read data from the buffer. This is repeated until `ACount` bytes are read, or no more data is available.

See also: `TReadBufStream.Seek` (??), `TReadBufStream.Read` (??)



## 5.6 TWriteBufStream

### 5.6.1 Description

`TWriteBufStream` is a write-only buffered stream. It implements the needed methods to write data to the buffer and flush the buffer (i.e., write its contents to the source stream) when needed.

See also: `TBufStream` (92), `TReadBufStream` (95)

### 5.6.2 Method overview

Page	Property	Description
<a href="#">96</a>	<code>Destroy</code>	Remove the <code>TWriteBufStream</code> instance from memory
<a href="#">96</a>	<code>Seek</code>	Set stream position.
<a href="#">96</a>	<code>Write</code>	Write data to the stream

### 5.6.3 TWriteBufStream.Destroy

Synopsis: Remove the `TWriteBufStream` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` flushes the buffer and then calls the inherited `Destroy` (??).

Errors: If an error occurs during flushing of the buffer, an exception may be raised.

See also: `Create` (??), `TBufStream.Destroy` (??)

### 5.6.4 TWriteBufStream.Seek

Synopsis: Set stream position.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: `public`

Description: `Seek` always raises an `EStreamError` exception, except when the seek operation would not alter the current position.

A later implementation may perform a proper seek operation by flushing the buffer and doing a seek on the source stream.

See also: `TWriteBufStream.Write` (??), `TWriteBufStream.Read` (??), `TReadBufStream.Seek` (??)

### 5.6.5 TWriteBufStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(const ABuffer; ACount: LongInt) : Integer; Override`

Visibility: `public`

**Description:** `Write` writes at most `ACount` bytes from `ABuffer` to the stream. The data is written to the internal buffer first. As soon as the internal buffer is full, it is flushed to the destination stream, and the internal buffer is filled again. This process continues till all data is written (or an error occurs).

**Errors:** An exception may occur if the destination stream has problems writing.

**See also:** `TWriteBufStream.Seek` (??), `TWriteBufStream.Read` (??), `TReadBufStream.Write` (??)

## Chapter 6

# Reference for unit 'CacheCls'

### 6.1 Used units

Table 6.1: Used units by unit 'CacheCls'

Name	Page
System	??
sysutils	??

### 6.2 Overview

The `CacheCls` unit implements a caching class: similar to a hash class, it can be used to cache data, associated with string values (keys). The class is called `TCache`

### 6.3 Constants, types and variables

#### 6.3.1 Resource strings

```
SInvalidIndex = '''Invalid index %i'''
```

Message shown when an invalid index is passed.

#### 6.3.2 Types

```
PCacheSlot = ^TCacheSlot
```

Pointer to `TCacheSlot` (99) record.

```
PCacheSlotArray = ^TCacheSlotArray
```

Pointer to `TCacheSlotArray` (99) array

```
TCacheSlot = record
```

```

Prev : PCacheSlot;
Next : PCacheSlot;
Data : Pointer;
Index : Integer;
end

```

TCacheSlot is internally used by the TCache (99) class. It represents 1 element in the linked list.

```
TCacheSlotArray = Array[0..MaxIntdivSizeOf(TCacheSlot)-1] of TCacheSlot
```

TCacheSlotArray is an array of TCacheSlot items. Do not use TCacheSlotArray directly, instead, use PCacheSlotArray (98) and allocate memory dynamically.

```
TOnFreeSlot = procedure(ACache: TCache; SlotIndex: Integer) of object
```

TOnFreeSlot is a callback prototype used when not enough slots are free, and a slot must be freed.

```

TOnIsDataEqual = function(ACache: TCache; AData1: Pointer;
                          AData2: Pointer) : Boolean of object

```

TOnIsDataEqual is a callback prototype; It is used by the TCache.Add (??) call to determine whether the item to be added is a new item or not. The function returns True if the 2 data pointers AData1 and AData2 should be considered equal, or False when they are not.

For most purposes, comparing the pointers will be enough, but if the pointers are ansistrings, then the contents should be compared.

## 6.4 ECacheError

### 6.4.1 Description

Exception class used in the cachecls unit.

## 6.5 TCache

### 6.5.1 Description

TCache implements a cache class: it is a list-like class, but which uses a counting mechanism, and keeps a Most-Recent-Used list; this list represents the 'cache'. The list is internally kept as a doubly-linked list.

The Data (??) property offers indexed access to the array of items. When accessing the array through this property, the MRUSlot (??) property is updated.

### 6.5.2 Method overview

Page	Property	Description
<a href="#">100</a>	Add	Add a data element to the list.
<a href="#">101</a>	AddNew	Add a new item to the list.
<a href="#">100</a>	Create	Create a new cache class.
<a href="#">100</a>	Destroy	Free the TCache class from memory
<a href="#">101</a>	FindSlot	Find data pointer in the list
<a href="#">101</a>	IndexOf	Return index of a data pointer in the list.
<a href="#">102</a>	Remove	Remove a data item from the list.

### 6.5.3 Property overview

Page	Property	Access	Description
<a href="#">102</a>	Data	rw	Indexed access to data items
<a href="#">103</a>	LRUSlot	r	Last used item
<a href="#">102</a>	MRUSlot	rw	Most recent item slot.
<a href="#">104</a>	OnFreeSlot	rw	Event called when a slot is freed
<a href="#">103</a>	OnIsDataEqual	rw	Event to compare 2 items.
<a href="#">103</a>	SlotCount	rw	Number of slots in the list
<a href="#">103</a>	Slots	r	Indexed array to the slots

### 6.5.4 TCache.Create

Synopsis: Create a new cache class.

Declaration: `constructor Create (ASlotCount: Integer)`

Visibility: `public`

Description: `Create` instantiates a new instance of `TCache`. It allocates room for `ASlotCount` entries in the list. The number of slots can be increased later.

See also: `TCache.SlotCount` (??)

### 6.5.5 TCache.Destroy

Synopsis: Free the TCache class from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the array for the elements, and calls the inherited `Destroy`. The elements in the array are not freed by this action.

See also: `TCache.Create` (??)

### 6.5.6 TCache.Add

Synopsis: Add a data element to the list.

Declaration: `function Add (AData: Pointer) : Integer`

Visibility: `public`

**Description:** Add checks whether `AData` is already in the list. If so, the item is added to the top of the MRU list. If the item is not yet in the list, then the item is added to the list and placed at the top of the MRU list using the `AddNew (??)` call.

The function returns the index at which the item was added.

If the maximum number of slots is reached, and a new item is being added, the least used item is dropped from the list.

See also: `TCache.AddNew (??)`, `TCache.FindSlot (??)`, `TCache.IndexOf (??)`, `TCache.Data (??)`, `TCache.MRUSlot (??)`

### 6.5.7 TCache.AddNew

**Synopsis:** Add a new item to the list.

**Declaration:** `function AddNew(AData: Pointer) : Integer`

**Visibility:** public

**Description:** `AddNew` adds a new item to the list: in difference with the `Add (??)` call, no checking is performed to see whether the item is already in the list.

The function returns the index at which the item was added.

If the maximum number of slots is reached, and a new item is being added, the least used item is dropped from the list.

See also: `TCache.Add (??)`, `TCache.FindSlot (??)`, `TCache.IndexOf (??)`, `TCache.Data (??)`, `TCache.MRUSlot (??)`

### 6.5.8 TCache.FindSlot

**Synopsis:** Find data pointer in the list

**Declaration:** `function FindSlot(AData: Pointer) : PCacheSlot`

**Visibility:** public

**Description:** `FindSlot` checks all items in the list, and returns the slot which contains a data pointer that matches the pointer `AData`.

If no item with data pointer that matches `AData` is found, `Nil` is returned.

For this function to work correctly, the `OnIsDataEqual (??)` event must be set.

**Errors:** If `OnIsDataEqual` is not set, an exception will be raised.

See also: `TCache.IndexOf (??)`, `TCache.Add (??)`, `TCache.OnIsDataEqual (??)`

### 6.5.9 TCache.IndexOf

**Synopsis:** Return index of a data pointer in the list.

**Declaration:** `function IndexOf(AData: Pointer) : Integer`

**Visibility:** public

**Description:** `IndexOF` searches in the list for a slot with data pointer that matches `AData` and returns the index of the slot.

If no item with data pointer that matches `AData` is found, `-1` is returned.

For this function to work correctly, the `OnIsDataEqual (??)` event must be set.

**Errors:** If `OnIsDataEqual` is not set, an exception will be raised.

See also: `TCache.FindSlot (??)`, `TCache.Add (??)`, `TCache.OnIsDataEqual (??)`

### 6.5.10 TCache.Remove

**Synopsis:** Remove a data item from the list.

**Declaration:** `procedure Remove (AData: Pointer)`

**Visibility:** `public`

**Description:** `Remove` searches the slot which matches `AData` and if it is found, sets the data pointer to `Nil`, thus effectively removing the pointer from the list.

**Errors:** None.

See also: `TCache.FindSlot (??)`

### 6.5.11 TCache.Data

**Synopsis:** Indexed access to data items

**Declaration:** `Property Data [SlotIndex: Integer]: Pointer`

**Visibility:** `public`

**Access:** Read, Write

**Description:** `Data` offers index-based access to the data pointers in the cache. By accessing an item in the list in this manner, the item is moved to the front of the MRU list, i.e. `MRUSlot (??)` will point to the accessed item. The access is both read and write.

The index is zero-based and can maximally be `SlotCount-1 (??)`. Providing an invalid index will result in an exception.

See also: `TCache.MRUSlot (??)`

### 6.5.12 TCache.MRUSlot

**Synopsis:** Most recent item slot.

**Declaration:** `Property MRUSlot : PCacheSlot`

**Visibility:** `public`

**Access:** Read, Write

**Description:** `MRUSlot` points to the most recent used slot. The most recent used slot is updated when the list is accessed through the `Data (??)` property, or when an item is added to the list with `Add (??)` or `AddNew (??)`

See also: `TCache.Add (??)`, `TCache.AddNew (??)`, `TCache.Data (??)`, `TCache.LRUSlot (??)`

### 6.5.13 TCache.LRUSlot

Synopsis: Last used item

Declaration: Property LRUSlot : PCacheSlot

Visibility: public

Access: Read

Description: LRUSlot points to the least recent used slot. It is the last item in the chain of slots.

See also: TCache.Add (??), TCache.AddNew (??), TCache.Data (??), TCache.MRUSlot (??)

### 6.5.14 TCache.SlotCount

Synopsis: Number of slots in the list

Declaration: Property SlotCount : Integer

Visibility: public

Access: Read,Write

Description: SlotCount is the number of slots in the list. Its initial value is set when the TCache instance is created, but this can be changed at any time. If items are added to the list and the list is full, then the number of slots is not increased, but the least used item is dropped from the list. In that case OnFreeSlot (??) is called.

See also: TCache.Create (??), TCache.Data (??), TCache.Slots (??)

### 6.5.15 TCache.Slots

Synopsis: Indexed array to the slots

Declaration: Property Slots[SlotIndex: Integer]: PCacheSlot

Visibility: public

Access: Read

Description: Slots provides index-based access to the TCacheSlot records in the list. Accessing the records directly does not change their position in the MRU list.

The index is zero-based and can maximally be SlotCount-1 (??). Providing an invalid index will result in an exception.

See also: TCache.Data (??), TCache.SlotCount (??)

### 6.5.16 TCache.OnIsDataEqual

Synopsis: Event to compare 2 items.

Declaration: Property OnIsDataEqual : TOnIsDataEqual

Visibility: public

Access: Read,Write



**Description:** `OnIsDataEqual` is used by `FindSlot (??)` and `IndexOf (??)` to compare items when looking for a particular item. These functions are called by the `Add (??)` method. Failing to set this event will result in an exception. The function should return `True` if the 2 data pointers should be considered equal.

See also: `TCache.FindSlot (??)`, `TCache.IndexOf (??)`, `TCache.Add (??)`

### 6.5.17 TCache.OnFreeSlot

**Synopsis:** Event called when a slot is freed

**Declaration:** `Property OnFreeSlot : TOnFreeSlot`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `OnFreeSlot` is called when an item needs to be freed, i.e. when a new item is added to a full list, and the least recent used item needs to be dropped from the list.

The cache class instance and the index of the item to be removed are passed to the callback.

See also: `TCache.Add (??)`, `TCache.AddNew (??)`, `TCache.SlotCount (??)`

## Chapter 7

# Reference for unit 'contrns'

### 7.1 Used units

Table 7.1: Used units by unit 'contrns'

Name	Page
Classes	??
System	??
sysutils	??

### 7.2 Overview

The `contrns` unit implements various general-purpose classes:

**Object lists** lists that manage objects instead of pointers, and which automatically dispose of the objects.

**Component lists** lists that manage components instead of pointers, and which automatically dispose the components.

**Class lists** lists that manage class pointers instead of pointers.

**Stacks** Stack classes to push/pop pointers or objects

**Queues** Classes to manage a FIFO list of pointers or objects

**Hash lists** General-purpose Hash lists.

### 7.3 Constants, types and variables

#### 7.3.1 Constants

`MaxHashListSize = Maxint div 16`

`MaxHashListSize` is the maximum number of elements a hash list can contain.

```
MaxHashStrSize = Maxint
```

MaxHashStrSize is the maximum amount of data for the key string values. The key strings are kept in a continuous memory area. This constant determines the maximum size of this memory area.

```
MaxHashTableSize = Maxint div 4
```

MaxHashTableSize is the maximum number of elements in the hash.

```
MaxItemsPerHash = 3
```

MaxItemsPerHash is the threshold above which the hash is expanded. If the number of elements in a hash bucket becomes larger than this value, the hash size is increased.

### 7.3.2 Types

```
PBucket = ^TBucket
```

Pointer to TBucket (106)" type.

```
PHashItem = ^THashItem
```

PHashItem is a pointer type, pointing to the THashItem (108) record.

```
PHashItemList = ^THashItemList
```

PHashItemList is a pointer to the THashItemList (108). It's used in the TFPHashList (125) as a pointer to the memory area containing the hash item records.

```
PHashTable = ^THashTable
```

PHashTable is a pointer to the THashTable (108). It's used in the TFPHashList (125) as a pointer to the memory area containing the hash values.

```
TBucket = record
  Count : Integer;
  Items : TBucketItemArray;
end
```

TBucket describes 1 bucket in the TCustomBucketList (116) class. It is a container for TBucketItem (107) records. It should never be used directly.

```
TBucketArray = Array of TBucket
```

Array of TBucket (106) records.

```
TBucketItem = record
  Item : Pointer;
  Data : Pointer;
end
```

TBucketItem is a record used for internal use in TCustomBucketList (116). It should not be necessary to use it directly.

TBucketItemArray = Array of TBucketItem

Array of TBucketItem records

TBucketListSizes = (bl2,bl4,bl8,bl16,bl32,bl64,bl128,bl256)

Table 7.2: Enumeration values for type TBucketListSizes

Value	Explanation
bl128	List with 128 buckets
bl16	List with 16 buckets
bl2	List with 2 buckets
bl256	List with 256 buckets
bl32	List with 32 buckets
bl4	List with 4 buckets
bl64	List with 64 buckets
bl8	List with 8 buckets

TBucketListSizes is used to set the bucket list size: It specified the number of buckets created by TBucketList (109).

TBucketProc = procedure(AInfo: Pointer;AItem: Pointer;AData: Pointer;  
out AContinue: Boolean)

TBucketProc is the prototype for the TCustomBucketList.Foreach (??) call. It is the plain procedural form. The Continue parameter can be set to False to indicate that the Foreach call should stop the iteration.

For a procedure of object (a method) callback, see the TBucketProcObject (107) prototype.

TBucketProcObject = procedure(AItem: Pointer;AData: Pointer;  
out AContinue: Boolean) of object

TBucketProcObject is the prototype for the TCustomBucketList.Foreach (??) call. It is the method (procedure of object) form. The Continue parameter can be set to False to indicate that the Foreach call should stop the iteration.

For a plain procedural callback, see the TBucketProc (107) prototype.

TDataIteratorMethod = procedure(Item: Pointer;const Key: String;  
var Continue: Boolean) of object

TDataIteratorMethod is a callback prototype for the TFPDataHashTable.Iterate (??) method. It is called for each data pointer in the hash list, passing the key (key) and data pointer (item) for each item in the list. If Continue is set to false, the iteration stops.

THashFunction = function(const S: String;const TableSize: LongWord)  
: LongWord

THashFunction is the prototype for a hash calculation function. It should calculate a hash of string S, where the hash table size is TableSize. The return value should be the hash value.

```
THashItem = record
  HashValue : LongWord;
  StrIndex : Integer;
  NextIndex : Integer;
  Data : Pointer;
end
```

THashItem is used internally in the hash list. It should never be used directly.

```
THashItemList = Array[0..MaxHashListSize-1] of THashItem
```

THashItemList is an array type, primarily used to be able to define the PHashItemList (106) type. It's used in the TFPHashList (125) class.

```
THashTable = Array[0..MaxHashTableSize-1] of Integer
```

THashTable defines an array of integers, used to hold hash values. It's mainly used to define the PHashTable (106) class.

```
THTCustomNodeClass = Class of THTCustomNode
```

THTCustomNodeClass was used by TFPCustomHashTable (118) to decide which class should be created for elements in the list.

```
THTNode = THTDataNode
```

THTNode is provided for backwards compatibility.

```
TIteratorMethod = TDataIteratorMethod
```

TIteratorMethod is used in an internal TFPDataHashTable (124) method.

```
TObjectIteratorMethod = procedure(Item: TObject;const Key: String;
                                   var Continue: Boolean) of object
```

TObjectIteratorMethod is the iterator callback prototype. It is used to iterate over all items in the hash table, and is called with each key value (Key) and associated object (Item). If Continue is set to false, the iteration stops.

```
TObjectListCallback = procedure(data: TObject;arg: pointer) of object
```

TObjectListCallback is used as the prototype for the TFPObjectList.ForEachCall (??) link call when a method should be called. The Data argument will contain each of the objects in the list in turn, and the Data argument will contain the data passed to the ForEachCall call.

```
TObjectListStaticCallback = procedure(data: TObject;arg: pointer)
```

`TObjectListCallback` is used as the prototype for the `TFPObjectList.ForEachCall (??)` link call when a plain procedure should be called. The `Data` argument will contain each of the objects in the list in turn, and the `Data` argument will contain the data passed to the `ForEachCall` call.

```
TStringIteratorMethod = procedure(Item: String;const Key: String;
                                var Continue: Boolean) of object
```

`TStringIteratorMethod` is the callback prototype for the `Iterate (??)` method. It is called for each element in the hash table, with the string. If `Continue` is set to `false`, the iteration stops.

## 7.4 Procedures and functions

### 7.4.1 RSHash

Synopsis: Standard hash value calculating function.

Declaration: `function RSHash(const S: String;const TableSize: LongWord) : LongWord`

Visibility: default

Description: `RSHash` is the standard hash calculating function used in the `TFPCustomHashTable (118)` hash class. It's Robert Sedgwick's "Algorithms in C" hash function.

Errors: None.

See also: `TFPCustomHashTable (118)`

## 7.5 EDuplicate

### 7.5.1 Description

Exception raised when a key is stored twice in a hash table.

See also: `TFPCustomHashTable.Add (??)`

## 7.6 EKeyNotFound

### 7.6.1 Description

Exception raised when a key is not found.

See also: `TFPCustomHashTable.Delete (??)`

## 7.7 TBucketList

### 7.7.1 Description

`TBucketList` is a descendent of `TCustomBucketList` which allows to specify a bucket count which is a multiple of 2, up to 256 buckets. The size is passed to the constructor and cannot be changed in the lifetime of the bucket list instance.

The buckets for an item is determined by looking at the last bits of the item pointer: For 2 buckets, the last bit is examined, for 4 buckets, the last 2 bits are taken and so on. The algorithm takes into account the average granularity (4) of heap pointers.

See also: [TCustomBucketList \(116\)](#)

### 7.7.2 Method overview

Page	Property	Description
<a href="#">110</a>	Create	Create a new <code>TBucketList</code> instance.

### 7.7.3 TBucketList.Create

Synopsis: Create a new `TBucketList` instance.

Declaration: constructor `Create (ABuckets: TBucketListSizes)`

Visibility: public

Description: `Create` instantiates a new bucketlist instance with a number of buckets determined by `ABuckets`. After creation, the number of buckets can no longer be changed.

Errors: If not enough memory is available to create the instance, an exception may be raised.

See also: [TBucketListSizes \(107\)](#)

## 7.8 TClassList

### 7.8.1 Description

`TClassList` is a `Tlist` (??) descendent which stores class references instead of pointers. It introduces no new behaviour other than ensuring all stored pointers are class pointers.

The `OwnsObjects` property as found in `TComponentList` and `TObjectList` is not implemented as there are no actual instances.

See also: [#rtl.classes.tlist \(??\)](#), [TComponentList \(113\)](#), [TObjectList \(157\)](#)

### 7.8.2 Method overview

Page	Property	Description
<a href="#">111</a>	Add	Add a new class pointer to the list.
<a href="#">111</a>	Extract	Extract a class pointer from the list.
<a href="#">112</a>	First	Return first non-nil class pointer
<a href="#">111</a>	IndexOf	Search for a class pointer in the list.
<a href="#">112</a>	Insert	Insert a new class pointer in the list.
<a href="#">112</a>	Last	Return last non- <code>Nil</code> class pointer
<a href="#">111</a>	Remove	Remove a class pointer from the list.

### 7.8.3 Property overview

Page	Property	Access	Description
<a href="#">112</a>	Items	rw	Index based access to class pointers.

### 7.8.4 TClassList.Add

Synopsis: Add a new class pointer to the list.

Declaration: `function Add(AClass: TClass) : Integer`

Visibility: `public`

Description: `Add` adds `AClass` to the list, and returns the position at which it was added. It simply overrides the `TList` (??) behaviour, and introduces no new functionality.

Errors: If not enough memory is available to expand the list, an exception may be raised.

See also: `TClassList.Extract` (??), `#rtl.classes.tlist.add` (??)

### 7.8.5 TClassList.Extract

Synopsis: Extract a class pointer from the list.

Declaration: `function Extract(Item: TClass) : TClass`

Visibility: `public`

Description: `Extract` extracts a class pointer `Item` from the list, if it is present in the list. It returns the extracted class pointer, or `Nil` if the class pointer was not present in the list. It simply overrides the implementation in `TList` so it accepts a class pointer instead of a simple pointer. No new behaviour is introduced.

Errors: None.

See also: `TClassList.Remove` (??), `#rtl.classes.Tlist.Extract` (??)

### 7.8.6 TClassList.Remove

Synopsis: Remove a class pointer from the list.

Declaration: `function Remove(AClass: TClass) : Integer`

Visibility: `public`

Description: `Remove` removes a class pointer `Item` from the list, if it is present in the list. It returns the index of the removed class pointer, or `-1` if the class pointer was not present in the list. It simply overrides the implementation in `TList` so it accepts a class pointer instead of a simple pointer. No new behaviour is introduced.

Errors: None.

See also: `TClassList.Extract` (??), `#rtl.classes.Tlist.Remove` (??)

### 7.8.7 TClassList.IndexOf

Synopsis: Search for a class pointer in the list.

Declaration: `function IndexOf(AClass: TClass) : Integer`

Visibility: `public`

Description: `IndexOf` searches for `AClass` in the list, and returns its position if it was found, or `-1` if it was not found in the list.

Errors: None.

See also: `#rtl.classes.tlist.indexof` (??)



### 7.8.8 TClassList.First

Synopsis: Return first non-nil class pointer

Declaration: `function First : TClass`

Visibility: public

Description: `First` returns a reference to the first non-`Nil` class pointer in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TClassList.Last` (??), `TClassList.Pack` (??)

### 7.8.9 TClassList.Last

Synopsis: Return last non-`Nil` class pointer

Declaration: `function Last : TClass`

Visibility: public

Description: `Last` returns a reference to the last non-`Nil` class pointer in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TClassList.First` (??), `TClassList.Pack` (??)

### 7.8.10 TClassList.Insert

Synopsis: Insert a new class pointer in the list.

Declaration: `procedure Insert (Index: Integer; AClass: TClass)`

Visibility: public

Description: `Insert` inserts a class pointer in the list at position `Index`. It simply overrides the parent implementation so it only accepts class pointers. It introduces no new behaviour.

Errors: None.

See also: `#rtl.classes.TList.Insert` (??), `TClassList.Add` (??), `TClassList.Remove` (??)

### 7.8.11 TClassList.Items

Synopsis: Index based access to class pointers.

Declaration: `Property Items [Index: Integer]: TClass; default`

Visibility: public

Access: Read, Write

Description: `Items` provides index-based access to the class pointers in the list. `TClassList` overrides the default `Items` implementation of `TList` so it returns class pointers instead of pointers.

See also: `#rtl.classes.TList.Items` (??), `#rtl.classes.TList.Count` (??)

## 7.9 TComponentList

### 7.9.1 Description

`TComponentList` is a `TObjectList` (157) descendent which has as the default array property `TComponents` (??) instead of objects. It overrides some methods so only components can be added.

In difference with `TObjectList` (157), `TComponentList` removes any `TComponent` from the list if the `TComponent` instance was freed externally. It uses the `FreeNotification` mechanism for this.

See also: `#rtl.classes.TList` (??), `TFPObjectList` (144), `TObjectList` (157), `TClassList` (110)

### 7.9.2 Method overview

Page	Property	Description
113	Add	Add a component to the list.
113	Destroy	Destroys the instance
114	Extract	Remove a component from the list without destroying it.
115	First	First non-nil instance in the list.
114	IndexOf	Search for an instance in the list
115	Insert	Insert a new component in the list
115	Last	Last non-nil instance in the list.
114	Remove	Remove a component from the list, possibly destroying it.

### 7.9.3 Property overview

Page	Property	Access	Description
115	Items	rw	Index-based access to the elements in the list.

### 7.9.4 TComponentList.Destroy

Synopsis: Destroys the instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` unhooks the free notification handler and then calls the inherited `destroy` to clean up the `TComponentList` instance.

Errors: None.

See also: `TObjectList` (157), `#rtl.classes.TComponent` (??)

### 7.9.5 TComponentList.Add

Synopsis: Add a component to the list.

Declaration: `function Add(AComponent: TComponent) : Integer`

Visibility: `public`

Description: `Add` overrides the `Add` operation of it's ancestors, so it only accepts `TComponent` instances. It introduces no new behaviour.

The function returns the index at which the component was added.

Errors: If not enough memory is available to expand the list, an exception may be raised.

See also: `TObjectList.Add` (??)

### 7.9.6 TComponentList.Extract

Synopsis: Remove a component from the list without destroying it.

Declaration: `function Extract (Item: TComponent) : TComponent`

Visibility: public

Description: `Extract` removes a component (`Item`) from the list, without destroying it. It overrides the implementation of `TObjectList` (157) so only `TComponent` descendents can be extracted. It introduces no new behaviour.

`Extract` returns the instance that was extracted, or `Nil` if no instance was found.

See also: `TComponentList.Remove` (??), `TObjectList.Extract` (??)

### 7.9.7 TComponentList.Remove

Synopsis: Remove a component from the list, possibly destroying it.

Declaration: `function Remove (AComponent: TComponent) : Integer`

Visibility: public

Description: `Remove` removes `item` from the list, and if the list owns it's items, it also destroys it. It returns the index of the item that was removed, or -1 if no item was removed.

`Remove` simply overrides the implementation in `TObjectList` (157) so it only accepts `TComponent` descendents. It introduces no new behaviour.

Errors: None.

See also: `TComponentList.Extract` (??), `TObjectList.Remove` (??)

### 7.9.8 TComponentList.IndexOf

Synopsis: Search for an instance in the list

Declaration: `function IndexOf (AComponent: TComponent) : Integer`

Visibility: public

Description: `IndexOf` searches for an instance in the list and returns it's position in the list. The position is zero-based. If no instance is found, -1 is returned.

`IndexOf` just overrides the implementation of the parent class so it accepts only `TComponent` instances. It introduces no new behaviour.

Errors: None.

See also: `TObjectList.IndexOf` (??)

### 7.9.9 TComponentList.First

Synopsis: First non-nil instance in the list.

Declaration: `function First : TComponent`

Visibility: public

Description: `First` overrides the implementation of it's ancestors to return the first non-nil instance of `TComponent` in the list. If no non-nil instance is found, `Nil` is returned.

Errors: None.

See also: `TComponentList.Last` (??), `TObjectList.First` (??)

### 7.9.10 TComponentList.Last

Synopsis: Last non-nil instance in the list.

Declaration: `function Last : TComponent`

Visibility: public

Description: `Last` overrides the implementation of it's ancestors to return the last non-nil instance of `TComponent` in the list. If no non-nil instance is found, `Nil` is returned.

Errors: None.

See also: `TComponentList.First` (??), `TObjectList.Last` (??)

### 7.9.11 TComponentList.Insert

Synopsis: Insert a new component in the list

Declaration: `procedure Insert (Index: Integer; AComponent: TComponent)`

Visibility: public

Description: `Insert` inserts a `TComponent` instance (`AComponent`) in the list at position `Index`. It simply overrides the parent implementation so it only accepts `TComponent` instances. It introduces no new behaviour.

Errors: None.

See also: `TObjectList.Insert` (??), `TComponentList.Add` (??), `TComponentList.Remove` (??)

### 7.9.12 TComponentList.Items

Synopsis: Index-based access to the elements in the list.

Declaration: `Property Items[Index: Integer]: TComponent; default`

Visibility: public

Access: Read,Write

Description: `Items` provides access to the components in the list using an index. It simply overrides the default property of the parent classes so it returns/accepts `TComponent` instances only. Note that the index is zero based.

See also: `TObjectList.Items` (??)

## 7.10 TCustomBucketList

### 7.10.1 Description

TCustomBucketList is an associative list using buckets for storage. It scales better than a regular TList (??) list class, especially when an item must be searched in the list.

Since the list associates a data pointer with each item pointer, it follows that each item pointer must be unique, and can be added to the list only once.

The TCustomBucketList class does not determine the number of buckets or the bucket hash mechanism, this must be done by descendent classes such as TBucketList (109). TCustomBucketList only takes care of storage and retrieval of items in the various buckets.

Because TCustomBucketList is an abstract class - it does not determine the number of buckets - one should never instantiate an instance of TCustomBucketList, but always use a descendent class such as TCustomBucketList (116).

See also: TBucketList (109)

### 7.10.2 Method overview

Page	Property	Description
<a href="#">117</a>	Add	Add an item to the list
<a href="#">117</a>	Assign	Assign one bucket list to another
<a href="#">116</a>	Clear	Clear the list
<a href="#">116</a>	Destroy	Frees the bucketlist from memory
<a href="#">117</a>	Exists	Check if an item exists in the list.
<a href="#">117</a>	Find	Find an item in the list
<a href="#">118</a>	ForEach	Loop over all items.
<a href="#">118</a>	Remove	Remove an item from the list.

### 7.10.3 Property overview

Page	Property	Access	Description
<a href="#">118</a>	Data	rw	Associative array for data pointers

### 7.10.4 TCustomBucketList.Destroy

Synopsis: Frees the bucketlist from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees all storage for the buckets from memory. The items themselves are not freed from memory.

### 7.10.5 TCustomBucketList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: `public`

**Description:** `Clear` clears the list. The items and their data themselves are not disposed of, this must be done separately. `Clear` only removes all references to the items from the list.

**Errors:** None.

**See also:** `TCustomBucketList.Add` (??)

### 7.10.6 `TCustomBucketList.Add`

**Synopsis:** Add an item to the list

**Declaration:** `function Add(AItem: Pointer; AData: Pointer) : Pointer`

**Visibility:** `public`

**Description:** `Add` adds `AItem` with it's associated `AData` to the list and returns `AData`.

**Errors:** If `AItem` is already in the list, an `EListError` exception will be raised.

**See also:** `TCustomBucketList.Exists` (??), `TCustomBucketList.Clear` (??)

### 7.10.7 `TCustomBucketList.Assign`

**Synopsis:** Assign one bucket list to another

**Declaration:** `procedure Assign(AList: TCustomBucketList)`

**Visibility:** `public`

**Description:** `Assign` is implemented by `TCustomBucketList` to copy the contents of another bucket list to the bucket list. It clears the contents prior to the copy operation.

**See also:** `TCustomBucketList.Add` (??), `TCustomBucketList.Clear` (??)

### 7.10.8 `TCustomBucketList.Exists`

**Synopsis:** Check if an item exists in the list.

**Declaration:** `function Exists(AItem: Pointer) : Boolean`

**Visibility:** `public`

**Description:** `Exists` searches the list and returns `True` if the `AItem` is already present in the list. If the item is not yet in the list, `False` is returned.

If the data pointer associated with `AItem` is also needed, then it is better to use `Find` (??).

**See also:** `TCustomBucketList.Find` (??)

### 7.10.9 `TCustomBucketList.Find`

**Synopsis:** Find an item in the list

**Declaration:** `function Find(AItem: Pointer; out AData: Pointer) : Boolean`

**Visibility:** `public`

**Description:** `Find` searches for `AItem` in the list and returns the data pointer associated with it in `AData` if the item was found. In that case the return value is `True`. If `AItem` is not found in the list, `False` is returned.

**See also:** `TCustomBucketList.Exists` (??)

### 7.10.10 TCustomBucketList.ForEach

Synopsis: Loop over all items.

Declaration: `function ForEach(AProc: TBucketProc; AInfo: Pointer) : Boolean`  
`function ForEach(AProc: TBucketProcObject) : Boolean`

Visibility: public

Description: Foreach loops over all items in the list and calls AProc, passing it in turn each item in the list.

AProc exists in 2 variants: one which is a simple procedure, and one which is a method. In the case of the simple procedure, the AInfo argument is passed as well in each call to AProc.

The loop stops when all items have been processed, or when the AContinue argument of AProc contains False on return.

The result of the function is True if all items were processed, or False if the loop was interrupted with a AContinue return of False.

Errors: None.

See also: TCustomBucketList.Data (??)

### 7.10.11 TCustomBucketList.Remove

Synopsis: Remove an item from the list.

Declaration: `function Remove(AItem: Pointer) : Pointer`

Visibility: public

Description: Remove removes AItem from the list, and returns the associated data pointer of the removed item. If the item was not in the list, then Nil is returned.

See also: Find (??)

### 7.10.12 TCustomBucketList.Data

Synopsis: Associative array for data pointers

Declaration: `Property Data[AItem: Pointer]: Pointer; default`

Visibility: public

Access: Read, Write

Description: Data provides direct access to the Data pointers associated with the AItem pointers. If AItem is not in the list of pointers, an EListError exception will be raised.

See also: TCustomBucketList.Find (??), TCustomBucketList.Exists (??)

## 7.11 TFPCustomHashTable

### 7.11.1 Description

TFPCustomHashTable is a general-purpose hashing class. It can store string keys and pointers associated with these strings. The hash mechanism is configurable and can be optionally be specified

when a new instance of the class is created; A default hash mechanism is implemented in `RSHash` (109).

A `TFPHasList` should be used when fast lookup of data based on some key is required. The other container objects only offer linear search methods, while the hash list offers faster search mechanisms.

See also: `THTCustomNode` (152), `TFPObjectList` (144), `RSHash` (109)

### 7.11.2 Method overview

Page	Property	Description
120	<code>ChangeTableSize</code>	Change the table size of the hash table.
120	<code>Clear</code>	Clear the hash table.
119	<code>Create</code>	Instantiate a new <code>TFPCustomHashTable</code> instance using the default hash mechanism
120	<code>CreateWith</code>	Instantiate a new <code>TFPCustomHashTable</code> instance with given algorithm and size
121	<code>Delete</code>	Delete a key from the hash list.
120	<code>Destroy</code>	Free the hash table.
121	<code>Find</code>	Search for an item with a certain key value.
121	<code>IsEmpty</code>	Check if the hash table is empty.

### 7.11.3 Property overview

Page	Property	Access	Description
123	<code>AVGChainLen</code>	r	Average chain length
122	<code>Count</code>	r	Number of items in the hash table.
124	<code>Density</code>	r	Number of filled slots
121	<code>HashFunction</code>	rw	Hash function currently in use
122	<code>HashTable</code>	r	Hash table instance
122	<code>HashTableSize</code>	rw	Size of the hash table
123	<code>LoadFactor</code>	r	Fraction of count versus size
123	<code>MaxChainLength</code>	r	Maximum chain length
123	<code>NumberOfCollisions</code>	r	Number of extra items
122	<code>VoidSlots</code>	r	Number of empty slots in the hash table.

### 7.11.4 `TFPCustomHashTable.Create`

**Synopsis:** Instantiate a new `TFPCustomHashTable` instance using the default hash mechanism

**Declaration:** `constructor Create`

**Visibility:** `public`

**Description:** `Create` creates a new instance of `TFPCustomHashTable` with hash size 196613 and hash algorithm `RSHash` (109)

**Errors:** If no memory is available, an exception may be raised.

See also: `CreateWith` (??)



### 7.11.5 TFPCustomHashTable.CreateWith

Synopsis: Instantiate a new `TFPCustomHashTable` instance with given algorithm and size

Declaration: constructor `CreateWith(AHashTableSize: LongWord;  
aHashFunc: THashFunction)`

Visibility: public

Description: `CreateWith` creates a new instance of `TFPCustomHashTable` with hash size `AHashTableSize` and hash calculating algorithm `aHashFunc`.

Errors: If no memory is available, an exception may be raised.

See also: `Create` (??)

### 7.11.6 TFPCustomHashTable.Destroy

Synopsis: Free the hash table.

Declaration: destructor `Destroy`; Override

Visibility: public

Description: `Destroy` removes the hash table from memory. If any data was associated with the keys in the hash table, then this data is not freed. This must be done by the programmer.

Errors: None.

See also: `Destroy` (??), `Create` (??), `Create` (??), `THTCustomNode.Data` (??)

### 7.11.7 TFPCustomHashTable.ChangeTableSize

Synopsis: Change the table size of the hash table.

Declaration: procedure `ChangeTableSize(const ANewSize: LongWord)`; Virtual

Visibility: public

Description: `ChangeTableSize` changes the size of the hash table: it recomputes the hash value for all of the keys in the table, so this is an expensive operation.

Errors: If no memory is available, an exception may be raised.

See also: `HashTableSize` (??)

### 7.11.8 TFPCustomHashTable.Clear

Synopsis: Clear the hash table.

Declaration: procedure `Clear`; Virtual

Visibility: public

Description: `Clear` removes all keys and their associated data from the hash table. The data itself is not freed from memory, this should be done by the programmer.

Errors: None.

See also: `Destroy` (??)

### 7.11.9 TFPCustomHashTable.Delete

Synopsis: Delete a key from the hash list.

Declaration: `procedure Delete(const aKey: String); Virtual`

Visibility: public

Description: `Delete` deletes all keys with value `AKey` from the hash table. It does not free the data associated with key. If `AKey` is not in the list, nothing is removed.

Errors: None.

See also: `TFPCustomHashTable.Find (??)`, `TFPCustomHashTable.Add (??)`

### 7.11.10 TFPCustomHashTable.Find

Synopsis: Search for an item with a certain key value.

Declaration: `function Find(const aKey: String) : THTCustomNode`

Visibility: public

Description: `Find` searches for the `THTCustomNode` (152) instance with key value equal to `Akey` and if it finds it, it returns the instance. If no matching value is found, `Nil` is returned.

Note that the instance returned by this function cannot be freed; If it should be removed from the hash table, the `Delete (??)` method should be used instead.

Errors: None.

See also: `Add (??)`, `Delete (??)`

### 7.11.11 TFPCustomHashTable.IsEmpty

Synopsis: Check if the hash table is empty.

Declaration: `function IsEmpty : Boolean`

Visibility: public

Description: `IsEmpty` returns `True` if the hash table contains no elements, or `False` if there are still elements in the hash table.

See also: `TFPCustomHashTable.Count (??)`, `TFPCustomHashTable.HashTableSize (??)`, `TFPCustomHashTable.AVGChainLen (??)`, `TFPCustomHashTable.MaxChainLength (??)`

### 7.11.12 TFPCustomHashTable.HashFunction

Synopsis: Hash function currently in use

Declaration: `Property HashFunction : THashFunction`

Visibility: public

Access: Read,Write

Description: `HashFunction` is the hash function currently in use to calculate hash values from keys. The property can be set, this simply calls `SetHashFunction (??)`. Note that setting the hash function does NOT the hash value of all keys to be recomputed, so changing the value while there are still keys in the table is not a good idea.

See also: `SetHashFunction (??)`, `HashTableSize (??)`

### 7.11.13 TFPCustomHashTable.Count

Synopsis: Number of items in the hash table.

Declaration: `Property Count : LongWord`

Visibility: public

Access: Read

Description: `Count` is the number of items in the hash table.

See also: `TFPCustomHashTable.IsEmpty (??)`, `TFPCustomHashTable.HashTableSize (??)`, `TFPCustomHashTable.AVGChainLen (??)`, `TFPCustomHashTable.MaxChainLength (??)`

### 7.11.14 TFPCustomHashTable.HashTableSize

Synopsis: Size of the hash table

Declaration: `Property HashTableSize : LongWord`

Visibility: public

Access: Read,Write

Description: `HashTableSize` is the size of the hash table. It can be set, in which case it will be rounded to the nearest prime number suitable for RSHash.

See also: `TFPCustomHashTable.IsEmpty (??)`, `TFPCustomHashTable.Count (??)`, `TFPCustomHashTable.AVGChainLen (??)`, `TFPCustomHashTable.MaxChainLength (??)`, `TFPCustomHashTable.VoidSlots (??)`, `TFPCustomHashTable.Density (??)`

### 7.11.15 TFPCustomHashTable.HashTable

Synopsis: Hash table instance

Declaration: `Property HashTable : TFPObjectList`

Visibility: public

Access: Read

Description: `TFPCustomHashTable` is the internal list object (`TFPObjectList` (144)) used for the hash table. Each element in this table is again a `TFPObjectList` (144) instance or `Nil`.

### 7.11.16 TFPCustomHashTable.VoidSlots

Synopsis: Number of empty slots in the hash table.

Declaration: `Property VoidSlots : LongWord`

Visibility: public

Access: Read

Description: `VoidSlots` is the number of empty slots in the hash table. Calculating this is an expensive operation.

See also: `TFPCustomHashTable.IsEmpty (??)`, `TFPCustomHashTable.Count (??)`, `TFPCustomHashTable.AVGChainLen (??)`, `TFPCustomHashTable.MaxChainLength (??)`, `TFPCustomHashTable.LoadFactor (??)`, `TFPCustomHashTable.Density (??)`, `TFPCustomHashTable.NumberOfCollisions (??)`

### 7.11.17 TFPCustomHashTable.LoadFactor

Synopsis: Fraction of count versus size

Declaration: Property LoadFactor : double

Visibility: public

Access: Read

Description: LoadFactor is the ratio of elements in the table versus table size. Ideally, this should be as small as possible.

See also: TFPCustomHashTable.IsEmpty (??), TFPCustomHashTable.Count (??), TFPCustomHashTable.AVGChainLen (??), TFPCustomHashTable.MaxChainLength (??), TFPCustomHashTable.VoidSlots (??), TFPCustomHashTable.Density (??), TFPCustomHashTable.NumberOfCollisions (??)

### 7.11.18 TFPCustomHashTable.AVGChainLen

Synopsis: Average chain length

Declaration: Property AVGChainLen : double

Visibility: public

Access: Read

Description: AVGChainLen is the average chain length, i.e. the ratio of elements in the table versus the number of filled slots. Calculating this is an expensive operation.

See also: TFPCustomHashTable.IsEmpty (??), TFPCustomHashTable.Count (??), TFPCustomHashTable.LoadFactor (??), TFPCustomHashTable.MaxChainLength (??), TFPCustomHashTable.VoidSlots (??), TFPCustomHashTable.Density (??), TFPCustomHashTable.NumberOfCollisions (??)

### 7.11.19 TFPCustomHashTable.MaxChainLength

Synopsis: Maximum chain length

Declaration: Property MaxChainLength : LongWord

Visibility: public

Access: Read

Description: MaxChainLength is the length of the longest chain in the hash table. Calculating this is an expensive operation.

See also: TFPCustomHashTable.IsEmpty (??), TFPCustomHashTable.Count (??), TFPCustomHashTable.LoadFactor (??), TFPCustomHashTable.AvgChainLength (??), TFPCustomHashTable.VoidSlots (??), TFPCustomHashTable.Density (??), TFPCustomHashTable.NumberOfCollisions (??)

### 7.11.20 TFPCustomHashTable.NumberOfCollisions

Synopsis: Number of extra items

Declaration: Property NumberOfCollisions : LongWord

Visibility: public

Access: Read

**Description:** `NumberOfCollisions` is the number of items which are not the first item in a chain. If this number is too big, the hash size may be too small.

**See also:** `TFPCustomHashTable.IsEmpty` (??), `TFPCustomHashTable.Count` (??), `TFPCustomHashTable.LoadFactor` (??), `TFPCustomHashTable.AvgChainLength` (??), `TFPCustomHashTable.VoidSlots` (??), `TFPCustomHashTable.Density` (??)

### 7.11.21 TFPCustomHashTable.Density

**Synopsis:** Number of filled slots

**Declaration:** `Property Density : LongWord`

Visibility: public

Access: Read

**Description:** `Density` is the number of filled slots in the hash table.

**See also:** `TFPCustomHashTable.IsEmpty` (??), `TFPCustomHashTable.Count` (??), `TFPCustomHashTable.LoadFactor` (??), `TFPCustomHashTable.AvgChainLength` (??), `TFPCustomHashTable.VoidSlots` (??), `TFPCustomHashTable.Density` (??)

## 7.12 TFPDataHashTable

### 7.12.1 Description

`TFPDataHashTable` is a `TFPCustomHashTable` (118) descendent which stores simple data pointers together with the keys. In case the data associated with the keys are objects, it's better to use `TFPObjectHashTable` (142), or for string data, `TFPStringHashTable` (151) is more suitable. The data pointers are exposed with their keys through the `Items` (??) property.

**See also:** `TFPObjectHashTable` (142), `TFPStringHashTable` (151), `Items` (??)

### 7.12.2 Method overview

Page	Property	Description
<a href="#">124</a>	<code>Add</code>	Add a data pointer to the list.

### 7.12.3 Property overview

Page	Property	Access	Description
<a href="#">125</a>	<code>Items</code>	rw	Key-based access to the items in the table

### 7.12.4 TFPDataHashTable.Add

**Synopsis:** Add a data pointer to the list.

**Declaration:** `procedure Add(const aKey: String; AItem: pointer); Virtual`

Visibility: public

**Description:** Add adds a data pointer (AItem) to the list with key AKey.

**Errors:** If AKey already exists in the table, an exception is raised.

**See also:** TFPDataHashTable.Items (??)

### 7.12.5 TFPDataHashTable.Items

**Synopsis:** Key-based access to the items in the table

**Declaration:** `Property Items[index: String]: Pointer; default`

**Visibility:** public

**Access:** Read,Write

**Description:** Items provides access to the items in the hash table using their key: the array index Index is the key. A key which is not present will result in an Nil pointer.

**See also:** TFPStringHashTable.Add (??)

## 7.13 TFPHashList

### 7.13.1 Description

TFPHashList implements a fast hash class. The class is built for speed, therefore the key values can be shortstrings only, and the data can only be pointers.

if a base class for an own hash class is wanted, the TFPCustomHashTable (118) class can be used. If a hash class for objects is needed instead of pointers, the TFPHashObjectList (135) class can be used.

**See also:** TFPCustomHashTable (118), TFPHashObjectList (135), TFPDataHashTable (124), TFPStringHashTable (151)

### 7.13.2 Method overview

Page	Property	Description
<a href="#">127</a>	Add	Add a new key/data pair to the list
<a href="#">127</a>	Clear	Clear the list
<a href="#">126</a>	Create	Create a new instance of the hashlist
<a href="#">128</a>	Delete	Delete an item from the list.
<a href="#">126</a>	Destroy	Removes an instance of the hashlist from the heap
<a href="#">128</a>	Error	Raise an error
<a href="#">128</a>	Expand	Expand the list
<a href="#">129</a>	Extract	Extract a pointer from the list
<a href="#">129</a>	Find	Find data associated with key
<a href="#">129</a>	FindIndexOf	Return index of named item.
<a href="#">130</a>	FindWithHash	Find first element with given name and hash value
<a href="#">131</a>	ForEachCall	Call a procedure for each element in the list
<a href="#">128</a>	GetNextCollision	Get next collision number
<a href="#">127</a>	HashOfIndex	Return the hash value of an item by index
<a href="#">129</a>	IndexOf	Return the index of the data pointer
<a href="#">127</a>	NameOfIndex	Returns the key name of an item by index
<a href="#">130</a>	Pack	Remove nil pointers from the list
<a href="#">130</a>	Remove	Remove first instance of a pointer
<a href="#">130</a>	Rename	Rename a key
<a href="#">131</a>	ShowStatistics	Return some statistics for the list.

### 7.13.3 Property overview

Page	Property	Access	Description
<a href="#">131</a>	Capacity	rw	Capacity of the list.
<a href="#">131</a>	Count	rw	Current number of elements in the list.
<a href="#">132</a>	Items	rw	Indexed array with pointers
<a href="#">132</a>	List	r	Low-level hash list
<a href="#">132</a>	Strs	r	Low-level memory area with strings.

### 7.13.4 TFPHashList.Create

Synopsis: Create a new instance of the hashlist

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of `TFPHashList` on the heap and sets the hash capacity to 1.

See also: `TFPHashList.Destroy` (??)

### 7.13.5 TFPHashList.Destroy

Synopsis: Removes an instance of the hashlist from the heap

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the memory structures maintained by the hashlist and removes the `TFPHashList` instance from the heap.

`Destroy` should not be called directly, it's better to use `Free` or `FreeAndNil` instead.

See also: `TFPHashList.Create (??)`, `TFPHashList.Clear (??)`

### 7.13.6 TFPHashList.Add

Synopsis: Add a new key/data pair to the list

Declaration: `function Add(const AName: shortstring; Item: Pointer) : Integer`

Visibility: public

Description: `Add` adds a new data pointer (`Item`) with key `AName` to the list. It returns the position of the item in the list.

Errors: If not enough memory is available to hold the key and data, an exception may be raised.

See also: `TFPHashList.Extract (??)`, `TFPHashList.Remove (??)`, `TFPHashList.Delete (??)`

### 7.13.7 TFPHashList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` removes all items from the list. It does not free the data items themselves. It frees all memory needed to contain the items.

Errors: None.

See also: `TFPHashList.Extract (??)`, `TFPHashList.Remove (??)`, `TFPHashList.Delete (??)`, `TFPHashList.Add (??)`

### 7.13.8 TFPHashList.NameOfIndex

Synopsis: Returns the key name of an item by index

Declaration: `function NameOfIndex(Index: Integer) : ShortString`

Visibility: public

Description: `NameOfIndex` returns the key name of the item at position `Index`.

Errors: If `Index` is out of the valid range, an exception is raised.

See also: `TFPHashList.HashOfIndex (??)`, `TFPHashList.Find (??)`, `TFPHashList.FindIndexOf (??)`, `TFPHashList.FindWithHash (??)`

### 7.13.9 TFPHashList.HashOfIndex

Synopsis: Return the hash value of an item by index

Declaration: `function HashOfIndex(Index: Integer) : LongWord`

Visibility: public

Description: `HashOfIndex` returns the hash value of the item at position `Index`.



Errors: If `Index` is out of the valid range, an exception is raised.

See also: `TFPHashList.HashOfName (??)`, `TFPHashList.Find (??)`, `TFPHashList.FindIndexOf (??)`, `TFPHashList.FindWithHash (??)`

### 7.13.10 TFPHashList.GetNextCollision

Synopsis: Get next collision number

Declaration: `function GetNextCollision(Index: Integer) : Integer`

Visibility: public

Description: `GetNextCollision` returns the next collision in hash item `Index`. This is the count of items with the same hash.means that the next it

### 7.13.11 TFPHashList.Delete

Synopsis: Delete an item from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: public

Description: `Delete` deletes the item at position `Index`. The data to which it points is not freed from memory.

Errors: `TFPHashList.Extract (??)``TFPHashList.Remove (??)``TFPHashList.Add (??)`

### 7.13.12 TFPHashList.Error

Synopsis: Raise an error

Declaration: `class procedure Error(const Msg: String;Data: PtrInt)`

Visibility: default

Description: `Error` raises an `EListError` exception, with message `Msg`. The `Data` pointer is used to format the message.

### 7.13.13 TFPHashList.Expand

Synopsis: Expand the list

Declaration: `function Expand : TFPHashList`

Visibility: public

Description: `Expand` enlarges the capacity of the list if the maximum capacity was reached. It returns itself.

Errors: If not enough memory is available, an exception may be raised.

See also: `TFPHashList.Clear (??)`

### 7.13.14 TFPHashList.Extract

Synopsis: Extract a pointer from the list

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: public

Description: `Extract` removes the data item from the list, if it is in the list. It returns the pointer if it was removed from the list, `Nil` otherwise.

`Extract` does a linear search, and is not very efficient.

See also: `TFPHashList.Delete` (??), `TFPHashList.Remove` (??), `TFPHashList.Clear` (??)

### 7.13.15 TFPHashList.IndexOf

Synopsis: Return the index of the data pointer

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` returns the index of the first occurrence of pointer `Item`. If the item is not in the list, -1 is returned.

The performed search is linear, and not very efficient.

See also: `TFPHashList.HashOfIndex` (??), `TFPHashList.NameOfIndex` (??), `TFPHashList.Find` (??), `TFPHashList.FindIndexOf` (??), `TFPHashList.FindWithHash` (??)

### 7.13.16 TFPHashList.Find

Synopsis: Find data associated with key

Declaration: `function Find(const AName: shortstring) : Pointer`

Visibility: public

Description: `Find` searches (using the hash) for the data item associated with item `AName` and returns the data pointer associated with it. If the item is not found, `Nil` is returned. It uses the hash value of the key to perform the search.

See also: `TFPHashList.HashOfIndex` (??), `TFPHashList.NameOfIndex` (??), `TFPHashList.IndexOf` (??), `TFPHashList.FindIndexOf` (??), `TFPHashList.FindWithHash` (??)

### 7.13.17 TFPHashList.FindIndexOf

Synopsis: Return index of named item.

Declaration: `function FindIndexOf(const AName: shortstring) : Integer`

Visibility: public

Description: `FindIndexOf` returns the index of the key `AName`, or -1 if the key does not exist in the list. It uses the hash value to search for the key.

See also: `TFPHashList.HashOfIndex` (??), `TFPHashList.NameOfIndex` (??), `TFPHashList.IndexOf` (??), `TFPHashList.Find` (??), `TFPHashList.FindWithHash` (??)

### 7.13.18 TFPHashList.FindWithHash

Synopsis: Find first element with given name and hash value

Declaration: `function FindWithHash(const AName: shortstring; AHash: LongWord)  
: Pointer`

Visibility: public

Description: `FindWithHash` searches for the item with key `AName`. It uses the provided hash value `AHash` to perform the search. If the item exists, the data pointer is returned, if not, the result is `Nil`.

See also: `TFPHashList.HashOfIndex (??)`, `TFPHashList.NameOfIndex (??)`, `TFPHashList.IndexOf (??)`, `TFPHashList.Find (??)`, `TFPHashList.FindIndexOf (??)`

### 7.13.19 TFPHashList.Rename

Synopsis: Rename a key

Declaration: `function Rename(const AOldName: shortstring; const ANewName: shortstring)  
: Integer`

Visibility: public

Description: `Rename` renames key `AOldname` to `ANewName`. The hash value is recomputed and the item is moved in the list to it's new position.

Errors: If an item with `ANewName` already exists, an exception will be raised.

### 7.13.20 TFPHashList.Remove

Synopsis: Remove first instance of a pointer

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: public

Description: `Remove` removes the first occurrence of the data pointer `Item` in the list, if it is present. The return value is the removed data pointer, or `Nil` if no data pointer was removed.

See also: `TFPHashList.Delete (??)`, `TFPHashList.Clear (??)`, `TFPHashList.Extract (??)`

### 7.13.21 TFPHashList.Pack

Synopsis: Remove nil pointers from the list

Declaration: `procedure Pack`

Visibility: public

Description: `Pack` removes all `Nil` items from the list, and frees all unused memory.

See also: `TFPHashList.Clear (??)`

### 7.13.22 TFPHashList.ShowStatistics

Synopsis: Return some statistics for the list.

Declaration: `procedure ShowStatistics`

Visibility: `public`

Description: `ShowStatistics` prints some information about the hash list to standard output. It prints the following values:

**HashSize**Size of the hash table

**HashMean**Mean hash value

**HashStdDev**Standard deviation of hash values

**ListSize**Size and capacity of the list

**StringSize**Size and capacity of key strings

### 7.13.23 TFPHashList.ForEachCall

Synopsis: Call a procedure for each element in the list

Declaration: `procedure ForEachCall(proc2call: TListCallback;arg: pointer)`  
`procedure ForEachCall(proc2call: TListStaticCallback;arg: pointer)`

Visibility: `public`

Description: `ForEachCall` loops over the items in the list and calls `proc2call`, passing it the item and `arg`.

### 7.13.24 TFPHashList.Capacity

Synopsis: Capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: Read,Write

Description: `Capacity` returns the current capacity of the list. The capacity is expanded as more elements are added to the list. If a good estimate of the number of elements that will be added to the list, the property can be set to a sufficiently large value to avoid reallocation of memory each time the list needs to grow.

See also: `Count (??)`, `Items (??)`

### 7.13.25 TFPHashList.Count

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: Read,Write

Description: `Count` is the current number of elements in the list.

See also: `Capacity (??)`, `Items (??)`

### 7.13.26 TFPHashList.Items

Synopsis: Indexed array with pointers

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the pointers, the index runs from 0 to Count-1 (??).

Errors: Specifying an invalid index will result in an exception.

See also: Capacity (??), Count (??)

### 7.13.27 TFPHashList.List

Synopsis: Low-level hash list

Declaration: `Property List : PHashItemList`

Visibility: public

Access: Read

Description: `List` exposes the low-level item list (108). It should not be used directly.

See also: `Strs` (??), `THashItemList` (108)

### 7.13.28 TFPHashList.Strs

Synopsis: Low-level memory area with strings.

Declaration: `Property Strs : PChar`

Visibility: public

Access: Read

Description: `Strs` exposes the raw memory area with the strings.

See also: `List` (??)

## 7.14 TFPHashObject

### 7.14.1 Description

`TFPHashObject` is a `TObject` descendent which is aware of the `TFPHashObjectList` (135) class. It has a name property and an owning list: if the name is changed, it will reposition itself in the list which owns it. It offers methods to change the owning list: the object will correctly remove itself from the list which currently owns it, and insert itself in the new list.

See also: `TFPHashObject.Name` (??), `TFPHashObject.ChangeOwner` (??), `TFPHashObject.ChangeOwnerAndName` (??)

### 7.14.2 Method overview

Page	Property	Description
<a href="#">133</a>	ChangeOwner	Change the list owning the object.
<a href="#">134</a>	ChangeOwnerAndName	Simultaneously change the list owning the object and the name of the object.
<a href="#">133</a>	Create	Create a named instance, and insert in a hash list.
<a href="#">133</a>	CreateNotOwned	Create an instance not owned by any list.
<a href="#">134</a>	Rename	Rename the object

### 7.14.3 Property overview

Page	Property	Access	Description
<a href="#">134</a>	Hash	r	Hash value
<a href="#">134</a>	Name	r	Current name of the object

### 7.14.4 TFPHashObject.CreateNotOwned

Synopsis: Create an instance not owned by any list.

Declaration: `constructor CreateNotOwned`

Visibility: `public`

Description: `CreateNotOwned` creates an instance of `TFPHashObject` which is not owned by any `TFPHashObjectList` ([135](#)) hash list. It also has no name when created in this way.

See also: `TFPHashObject.Name` ([??](#)), `TFPHashObject.ChangeOwner` ([??](#)), `TFPHashObject.ChangeOwnerAndName` ([??](#))

### 7.14.5 TFPHashObject.Create

Synopsis: Create a named instance, and insert in a hash list.

Declaration: `constructor Create (HashObjectList: TFPHashObjectList;  
const s: shortstring)`

Visibility: `public`

Description: `Create` creates an instance of `TFPHashObject`, gives it the name `S` and inserts it in the hash list `HashObjectList` ([135](#)).

See also: `CreateNotOwned` ([??](#)), `TFPHashObject.ChangeOwner` ([??](#)), `TFPHashObject.Name` ([??](#))

### 7.14.6 TFPHashObject.ChangeOwner

Synopsis: Change the list owning the object.

Declaration: `procedure ChangeOwner (HashObjectList: TFPHashObjectList)`

Visibility: `public`

Description: `ChangeOwner` can be used to move the object between hash lists: The object will be removed correctly from the hash list that currently owns it, and will be inserted in the list `HashObjectList`.

Errors: If an object with the same name already is present in the new hash list, an exception will be raised.

See also: `ChangeOwnerAndName` ([??](#)), `Name` ([??](#))

### 7.14.7 TFPHashObject.ChangeOwnerAndName

Synopsis: Simultaneously change the list owning the object and the name of the object.

Declaration: `procedure ChangeOwnerAndName (HashObjectList: TFPHashObjectList;  
const s: shortstring)`

Visibility: public

Description: `ChangeOwnerAndName` can be used to move the object between hash lists: The object will be removed correctly from the hash list that currently owns it (using the current name), and will be inserted in the list `HashObjectList` with the new name `S`.

Errors: If the new name already is present in the new hash list, an exception will be raised.

See also: `ChangeOwner` (??), `Name` (??)

### 7.14.8 TFPHashObject.Rename

Synopsis: Rename the object

Declaration: `procedure Rename (const ANewName: shortstring)`

Visibility: public

Description: `Rename` changes the name of the object, and notifies the hash list of this change.

Errors: If the new name already is present in the hash list, an exception will be raised.

See also: `ChangeOwner` (??), `ChangeOwnerAndName` (??), `Name` (??)

### 7.14.9 TFPHashObject.Name

Synopsis: Current name of the object

Declaration: `Property Name : shortstring`

Visibility: public

Access: Read

Description: `Name` is the name of the object, it is stored in the hash list using this name as the key.

See also: `Rename` (??), `ChangeOwnerAndName` (??)

### 7.14.10 TFPHashObject.Hash

Synopsis: Hash value

Declaration: `Property Hash : LongWord`

Visibility: public

Access: Read

Description: `Hash` is the hash value of the object in the hash list that owns it.

See also: `Name` (??)

## 7.15 TFPHashObjectList

### 7.15.1 Method overview

Page	Property	Description
<a href="#">136</a>	Add	Add a new key/data pair to the list
<a href="#">136</a>	Clear	Clear the list
<a href="#">135</a>	Create	Create a new instance of the hashlist
<a href="#">137</a>	Delete	Delete an object from the list.
<a href="#">135</a>	Destroy	Removes an instance of the hashlist from the heap
<a href="#">137</a>	Expand	Expand the list
<a href="#">138</a>	Extract	Extract a object instance from the list
<a href="#">138</a>	Find	Find data associated with key
<a href="#">139</a>	FindIndexOf	Return index of named object.
<a href="#">139</a>	FindInstanceOf	Search an instance of a certain class
<a href="#">139</a>	FindWithHash	Find first element with given name and hash value
<a href="#">140</a>	ForEachCall	Call a procedure for each object in the list
<a href="#">137</a>	GetNextCollision	Get next collision number
<a href="#">137</a>	HashOfIndex	Return the hash valye of an object by index
<a href="#">138</a>	IndexOf	Return the index of the object instance
<a href="#">136</a>	NameOfIndex	Returns the key name of an object by index
<a href="#">140</a>	Pack	Remove nil object instances from the list
<a href="#">138</a>	Remove	Remove first occurrence of a object instance
<a href="#">139</a>	Rename	Rename a key
<a href="#">140</a>	ShowStatistics	Return some statistics for the list.

### 7.15.2 Property overview

Page	Property	Access	Description
<a href="#">140</a>	Capacity	rw	Capacity of the list.
<a href="#">141</a>	Count	rw	Current number of elements in the list.
<a href="#">141</a>	Items	rw	Indexed array with object instances
<a href="#">141</a>	List	r	Low-level hash list
<a href="#">141</a>	OwnsObjects	rw	Does the list own the objects it contains

### 7.15.3 TFPHashObjectList.Create

Synopsis: Create a new instance of the hashlist

Declaration: constructor `Create (FreeObjects: Boolean)`

Visibility: public

Description: `Create` creates a new instance of `TFPHashObjectList` on the heap and sets the hash capacity to 1.

If `FreeObjects` is `True` (the default), then the list owns the objects: when an object is removed from the list, it is destroyed (freed from memory). Clearing the list will free all objects in the list.

See also: `TFPHashObjectList.Destroy` (??), `TFPHashObjectList.OwnsObjects` (??)

### 7.15.4 TFPHashObjectList.Destroy

Synopsis: Removes an instance of the hashlist from the heap



**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` cleans up the memory structures maintained by the hashlist and removes the `TFPHashObjectList` instance from the heap. If the list owns its objects, they are freed from memory as well.

`Destroy` should not be called directly, it's better to use `Free` or `FreeAndNil` instead.

**See also:** `TFPHashObjectList.Create (??)`, `TFPHashObjectList.Clear (??)`

### 7.15.5 TFPHashObjectList.Clear

**Synopsis:** Clear the list

**Declaration:** `procedure Clear`

**Visibility:** `public`

**Description:** `Clear` removes all objects from the list. It does not free the objects themselves, unless `OwnsObjects (??)` is `True`. It always frees all memory needed to contain the objects.

**Errors:** None.

**See also:** `TFPHashObjectList.Extract (??)`, `TFPHashObjectList.Remove (??)`, `TFPHashObjectList.Delete (??)`, `TFPHashObjectList.Add (??)`

### 7.15.6 TFPHashObjectList.Add

**Synopsis:** Add a new key/data pair to the list

**Declaration:** `function Add(const AName: shortstring; AObject: TObject) : Integer`

**Visibility:** `public`

**Description:** `Add` adds a new object instance (`AObject`) with key `AName` to the list. It returns the position of the object in the list.

**Errors:** If not enough memory is available to hold the key and data, an exception may be raised. If an object with this name already exists in the list, an exception is raised.

**See also:** `TFPHashObjectList.Extract (??)`, `TFPHashObjectList.Remove (??)`, `TFPHashObjectList.Delete (??)`

### 7.15.7 TFPHashObjectList.NameOfIndex

**Synopsis:** Returns the key name of an object by index

**Declaration:** `function NameOfIndex(Index: Integer) : ShortString`

**Visibility:** `public`

**Description:** `NameOfIndex` returns the key name of the object at position `Index`.

**Errors:** If `Index` is out of the valid range, an exception is raised.

**See also:** `TFPHashObjectList.HashOfIndex (??)`, `TFPHashObjectList.Find (??)`, `TFPHashObjectList.FindIndexOf (??)`, `TFPHashObjectList.FindWithHash (??)`

### 7.15.8 TFPHashObjectList.HashOfIndex

Synopsis: Return the hash valye of an object by index

Declaration: `function HashOfIndex(Index: Integer) : LongWord`

Visibility: public

Description: `HashOfIndex` returns the hash value of the object at position `Index`.

Errors: If `Index` is out of the valid range, an exception is raised.

See also: `TFPHashObjectList.HashOfName` (??), `TFPHashObjectList.Find` (??), `TFPHashObjectList.FindIndexOf` (??), `TFPHashObjectList.FindWithHash` (??)

### 7.15.9 TFPHashObjectList.GetNextCollision

Synopsis: Get next collision number

Declaration: `function GetNextCollision(Index: Integer) : Integer`

Visibility: public

Description: Get next collision number

### 7.15.10 TFPHashObjectList.Delete

Synopsis: Delete an object from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: public

Description: `Delete` deletes the object at position `Index`. If `OwnsObjects` (??) is `True`, then the object itself is also freed from memory.

See also: `TFPHashObjectList.Extract` (??), `TFPHashObjectList.Remove` (??), `TFPHashObjectList.Add` (??), `OwnsObjects` (??)

### 7.15.11 TFPHashObjectList.Expand

Synopsis: Expand the list

Declaration: `function Expand : TFPHashObjectList`

Visibility: public

Description: `Expand` enlarges the capacity of the list if the maximum capacity was reached. It returns itself.

Errors: If not enough memory is available, an exception may be raised.

See also: `TFPHashObjectList.Clear` (??)

### 7.15.12 TFPHashObjectList.Extract

Synopsis: Extract a object instance from the list

Declaration: `function Extract (Item: TObject) : TObject`

Visibility: public

Description: `Extract` removes the data object from the list, if it is in the list. It returns the object instance if it was removed from the list, `Nil` otherwise. The object is *not* freed from memory, regardless of the value of `OwnsObjects` (??).

`Extract` does a linear search, and is not very efficient.

See also: `TFPHashObjectList.Delete` (??), `TFPHashObjectList.Remove` (??), `TFPHashObjectList.Clear` (??)

### 7.15.13 TFPHashObjectList.Remove

Synopsis: Remove first occurrence of a object instance

Declaration: `function Remove (AObject: TObject) : Integer`

Visibility: public

Description: `Remove` removes the first occurrence of the object instance `Item` in the list, if it is present. The return value is the location of the removed object instance, or `-1` if no object instance was removed.

If `OwnsObjects` (??) is `True`, then the object itself is also freed from memory.

See also: `TFPHashObjectList.Delete` (??), `TFPHashObjectList.Clear` (??), `TFPHashObjectList.Extract` (??)

### 7.15.14 TFPHashObjectList.IndexOf

Synopsis: Return the index of the object instance

Declaration: `function IndexOf (AObject: TObject) : Integer`

Visibility: public

Description: `IndexOf` returns the index of the first occurrence of object instance `AObject`. If the object is not in the list, `-1` is returned.

The performed search is linear, and not very efficient.

See also: `TFPHashObjectList.HashOfIndex` (??), `TFPHashObjectList.NameOfIndex` (??), `TFPHashObjectList.Find` (??), `TFPHashObjectList.FindIndexOf` (??), `TFPHashObjectList.FindWithHash` (??)

### 7.15.15 TFPHashObjectList.Find

Synopsis: Find data associated with key

Declaration: `function Find (const s: shortstring) : TObject`

Visibility: public

Description: `Find` searches (using the hash) for the data object associated with key `AName` and returns the data object instance associated with it. If the object is not found, `Nil` is returned. It uses the hash value of the key to perform the search.

See also: `TFPHashObjectList.HashOfIndex` (??), `TFPHashObjectList.NameOfIndex` (??), `TFPHashObjectList.IndexOf` (??), `TFPHashObjectList.FindIndexOf` (??), `TFPHashObjectList.FindWithHash` (??)

### 7.15.16 TFPHashObjectList.FindIndexOf

Synopsis: Return index of named object.

Declaration: `function FindIndexOf(const s: shortstring) : Integer`

Visibility: public

Description: `FindIndexOf` returns the index of the key `AName`, or -1 if the key does not exist in the list. It uses the hash value to search for the key.

See also: `TFPHashObjectList.HashOfIndex (??)`, `TFPHashObjectList.NameOfIndex (??)`, `TFPHashObjectList.IndexOf (??)`, `TFPHashObjectList.Find (??)`, `TFPHashObjectList.FindWithHash (??)`

### 7.15.17 TFPHashObjectList.FindWithHash

Synopsis: Find first element with given name and hash value

Declaration: `function FindWithHash(const AName: shortstring; AHash: LongWord)  
: Pointer`

Visibility: public

Description: `FindWithHash` searches for the object with key `AName`. It uses the provided hash value `AHash` to perform the search. If the object exists, the data object instance is returned, if not, the result is `Nil`.

See also: `TFPHashObjectList.HashOfIndex (??)`, `TFPHashObjectList.NameOfIndex (??)`, `TFPHashObjectList.IndexOf (??)`, `TFPHashObjectList.Find (??)`, `TFPHashObjectList.FindIndexOf (??)`

### 7.15.18 TFPHashObjectList.Rename

Synopsis: Rename a key

Declaration: `function Rename(const AOldName: shortstring; const ANewName: shortstring)  
: Integer`

Visibility: public

Description: `Rename` renames key `AOldname` to `ANewName`. The hash value is recomputed and the object is moved in the list to it's new position.

Errors: If an object with `ANewName` already exists, an exception will be raised.

### 7.15.19 TFPHashObjectList.FindInstanceOf

Synopsis: Search an instance of a certain class

Declaration: `function FindInstanceOf(AClass: TClass; AExact: Boolean;  
AStartAt: Integer) : Integer`

Visibility: public

Description: `FindInstanceOf` searches the list for an instance of class `AClass`. It starts searching at position `AStartAt`. If `AExact` is `True`, only instances of class `AClass` are considered. If `AExact` is `False`, then descendent classes of `AClass` are also taken into account when searching. If no instance is found, `Nil` is returned.

### 7.15.20 TFPHashObjectList.Pack

Synopsis: Remove nil object instances from the list

Declaration: `procedure Pack`

Visibility: public

Description: `Pack` removes all `Nil` objects from the list, and frees all unused memory.

See also: `TFPHashObjectList.Clear` (??)

### 7.15.21 TFPHashObjectList.ShowStatistics

Synopsis: Return some statistics for the list.

Declaration: `procedure ShowStatistics`

Visibility: public

Description: `ShowStatistics` prints some information about the hash list to standard output. It prints the following values:

**HashSize**Size of the hash table

**HashMean**Mean hash value

**HashStdDev**Standard deviation of hash values

**ListSize**Size and capacity of the list

**StringSize**Size and capacity of key strings

### 7.15.22 TFPHashObjectList.ForEachCall

Synopsis: Call a procedure for each object in the list

Declaration: `procedure ForEachCall(proc2call: TObjectListCallback;arg: pointer)`  
`procedure ForEachCall(proc2call: TObjectListStaticCallback;arg: pointer)`

Visibility: public

Description: `ForEachCall` loops over the objects in the list and calls `proc2call`, passing it the object and `arg`.

### 7.15.23 TFPHashObjectList.Capacity

Synopsis: Capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` returns the current capacity of the list. The capacity is expanded as more elements are added to the list. If a good estimate of the number of elements that will be added to the list, the property can be set to a sufficiently large value to avoid reallocation of memory each time the list needs to grow.

See also: `Count` (??), `Items` (??)

#### 7.15.24 TFPHashObjectList.Count

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the current number of elements in the list.

See also: `Capacity (??)`, `Items (??)`

#### 7.15.25 TFPHashObjectList.OwnsObjects

Synopsis: Does the list own the objects it contains

Declaration: `Property OwnsObjects : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `OwnsObjects` determines what to do when an object is removed from the list: if it is `True` (the default), then the list owns the objects: when an object is removed from the list, it is destroyed (freed from memory). Clearing the list will free all objects in the list.

The value of `OwnsObjects` is set when the hash list is created, and cannot be changed during the lifetime of the hash list.

See also: `TFPHashObjectList.Create (??)`

#### 7.15.26 TFPHashObjectList.Items

Synopsis: Indexed array with object instances

Declaration: `Property Items[Index: Integer]: TObject; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` provides indexed access to the object instances, the index runs from 0 to `Count-1 (??)`.

Errors: Specifying an invalid index will result in an exception.

See also: `Capacity (??)`, `Count (??)`

#### 7.15.27 TFPHashObjectList.List

Synopsis: Low-level hash list

Declaration: `Property List : TFPHashList`

Visibility: `public`

Access: `Read`

Description: `List` exposes the low-level hash list ([125](#)). It should not be used directly.

See also: `TFPHashList (125)`

## 7.16 TFPObjectHashTable

### 7.16.1 Description

TFPStringHashTable is a TFPCustomHashTable (118) descendent which stores object instances together with the keys. In case the data associated with the keys are strings themselves, it's better to use TFPStringHashTable (151), or for arbitrary pointer data, TFPDataHashTable (124) is more suitable. The objects are exposed with their keys through the Items (??) property.

See also: TFPStringHashTable (151), TFPDataHashTable (124), TFPObjectHashTable.Items (??)

### 7.16.2 Method overview

Page	Property	Description
143	Add	Add a new object to the hash table
142	Create	Create a new instance of TFPObjectHashTable
142	CreateWith	Create a new hash table with given size and hash function

### 7.16.3 Property overview

Page	Property	Access	Description
143	Items	rw	Key-based access to the objects
143	OwnsObjects	rw	Does the hash table own the objects ?

### 7.16.4 TFPObjectHashTable.Create

Synopsis: Create a new instance of TFPObjectHashTable

Declaration: constructor Create(AOwnsObjects: Boolean)

Visibility: public

Description: Create creates a new instance of TFPObjectHashTable on the heap. It sets the OwnsObjects (??) property to AOwnsObjects, and then calls the inherited Create. If AOwnsObjects is set to True, then the hash table owns the objects: whenever an object is removed from the list, it is automatically freed.

Errors: If not enough memory is available on the heap, an exception may be raised.

See also: TFPObjectHashTable.OwnsObjects (??), TFPObjectHashTable.CreateWith (??), TFPObjectHashTable.Items (??)

### 7.16.5 TFPObjectHashTable.CreateWith

Synopsis: Create a new hash table with given size and hash function

Declaration: constructor CreateWith(AHashTableSize: LongWord;  
aHashFunc: THashFunction; AOwnsObjects: Boolean)

Visibility: public

Description: CreateWith sets the OwnsObjects (??) property to AOwnsObjects, and then calls the inherited CreateWith. If AOwnsObjects is set to True, then the hash table owns the objects: whenever an object is removed from the list, it is automatically freed.

This constructor should be used when a table size and hash algorithm should be specified that differ from the default table size and hash algorithm.

Errors: If not enough memory is available on the heap, an exception may be raised.

See also: `TFObjectHashTable.OwnsObjects` (??), `TFObjectHashTable.Create` (??), `TFObjectHashTable.Items` (??)

### 7.16.6 TFObjectHashTable.Add

Synopsis: Add a new object to the hash table

Declaration: `procedure Add(const aKey: String; AItem: TObject); Virtual`

Visibility: public

Description: `Add` adds the object `AItem` to the hash table, and associates it with key `aKey`.

Errors: If the key `aKey` is already in the hash table, an exception will be raised.

See also: `TFObjectHashTable.Items` (??)

### 7.16.7 TFObjectHashTable.Items

Synopsis: Key-based access to the objects

Declaration: `Property Items[index: String]: TObject; default`

Visibility: public

Access: Read, Write

Description: `Items` provides access to the objects in the hash table using their key: the array index `Index` is the key. A key which is not present will result in an `Nil` instance.

See also: `TFObjectHashTable.Add` (??)

### 7.16.8 TFObjectHashTable.OwnsObjects

Synopsis: Does the hash table own the objects ?

Declaration: `Property OwnsObjects : Boolean`

Visibility: public

Access: Read, Write

Description: `OwnsObjects` determines what happens with objects which are removed from the hash table: if `True`, then removing an object from the hash list will free the object. If `False`, the object is not freed. Note that way in which the object is removed is not relevant: be it `Delete`, `Remove` or `Clear`.

See also: `TFObjectHashTable.Create` (??), `TFObjectHashTable.Items` (??)



## 7.17 TFObjectList

### 7.17.1 Description

`TFObjectList` is a `TFPList` (??) based list which has as the default array property `TObjects` (??) instead of pointers. By default it also manages the objects: when an object is deleted or removed from the list, it is automatically freed. This behaviour can be disabled when the list is created.

In difference with `TObjectList` (157), `TFObjectList` offers no notification mechanism of list operations, allowing it to be faster than `TObjectList`. For the same reason, it is also not a descendent of `TFPList` (although it uses one internally).

See also: `#rtl.classes.TFPList` (??), `TObjectList` (157)

### 7.17.2 Method overview

Page	Property	Description
<a href="#">145</a>	Add	Add an object to the list.
<a href="#">149</a>	Assign	Copy the contents of a list.
<a href="#">145</a>	Clear	Clear all elements in the list.
<a href="#">144</a>	Create	Create a new object list
<a href="#">146</a>	Delete	Delete an element from the list.
<a href="#">145</a>	Destroy	Clears the list and destroys the list instance
<a href="#">146</a>	Exchange	Exchange the location of two objects
<a href="#">146</a>	Expand	Expand the capacity of the list.
<a href="#">146</a>	Extract	Extract an object from the list
<a href="#">147</a>	FindInstanceOf	Search for an instance of a certain class
<a href="#">148</a>	First	Return the first non-nil object in the list
<a href="#">150</a>	ForEachCall	For each object in the list, call a method or procedure, passing it the object.
<a href="#">147</a>	IndexOf	Search for an object in the list
<a href="#">148</a>	Insert	Insert a new object in the list
<a href="#">148</a>	Last	Return the last non-nil object in the list.
<a href="#">148</a>	Move	Move an object to another location in the list.
<a href="#">149</a>	Pack	Remove all <code>Nil</code> references from the list
<a href="#">147</a>	Remove	Remove an item from the list.
<a href="#">149</a>	Sort	Sort the list of objects

### 7.17.3 Property overview

Page	Property	Access	Description
<a href="#">150</a>	Capacity	rw	Capacity of the list
<a href="#">150</a>	Count	rw	Number of elements in the list.
<a href="#">151</a>	Items	rw	Indexed access to the elements of the list.
<a href="#">151</a>	List	r	Internal list used to keep the objects.
<a href="#">150</a>	OwnsObjects	rw	Should the list free elements when they are removed.

### 7.17.4 TFObjectList.Create

Synopsis: Create a new object list

Declaration: `constructor Create`  
`constructor Create(FreeObjects: Boolean)`

Visibility: public

Description: `Create` instantiates a new object list. The `FreeObjects` parameter determines whether objects that are removed from the list should also be freed from memory. By default this is `True`. This behaviour can be changed after the list was instantiated.

Errors: None.

See also: `TFPObjectList.Destroy` (??), `TFPObjectList.OwnsObjects` (??), `TObjectList` ([157](#))

### 7.17.5 TFPObjectList.Destroy

Synopsis: Clears the list and destroys the list instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` clears the list, freeing all objects in the list if `OwnsObjects` (??) is `True`.

See also: `TFPObjectList.OwnsObjects` (??), `TObjectList.Create` (??)

### 7.17.6 TFPObjectList.Clear

Synopsis: Clear all elements in the list.

Declaration: `procedure Clear`

Visibility: public

Description: Removes all objects from the list, freeing all objects in the list if `OwnsObjects` (??) is `True`.

See also: `TObjectList.Destroy` (??)

### 7.17.7 TFPObjectList.Add

Synopsis: Add an object to the list.

Declaration: `function Add(AObject: TObject) : Integer`

Visibility: public

Description: `Add` adds `AObject` to the list and returns the index of the object in the list.

Note that when `OwnsObjects` (??) is `True`, an object should not be added twice to the list: this will result in memory corruption when the object is freed (as it will be freed twice). The `Add` method does not check this, however.

Errors: None.

See also: `TFPObjectList.OwnsObjects` (??), `TFPObjectList.Delete` (??)

### 7.17.8 TFObjectList.Delete

Synopsis: Delete an element from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: public

Description: `Delete` removes the object at index `Index` from the list. When `OwnsObjects` (??) is `True`, the object is also freed.

Errors: An access violation may occur when `OwnsObjects` (??) is `True` and either the object was freed externally, or when the same object is in the same list twice.

See also: `TFObjectList.Remove` (??), `TFObjectList.Extract` (??), `TFObjectList.OwnsObjects` (??), `TFObjectList.Add` (??), `TFObjectList.Clear` (??)

### 7.17.9 TFObjectList.Exchange

Synopsis: Exchange the location of two objects

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: public

Description: `Exchange` exchanges the objects at indexes `Index1` and `Index2` in a direct operation (i.e. no delete/add is performed).

Errors: If either `Index1` or `Index2` is invalid, an exception will be raised.

See also: `TFObjectList.Add` (??), `TFObjectList.Delete` (??)

### 7.17.10 TFObjectList.Expand

Synopsis: Expand the capacity of the list.

Declaration: `function Expand : TFObjectList`

Visibility: public

Description: `Expand` increases the capacity of the list. It calls `#rtl.classes.tfplist.expand` (??) and then returns a reference to itself.

Errors: If there is not enough memory to expand the list, an exception will be raised.

See also: `TFObjectList.Pack` (??), `TFObjectList.Clear` (??), `#rtl.classes.tfplist.expand` (??)

### 7.17.11 TFObjectList.Extract

Synopsis: Extract an object from the list

Declaration: `function Extract(Item: TObject) : TObject`

Visibility: public

Description: `Extract` removes `Item` from the list, if it is present in the list. It returns `Item` if it was found, `Nil` if item was not present in the list.

Note that the object is not freed, and that only the first found object is removed from the list.

Errors: None.

See also: `TFObjectList.Pack (??)`, `TFObjectList.Clear (??)`, `TFObjectList.Remove (??)`, `TFObjectList.Delete (??)`

### 7.17.12 TFObjectList.Remove

Synopsis: Remove an item from the list.

Declaration: `function Remove (AObject: TObject) : Integer`

Visibility: public

Description: `Remove` removes `Item` from the list, if it is present in the list. It frees `Item` if `OwnsObjects (??)` is `True`, and returns the index of the object that was found in the list, or -1 if the object was not found.

Note that only the first found object is removed from the list.

Errors: None.

See also: `TFObjectList.Pack (??)`, `TFObjectList.Clear (??)`, `TFObjectList.Delete (??)`, `TFObjectList.Extract (??)`

### 7.17.13 TFObjectList.IndexOf

Synopsis: Search for an object in the list

Declaration: `function IndexOf (AObject: TObject) : Integer`

Visibility: public

Description: `IndexOf` searches for the presence of `AObject` in the list, and returns the location (index) in the list. The index is 0-based, and -1 is returned if `AObject` was not found in the list.

Errors: None.

See also: `TFObjectList.Items (??)`, `TFObjectList.Remove (??)`, `TFObjectList.Extract (??)`

### 7.17.14 TFObjectList.FindInstanceOf

Synopsis: Search for an instance of a certain class

Declaration: `function FindInstanceOf (AClass: TClass; AExact: Boolean; AStartAt: Integer) : Integer`

Visibility: public

Description: `FindInstanceOf` will look through the instances in the list and will return the first instance which is a descendent of class `AClass` if `AExact` is `False`. If `AExact` is `true`, then the instance should be of class `AClass`.

If no instance of the requested class is found, `Nil` is returned.

Errors: None.

See also: `TFObjectList.IndexOf (??)`

### 7.17.15 TFObjectList.Insert

Synopsis: Insert a new object in the list

Declaration: `procedure Insert (Index: Integer; AObject: TObject)`

Visibility: public

Description: `Insert` inserts `AObject` at position `Index` in the list. All elements in the list after this position are shifted. The index is zero based, i.e. an insert at position 0 will insert an object at the first position of the list.

Errors: None.

See also: `TFObjectList.Add (??)`, `TFObjectList.Delete (??)`

### 7.17.16 TFObjectList.First

Synopsis: Return the first non-nil object in the list

Declaration: `function First : TObject`

Visibility: public

Description: `First` returns a reference to the first non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TFObjectList.Last (??)`, `TFObjectList.Pack (??)`

### 7.17.17 TFObjectList.Last

Synopsis: Return the last non-nil object in the list.

Declaration: `function Last : TObject`

Visibility: public

Description: `Last` returns a reference to the last non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TFObjectList.First (??)`, `TFObjectList.Pack (??)`

### 7.17.18 TFObjectList.Move

Synopsis: Move an object to another location in the list.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the object at current location `CurIndex` to location `NewIndex`. Note that the `NewIndex` is determined *after* the object was removed from location `CurIndex`, and can hence be shifted with 1 position if `CurIndex` is less than `NewIndex`.

Contrary to `exchange (??)`, the move operation is done by extracting the object from it's current location and inserting it at the new location.

**Errors:** If either `CurIndex` or `NewIndex` is out of range, an exception may occur.

**See also:** `TFPObjectList.Exchange (??)`, `TFPObjectList.Delete (??)`, `TFPObjectList.Insert (??)`

### 7.17.19 TFPObjectList.Assign

**Synopsis:** Copy the contents of a list.

**Declaration:** `procedure Assign (Obj: TFPObjectList)`

**Visibility:** `public`

**Description:** `Assign` copies the contents of `Obj` if `Obj` is of type `TFPObjectList`

**Errors:** None.

### 7.17.20 TFPObjectList.Pack

**Synopsis:** Remove all `Nil` references from the list

**Declaration:** `procedure Pack`

**Visibility:** `public`

**Description:** `Pack` removes all `Nil` elements from the list.

**Errors:** None.

**See also:** `TFPObjectList.First (??)`, `TFPObjectList.Last (??)`

### 7.17.21 TFPObjectList.Sort

**Synopsis:** Sort the list of objects

**Declaration:** `procedure Sort (Compare: TListSortCompare)`

**Visibility:** `public`

**Description:** `Sort` will perform a quick-sort on the list, using `Compare` as the compare algorithm. This function should accept 2 pointers and should return the following result:

**less than 0** If the first pointer comes before the second.

**equal to 0** If the pointers have the same value.

**larger than 0** If the first pointer comes after the second.

The function should be able to deal with `Nil` values.

**Errors:** None.

**See also:** `#rtl.classes.TList.Sort (??)`

### 7.17.22 TFObjectList.ForEachCall

Synopsis: For each object in the list, call a method or procedure, passing it the object.

Declaration: `procedure ForEachCall(proc2call: TObjectListCallback;arg: pointer)`  
`procedure ForEachCall(proc2call: TObjectListStaticCallback;arg: pointer)`

Visibility: public

Description: `ForEachCall` loops through all objects in the list, and calls `proc2call`, passing it the object in the list. Additionally, `arg` is also passed to the procedure. `Proc2call` can be a plain procedure or can be a method of a class.

Errors: None.

See also: [TObjectListStaticCallback \(109\)](#), [TObjectListCallback \(108\)](#)

### 7.17.23 TFObjectList.Capacity

Synopsis: Capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` is the number of elements that the list can contain before it needs to expand itself, i.e., reserve more memory for pointers. It is always equal or larger than `Count` (??).

See also: [TFObjectList.Count](#) (??)

### 7.17.24 TFObjectList.Count

Synopsis: Number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read,Write

Description: `Count` is the number of elements in the list. Note that this includes `Nil` elements.

See also: [TFObjectList.Capacity](#) (??)

### 7.17.25 TFObjectList.OwnsObjects

Synopsis: Should the list free elements when they are removed.

Declaration: `Property OwnsObjects : Boolean`

Visibility: public

Access: Read,Write

**Description:** `OwnsObjects` determines whether the objects in the list should be freed when they are removed (not extracted) from the list, or when the list is cleared. If the property is `True` then they are freed. If the property is `False` the elements are not freed.

The value is usually set in the constructor, and is seldom changed during the lifetime of the list. It defaults to `True`.

See also: `TFPObjectList.Create (??)`, `TFPObjectList.Delete (??)`, `TFPObjectList.Remove (??)`, `TFPObjectList.Clear (??)`

### 7.17.26 TFPObjectList.Items

**Synopsis:** Indexed access to the elements of the list.

**Declaration:** `Property Items[Index: Integer]: TObject; default`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Items` is the default property of the list. It provides indexed access to the elements in the list. The index `Index` is zero based, i.e., runs from 0 (zero) to `Count-1`.

See also: `TFPObjectList.Count (??)`

### 7.17.27 TFPObjectList.List

**Synopsis:** Internal list used to keep the objects.

**Declaration:** `Property List : TFPList`

**Visibility:** `public`

**Access:** `Read`

**Description:** `List` is a reference to the `TFPList (??)` instance used to manage the elements in the list.

See also: `#rtl.classes.tfplist (??)`

## 7.18 TFPStringHashTable

### 7.18.1 Description

`TFPStringHashTable` is a `TFPCustomHashTable (118)` descendent which stores simple strings together with the keys. In case the data associated with the keys are objects, it's better to use `TFPObjectHashTable (142)`, or for arbitrary pointer data, `TFPDataHashTable (124)` is more suitable. The strings are exposed with their keys through the `Items (??)` property.

See also: `TFPObjectHashTable (142)`, `TFPDataHashTable (124)`, `Items (??)`

### 7.18.2 Method overview

Page	Property	Description
<a href="#">152</a>	<code>Add</code>	Add a new string to the hash list



### 7.18.3 Property overview

Page	Property	Access	Description
<a href="#">152</a>	Items	rw	Key based access to the strings in the hash table

### 7.18.4 TFPStringHashTable.Add

Synopsis: Add a new string to the hash list

Declaration: `procedure Add(const aKey: String; const aItem: String); Virtual`

Visibility: public

Description: Add adds a new string `AItem` to the hash list with key `AKey`.

Errors: If a string with key `Akey` already exists in the hash table, an exception will be raised.

See also: `TFPStringHashTable.Items` (??)

### 7.18.5 TFPStringHashTable.Items

Synopsis: Key based access to the strings in the hash table

Declaration: `Property Items[index: String]: String; default`

Visibility: public

Access: Read, Write

Description: `Items` provides access to the strings in the hash table using their key: the array index `Index` is the key. A key which is not present will result in an empty string.

See also: `TFPStringHashTable.Add` (??)

## 7.19 THTCustomNode

### 7.19.1 Description

`THTCustomNode` is used by the `TFPCustomHashTable` ([118](#)) class to store the keys and associated values.

See also: `TFPCustomHashTable` ([118](#))

### 7.19.2 Method overview

Page	Property	Description
<a href="#">153</a>	CreateWith	Create a new instance of <code>THTCustomNode</code>
<a href="#">153</a>	HasKey	Check whether this node matches the given key.

### 7.19.3 Property overview

Page	Property	Access	Description
<a href="#">153</a>	Key	r	Key value associated with this hash item.

### 7.19.4 THTCustomNode.CreateWith

Synopsis: Create a new instance of `THTCustomNode`

Declaration: `constructor CreateWith(const AString: String)`

Visibility: `public`

Description: `CreateWith` creates a new instance of `THTCustomNode` and stores the string `AString` in it. It should never be necessary to call this method directly, it will be called by the `TFPCustomHashTable` (118) class when needed.

Errors: If no more memory is available, an exception may be raised.

See also: `TFPCustomHashTable` (118)

### 7.19.5 THTCustomNode.HasKey

Synopsis: Check whether this node matches the given key.

Declaration: `function HasKey(const AKey: String) : Boolean`

Visibility: `public`

Description: `HasKey` checks whether this node matches the given key `AKey`, by comparing it with the stored key. It returns `True` if it does, `False` if not.

Errors: None.

See also: `THTCustomNode.Key` (??)

### 7.19.6 THTCustomNode.Key

Synopsis: Key value associated with this hash item.

Declaration: `Property Key : String`

Visibility: `public`

Access: `Read`

Description: `Key` is the key value associated with this hash item. It is stored when the item is created, and is read-only.

See also: `THTCustomNode.CreateWith` (??)

## 7.20 THTDataNode

### 7.20.1 Description

`THTDataNode` is used by `TFPDataHashTable` (124) to store the hash items in. It simply holds the data pointer.

It should not be necessary to use `THTDataNode` directly, it's only for inner use by `TFPDataHashTable`

See also: `TFPDataHashTable` (124), `THTObjectNode` (154), `THTStringNode` (155)

### 7.20.2 Property overview

Page	Property	Access	Description
<a href="#">154</a>	Data	rw	Data pointer

### 7.20.3 THTDataNode.Data

Synopsis: Data pointer

Declaration: `Property Data : pointer`

Visibility: public

Access: Read,Write

Description: Pointer containing the user data associated with the hash value.

## 7.21 THTObjectNode

### 7.21.1 Description

THTObjectNode is a THTCustomNode ([152](#)) descendent which holds the data in the TFPObjec-tHashTable ([142](#)) hash table. It exposes a data string.

It should not be necessary to use THTObjectNode directly, it's only for inner use by TFPObjec-tHashTable

See also: TFPObjec-tHashTable ([142](#))

### 7.21.2 Property overview

Page	Property	Access	Description
<a href="#">154</a>	Data	rw	Object instance

### 7.21.3 THTObjectNode.Data

Synopsis: Object instance

Declaration: `Property Data : TObject`

Visibility: public

Access: Read,Write

Description: Data is the object instance associated with the key value. It is exposed in TFPObjec-tHashTable.Items (??)

See also: TFPObjec-tHashTable ([142](#)), TFPObjec-tHashTable.Items (??), THTOwnedObjectNode ([154](#))

## 7.22 THTOwnedObjectNode

### 7.22.1 Description

THTOwnedObjectNode is used instead of THTObjectNode ([154](#)) in case TFPObjec-tHashTable ([142](#)) owns it's objects. When this object is destroyed, the associated data object is also destroyed.

See also: TFPObjec-tHashTable ([142](#)), THTObjectNode ([154](#)), TFPObjec-tHashTable.OwnsObjects (??)

### 7.22.2 Method overview

Page	Property	Description
<a href="#">155</a>	Destroy	Destroys the node and the object.

### 7.22.3 THTOwnedObjectNode.Destroy

Synopsis: Destroys the node and the object.

Declaration: `destructor Destroy;` `Override`

Visibility: `public`

Description: `Destroy` first frees the data object, and then only frees itself.

See also: `THTOwnedObjectNode` ([154](#)), `TFPObjectHashTable.OwnsObjects` (??)

## 7.23 THTStringNode

### 7.23.1 Description

`THTStringNode` is a `THTCustomNode` ([152](#)) descendent which holds the data in the `TFPStringHashTable` ([151](#)) hash table. It exposes a data string.

It should not be necessary to use `THTStringNode` directly, it's only for inner use by `TFPStringHashTable`

See also: `TFPStringHashTable` ([151](#))

### 7.23.2 Property overview

Page	Property	Access	Description
<a href="#">155</a>	Data	rw	String data

### 7.23.3 THTStringNode.Data

Synopsis: String data

Declaration: `Property Data : String`

Visibility: `public`

Access: Read,Write

Description: `Data` is the data of this has node. The data is a string, associated with the key. It is also exposed in `TFPStringHashTable.Items` (??)

See also: `TFPStringHashTable` ([151](#))

## 7.24 TObjectBucketList

### 7.24.1 Description

`TObjectBucketList` is a class that redefines the associative `Data` array using `TObject` instead of `Pointer`. It also adds some overloaded versions of the `Add` and `Remove` calls using `TObject` instead of `Pointer` for the argument and result types.

See also: `TObjectBucketList` ([155](#))

### 7.24.2 Method overview

Page	Property	Description
<a href="#">156</a>	Add	Add an object to the list
<a href="#">156</a>	Remove	Remove an object from the list

### 7.24.3 Property overview

Page	Property	Access	Description
<a href="#">156</a>	Data	rw	Associative array of data items

### 7.24.4 TObjectBucketList.Add

Synopsis: Add an object to the list

Declaration: `function Add(AItem: TObject; AData: TObject) : TObject`

Visibility: public

Description: Add adds AItem to the list and associated AData with it.

See also: TObjectBucketList.Data (??), TObjectBucketList.Remove (??)

### 7.24.5 TObjectBucketList.Remove

Synopsis: Remove an object from the list

Declaration: `function Remove(AItem: TObject) : TObject`

Visibility: public

Description: Remove removes the object AItem from the list. It returns the Data object which was associated with the item. If AItem was not in the list, then Nil is returned.

See also: TObjectBucketList.Add (??), TObjectBucketList.Data (??)

### 7.24.6 TObjectBucketList.Data

Synopsis: Associative array of data items

Declaration: `Property Data[AItem: TObject]: TObject; default`

Visibility: public

Access: Read, Write

Description: Data provides associative access to the data in the list: it returns the data object associated with the AItem object. If the AItem object is not in the list, an EListError exception is raised.

See also: TObjectBucketList.Add (??)

## 7.25 TObjectList

### 7.25.1 Description

`TObjectList` is a `TList` (??) descendent which has as the default array property `TObjects` (??) instead of pointers. By default it also manages the objects: when an object is deleted or removed from the list, it is automatically freed. This behaviour can be disabled when the list is created.

In difference with `TFPObjectList` (144), `TObjectList` offers a notification mechanism of list change operations: insert, delete. This slows down bulk operations, so if the notifications are not needed, `TFPObjectList` may be more appropriate.

See also: `#rtl.classes.TList` (??), `TFPObjectList` (144), `TComponentList` (113), `TClassList` (110)

### 7.25.2 Method overview

Page	Property	Description
157	Add	Add an object to the list.
157	create	Create a new object list.
158	Extract	Extract an object from the list.
159	FindInstanceOf	Search for an instance of a certain class
159	First	Return the first non-nil object in the list
158	IndexOf	Search for an object in the list
159	Insert	Insert an object in the list.
159	Last	Return the last non-nil object in the list.
158	Remove	Remove (and possibly free) an element from the list.

### 7.25.3 Property overview

Page	Property	Access	Description
160	Items	rw	Indexed access to the elements of the list.
160	OwnsObjects	rw	Should the list free elements when they are removed.

### 7.25.4 TObjectList.create

Synopsis: Create a new object list.

Declaration: `constructor create`  
`constructor create(freeobjects: Boolean)`

Visibility: public

Description: `Create` instantiates a new object list. The `FreeObjects` parameter determines whether objects that are removed from the list should also be freed from memory. By default this is `True`. This behaviour can be changed after the list was instantiated.

Errors: None.

See also: `TObjectList.Destroy` (??), `TObjectList.OwnsObjects` (??), `TFPObjectList` (144)

### 7.25.5 TObjectList.Add

Synopsis: Add an object to the list.

Declaration: `function Add(AObject: TObject) : Integer`

Visibility: public

Description: Add overrides the TList (??) implementation to accept objects (AObject) instead of pointers.

The function returns the index of the position where the object was added.

Errors: If the list must be expanded, and not enough memory is available, an exception may be raised.

See also: TObjectList.Insert (??), #rtl.classes.TList.Delete (??), TObjectList.Extract (??), TObjectList.Remove (??)

### 7.25.6 TObjectList.Extract

Synopsis: Extract an object from the list.

Declaration: `function Extract (Item: TObject) : TObject`

Visibility: public

Description: Extract removes the object Item from the list if it is present in the list. Contrary to Remove (??), Extract does not free the extracted element if OwnsObjects (??) is True

The function returns a reference to the item which was removed from the list, or Nil if no element was removed.

Errors: None.

See also: TObjectList.Remove (??)

### 7.25.7 TObjectList.Remove

Synopsis: Remove (and possibly free) an element from the list.

Declaration: `function Remove (AObject: TObject) : Integer`

Visibility: public

Description: Remove removes Item from the list, if it is present in the list. It frees Item if OwnsObjects (??) is True, and returns the index of the object that was found in the list, or -1 if the object was not found.

Note that only the first found object is removed from the list.

Errors: None.

See also: TObjectList.Extract (??)

### 7.25.8 TObjectList.IndexOf

Synopsis: Search for an object in the list

Declaration: `function IndexOf (AObject: TObject) : Integer`

Visibility: public

Description: IndexOf overrides the TList (??) implementation to accept an object instance instead of a pointer.

The function returns the index of the first match for AObject in the list, or -1 if no match was found.

Errors: None.

See also: TObjectList.FindInstanceOf (??)

**7.25.9 TObjectList.FindInstanceOf**

Synopsis: Search for an instance of a certain class

Declaration: `function FindInstanceOf (AClass: TClass; AExact: Boolean;  
AStartAt: Integer) : Integer`

Visibility: public

Description: `FindInstanceOf` will look through the instances in the list and will return the first instance which is a descendent of class `AClass` if `AExact` is `False`. If `AExact` is `true`, then the instance should be of class `AClass`.

If no instance of the requested class is found, `Nil` is returned.

Errors: None.

See also: `TObjectList.IndexOf (??)`

**7.25.10 TObjectList.Insert**

Synopsis: Insert an object in the list.

Declaration: `procedure Insert (Index: Integer; AObject: TObject)`

Visibility: public

Description: `Insert` inserts `AObject` in the list at position `Index`. The index is zero-based. This method overrides the implementation in `TList (??)` to accept objects instead of pointers.

Errors: If an invalid `Index` is specified, an exception is raised.

See also: `TObjectList.Add (??)`, `TObjectList.Remove (??)`

**7.25.11 TObjectList.First**

Synopsis: Return the first non-nil object in the list

Declaration: `function First : TObject`

Visibility: public

Description: `First` returns a reference to the first non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TObjectList.Last (??)`, `TObjectList.Pack (??)`

**7.25.12 TObjectList.Last**

Synopsis: Return the last non-nil object in the list.

Declaration: `function Last : TObject`

Visibility: public

Description: `Last` returns a reference to the last non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TObjectList.First (??)`, `TObjectList.Pack (??)`



### 7.25.13 TObjectList.OwnsObjects

Synopsis: Should the list free elements when they are removed.

Declaration: `Property OwnsObjects : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `OwnsObjects` determines whether the objects in the list should be freed when they are removed (not extracted) from the list, or when the list is cleared. If the property is `True` then they are freed. If the property is `False` the elements are not freed.

The value is usually set in the constructor, and is seldom changed during the lifetime of the list. It defaults to `True`.

See also: `TObjectList.Create (??)`, `TObjectList.Delete (??)`, `TObjectList.Remove (??)`, `TObjectList.Clear (??)`

### 7.25.14 TObjectList.Items

Synopsis: Indexed access to the elements of the list.

Declaration: `Property Items[Index: Integer]: TObject; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` is the default property of the list. It provides indexed access to the elements in the list. The index `Index` is zero based, i.e., runs from 0 (zero) to `Count-1`.

See also: `#rtl.classes.TList.Count (??)`

## 7.26 TObjectQueue

### 7.26.1 Method overview

Page	Property	Description
<a href="#">161</a>	<code>Peek</code>	Look at the first object in the queue.
<a href="#">161</a>	<code>Pop</code>	Pop the first element off the queue
<a href="#">160</a>	<code>Push</code>	Push an object on the queue

### 7.26.2 TObjectQueue.Push

Synopsis: Push an object on the queue

Declaration: `function Push(AObject: TObject) : TObject`

Visibility: `public`

Description: `Push` pushes another object on the queue. It overrides the `Push` method as implemented in `TQueue` so it accepts only objects as arguments.

Errors: If not enough memory is available to expand the queue, an exception may be raised.

See also: `TObjectQueue.Pop (??)`, `TObjectQueue.Peek (??)`

### 7.26.3 TObjectQueue.Pop

Synopsis: Pop the first element off the queue

Declaration: `function Pop : TObject`

Visibility: public

Description: `Pop` removes the first element in the queue, and returns a reference to the instance. If the queue is empty, `Nil` is returned.

Errors: None.

See also: `TObjectQueue.Push` (??), `TObjectQueue.Peek` (??)

### 7.26.4 TObjectQueue.Peek

Synopsis: Look at the first object in the queue.

Declaration: `function Peek : TObject`

Visibility: public

Description: `Peek` returns the first object in the queue, without removing it from the queue. If there are no more objects in the queue, `Nil` is returned.

Errors: None

See also: `TObjectQueue.Push` (??), `TObjectQueue.Pop` (??)

## 7.27 TObjectStack

### 7.27.1 Description

`TObjectStack` is a stack implementation which manages pointers only.

`TObjectStack` introduces no new behaviour, it simply overrides some methods to accept and/or return `TObject` instances instead of pointers.

See also: `TOrderedList` ([162](#)), `TStack` ([165](#)), `TQueue` ([165](#)), `TObjectQueue` ([160](#))

### 7.27.2 Method overview

Page	Property	Description
<a href="#">162</a>	<code>Peek</code>	Look at the top object in the stack.
<a href="#">162</a>	<code>Pop</code>	Pop the top object of the stack.
<a href="#">161</a>	<code>Push</code>	Push an object on the stack.

### 7.27.3 TObjectStack.Push

Synopsis: Push an object on the stack.

Declaration: `function Push(AObject: TObject) : TObject`

Visibility: public

**Description:** `Push` pushes another object on the stack. It overrides the `Push` method as implemented in `TStack` so it accepts only objects as arguments.

**Errors:** If not enough memory is available to expand the stack, an exception may be raised.

**See also:** `TObjectStack.Pop` (??), `TObjectStack.Peek` (??)

#### 7.27.4 `TObjectStack.Pop`

**Synopsis:** Pop the top object of the stack.

**Declaration:** `function Pop : TObject`

**Visibility:** public

**Description:** `Pop` pops the top object of the stack, and returns the object instance. If there are no more objects on the stack, `Nil` is returned.

**Errors:** None

**See also:** `TObjectStack.Push` (??), `TObjectStack.Peek` (??)

#### 7.27.5 `TObjectStack.Peek`

**Synopsis:** Look at the top object in the stack.

**Declaration:** `function Peek : TObject`

**Visibility:** public

**Description:** `Peek` returns the top object of the stack, without removing it from the stack. If there are no more objects on the stack, `Nil` is returned.

**Errors:** None

**See also:** `TObjectStack.Push` (??), `TObjectStack.Pop` (??)

### 7.28 `TOrderedList`

#### 7.28.1 Description

`TOrderedList` provides the base class for `TQueue` (165) and `TStack` (165). It provides an interface for pushing and popping elements on or off the list, and manages the internal list of pointers.

Note that `TOrderedList` does not manage objects on the stack, i.e. objects are not freed when the ordered list is destroyed.

**See also:** `TQueue` (165), `TStack` (165)

**7.28.2 Method overview**

Page	Property	Description
<a href="#">164</a>	AtLeast	Check whether the list contains a certain number of elements.
<a href="#">163</a>	Count	Number of elements on the list.
<a href="#">163</a>	Create	Create a new ordered list
<a href="#">163</a>	Destroy	Free an ordered list
<a href="#">164</a>	Peek	Return the next element to be popped from the list.
<a href="#">164</a>	Pop	Remove an element from the list.
<a href="#">164</a>	Push	Push another element on the list.

**7.28.3 TOrderedList.Create**

Synopsis: Create a new ordered list

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new ordered list. It initializes the internal pointer list.

Errors: None.

See also: `TOrderedList.Destroy` (??)

**7.28.4 TOrderedList.Destroy**

Synopsis: Free an ordered list

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the internal pointer list, and removes the `TOrderedList` instance from memory.

Errors: None.

See also: `TOrderedList.Create` (??)

**7.28.5 TOrderedList.Count**

Synopsis: Number of elements on the list.

Declaration: `function Count : Integer`

Visibility: `public`

Description: `Count` is the number of pointers in the list.

Errors: None.

See also: `TOrderedList.AtLeast` (??)

### 7.28.6 TOrderedList.AtLeast

Synopsis: Check whether the list contains a certain number of elements.

Declaration: `function AtLeast (ACount: Integer) : Boolean`

Visibility: `public`

Description: `AtLeast` returns `True` if the number of elements in the list is equal to or bigger than `ACount`. It returns `False` otherwise.

Errors: None.

See also: `TOrderedList.Count` (??)

### 7.28.7 TOrderedList.Push

Synopsis: Push another element on the list.

Declaration: `function Push (AItem: Pointer) : Pointer`

Visibility: `public`

Description: `Push` adds `AItem` to the list, and returns `AItem`.

Errors: If not enough memory is available to expand the list, an exception may be raised.

See also: `TOrderedList.Pop` (??), `TOrderedList.Peek` (??)

### 7.28.8 TOrderedList.Pop

Synopsis: Remove an element from the list.

Declaration: `function Pop : Pointer`

Visibility: `public`

Description: `Pop` removes an element from the list, and returns the element that was removed from the list. If no element is on the list, `Nil` is returned.

Errors: None.

See also: `TOrderedList.Peek` (??), `TOrderedList.Push` (??)

### 7.28.9 TOrderedList.Peek

Synopsis: Return the next element to be popped from the list.

Declaration: `function Peek : Pointer`

Visibility: `public`

Description: `Peek` returns the element that will be popped from the list at the next call to `Pop` (??), without actually popping it from the list.

Errors: None.

See also: `TOrderedList.Pop` (??), `TOrderedList.Push` (??)

## 7.29 TQueue

### 7.29.1 Description

TQueue is a descendent of TOrderedList ([162](#)) which implements Push (??) and Pop (??) behaviour as a queue: what is first pushed on the queue, is popped of first (FIFO: First in, first out).

TQueue offers no new methods, it merely implements some abstract methods introduced by TOrderedList ([162](#))

See also: TOrderedList ([162](#)), TObjectQueue ([160](#)), TStack ([165](#))

## 7.30 TStack

### 7.30.1 Description

TStack is a descendent of TOrderedList ([162](#)) which implements Push (??) and Pop (??) behaviour as a stack: what is last pushed on the stack, is popped of first (LIFO: Last in, first out).

TStack offers no new methods, it merely implements some abstract methods introduced by TOrderedList ([162](#))

See also: TOrderedList ([162](#)), TObjectStack ([161](#)), TQueue ([165](#))

## Chapter 8

# Reference for unit 'CustApp'

### 8.1 Used units

Table 8.1: Used units by unit 'CustApp'

Name	Page
Classes	??
System	??
sysutils	??

### 8.2 Overview

The `CustApp` unit implements the `TCustomApplication` (167) class, which serves as the common ancestor to many kinds of `TApplication` classes: a GUI application in the LCL, a CGI application in FPCGI, a daemon application in `daemonapp`. It introduces some properties to describe the environment in which the application is running (environment variables, program command-line parameters) and introduces some methods to initialize and run a program, as well as functionality to handle exceptions.

Typical use of a descendent class is to introduce a global variable `Application` and use the following code:

```
Application.Initialize;  
Application.Run;
```

Since normally only a single instance of this class is created, and it is a `TComponent` descendent, it can be used as an owner for many components, doing so will ensure these components will be freed when the application terminates.

### 8.3 Constants, types and variables

#### 8.3.1 Types

```
TEventLogTypes = Set of TEventType
```

`TEventLogTypes` is a set of `TEventType` (??), used in `TCustomApplication.EventLogFilter` (??) to filter events that are sent to the system log.

`TExceptionEvent` = procedure (Sender: TObject; E: Exception) of object

`TExceptionEvent` is the prototype for the exception handling events in `TCustomApplication`.

### 8.3.2 Variables

`CustomApplication` : `TCustomApplication` = nil

`CustomApplication` contains the global application instance. All descendents of `TCustomApplication` (167) should, in addition to storing an instance pointer in some variable (most likely called "Application") store the instance pointer in this variable. This ensures that, whatever kind of application is being created, user code can access the application object.

## 8.4 TCustomApplication

### 8.4.1 Description

`TCustomApplication` is the ancestor class for classes that wish to implement a global application class instance. It introduces several application-wide functionalities.

- Exception handling in `HandleException` (??), `ShowException` (??), `OnException` (??) and `StopOnException` (??).
- Command-line parameter parsing in `FindOptionIndex` (??), `GetOptionValue` (??), `CheckOptions` (??) and `HasOption` (??)
- Environment variable handling in `GetEnvironmentList` (??) and `EnvironmentVariable` (??).

Descendent classes need to override the `DoRun` protected method to implement the functionality of the program.

### 8.4.2 Method overview

Page	Property	Description
171	<code>CheckOptions</code>	Check whether all given options on the command-line are valid.
168	<code>Create</code>	Create a new instance of the <code>TCustomApplication</code> class
168	<code>Destroy</code>	Destroys the <code>TCustomApplication</code> instance.
170	<code>FindOptionIndex</code>	Return the index of an option.
172	<code>GetEnvironmentList</code>	Return a list of environment variables.
170	<code>GetOptionValue</code>	Return the value of a command-line option.
168	<code>HandleException</code>	Handle an exception.
171	<code>HasOption</code>	Check whether an option was specified.
169	<code>Initialize</code>	Initialize the application
172	<code>Log</code>	Write a message to the event log
169	<code>Run</code>	Runs the application.
169	<code>ShowException</code>	Show an exception to the user
170	<code>Terminate</code>	Terminate the application.



### 8.4.3 Property overview

Page	Property	Access	Description
<a href="#">176</a>	CaseSensitiveOptions	rw	Are options interpreted case sensitive or not
<a href="#">174</a>	ConsoleApplication	r	Is the application a console application or not
<a href="#">175</a>	EnvironmentVariable	r	Environment variable access
<a href="#">176</a>	EventLogFilter	rw	Event to filter events, before they are sent to the system log
<a href="#">172</a>	ExeName	r	Name of the executable.
<a href="#">173</a>	HelpFile	rw	Location of the application help file.
<a href="#">174</a>	Location	r	Application location
<a href="#">174</a>	OnException	rw	Exception handling event
<a href="#">175</a>	OptionChar	rw	Command-line switch character
<a href="#">175</a>	ParamCount	r	Number of command-line parameters
<a href="#">174</a>	Params	r	Command-line parameters
<a href="#">176</a>	StopOnException	rw	Should the program loop stop on an exception
<a href="#">173</a>	Terminated	r	Was <code>Terminate</code> called or not
<a href="#">173</a>	Title	rw	Application title

### 8.4.4 TCustomApplication.Create

Synopsis: Create a new instance of the `TCustomApplication` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TCustomApplication` class. It sets some defaults for the various properties, and then calls the inherited `Create`.

See also: `TCustomApplication.Destroy` (??)

### 8.4.5 TCustomApplication.Destroy

Synopsis: Destroys the `TCustomApplication` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` simply calls the inherited `Destroy`.

See also: `TCustomApplication.Create` (??)

### 8.4.6 TCustomApplication.HandleException

Synopsis: Handle an exception.

Declaration: `procedure HandleException(Sender: TObject); Virtual`

Visibility: `public`

Description: `HandleException` is called (or can be called) to handle the exception `Sender`. If the exception is not of class `Exception` then the default handling of exceptions in the `SysUtils` unit is called.

If the exception is of class `Exception` and the `OnException` (??) handler is set, the handler is called with the exception object and `Sender` argument.

If the `OnException` handler is not set, then the exception is passed to the `ShowException (??)` routine, which can be overridden by descendent application classes to show the exception in a way that is fit for the particular class of application. (a GUI application might show the exception in a message dialog.

When the exception is handled in the above manner, and the `StopOnException (??)` property is set to `True`, the `Terminated (??)` property is set to `True`, which will cause the `Run (??)` loop to stop, and the application will exit.

See also: `ShowException (??)`, `StopOnException (??)`, `Terminated (??)`, `Run (??)`

### 8.4.7 TCustomApplication.Initialize

Synopsis: Initialize the application

Declaration: `procedure Initialize; Virtual`

Visibility: `public`

Description: `Initialize` can be overridden by descendent applications to perform any initialization after the class was created. It can be used to react to properties being set at program startup. End-user code should call `Initialize` prior to calling `Run`

In `TCustomApplication`, `Initialize` sets `Terminated` to `False`.

See also: `TCustomApplication.Run (??)`, `TCustomApplication.Terminated (??)`

### 8.4.8 TCustomApplication.Run

Synopsis: Runs the application.

Declaration: `procedure Run`

Visibility: `public`

Description: `Run` is the start of the user code: when called, it starts a loop and repeatedly calls `DoRun` until `Terminated` is set to `True`. If an exception is raised during the execution of `DoRun`, it is caught and handled to `TCustomApplication.HandleException (??)`. If `TCustomApplication.StopOnException (??)` is set to `True` (which is *not* the default), `Run` will exit, and the application will then terminate. The default is to call `DoRun` again, which is useful for applications running a message loop such as services and GUI applications.

See also: `TCustomApplication.HandleException (??)`, `TCustomApplication.StopException (??)`

### 8.4.9 TCustomApplication.ShowException

Synopsis: Show an exception to the user

Declaration: `procedure ShowException(E: Exception); Virtual`

Visibility: `public`

Description: `ShowException` should be overridden by descendent classes to show an exception message to the user. The default behaviour is to call the `ShowException (??)` procedure in the `SysUtils` unit.

Descendent classes should do something appropriate for their context: GUI applications can show a message box, daemon applications can write the exception message to the system log, web applications can send a 500 error response code.

Errors: None.

See also: `ShowException (??)`, `TCustomApplication.HandleException (??)`, `TCustomApplication.StopException (??)`

#### 8.4.10 TCustomApplication.Terminate

Synopsis: Terminate the application.

Declaration: `procedure Terminate; Virtual`

Visibility: public

Description: `Terminate` sets the `Terminated` property to `True`. By itself, this does not terminate the application. Instead, descendent classes should in their `DoRun` method, check the value of the `Terminated (??)` property and properly shut down the application if it is set to `True`.

See also: `TCustomApplication.Terminated (??)`, `TCustomApplication.Run (??)`

#### 8.4.11 TCustomApplication.FindOptionIndex

Synopsis: Return the index of an option.

Declaration: `function FindOptionIndex(const S: String;var Longopt: Boolean) : Integer`

Visibility: public

Description: `FindOptionIndex` will return the index of the option `S` or the long option `LongOpt`. Neither of them should include the switch character. If no such option was specified, -1 is returned. If either the long or short option was specified, then the position on the command-line is returned.

Depending on the value of the `CaseSensitiveOptions (??)` property, the search is performed case sensitive or case insensitive.

Options are identified as command-line parameters which start with `OptionChar (??)` (by default the dash ('-') character).

See also: `HasOption (??)`, `GetOptionValue (??)`, `CheckOptions (??)`, `CaseSensitiveOptions (??)`, `OptionChar (??)`

#### 8.4.12 TCustomApplication.GetOptionValue

Synopsis: Return the value of a command-line option.

Declaration: `function GetOptionValue(const S: String) : String`  
`function GetOptionValue(const C: Char;const S: String) : String`

Visibility: public

Description: `GetOptionValue` returns the value of an option. Values are specified in the usual GNU option format, either of

`--longopt=Value`

or

`-c Value`

is supported.

The function returns the specified value, or the empty string if none was specified.

Depending on the value of the `CaseSensitiveOptions` (??) property, the search is performed case sensitive or case insensitive.

Options are identified as command-line parameters which start with `OptionChar` (??) (by default the dash ('-') character).

See also: `FindOptionIndex` (??), `HasOption` (??), `CheckOptions` (??), `CaseSensitiveOptions` (??), `OptionChar` (??)

### 8.4.13 TCustomApplication.HasOption

Synopsis: Check whether an option was specified.

Declaration: `function HasOption(const S: String) : Boolean`  
`function HasOption(const C: Char;const S: String) : Boolean`

Visibility: public

Description: `HasOption` returns `True` if the specified option was given on the command line. Either the short option character `C` or the long option `S` may be used. Note that both options (requiring a value) and switches can be specified.

Depending on the value of the `CaseSensitiveOptions` (??) property, the search is performed case sensitive or case insensitive.

Options are identified as command-line parameters which start with `OptionChar` (??) (by default the dash ('-') character).

See also: `FindOptionIndex` (??), `GetOptionValue` (??), `CheckOptions` (??), `CaseSensitiveOptions` (??), `OptionChar` (??)

### 8.4.14 TCustomApplication.CheckOptions

Synopsis: Check whether all given options on the command-line are valid.

Declaration: `function CheckOptions(const ShortOptions: String;`  
`const Longopts: TStrings;Opts: TStrings;`  
`NonOpts: TStrings) : String`  
`function CheckOptions(const ShortOptions: String;`  
`const Longopts: TStrings) : String`  
`function CheckOptions(const ShortOptions: String;`  
`const LongOpts: Array of String) : String`  
`function CheckOptions(const ShortOptions: String;const LongOpts: String)`  
`: String`

Visibility: public

Description: `CheckOptions` scans the command-line and checks whether the options given are valid options. It also checks whether options that require a value are indeed specified with a value.

The `ShortOptions` contains a string with valid short option characters. Each character in the string is a valid option character. If a character is followed by a colon (:), then a value must be specified. If it is followed by 2 colon characters (::) then the value is optional.

`LongOpts` is a list of strings (which can be specified as an array, a `TStrings` instance or a string with whitespace-separated values) of valid long options.

When the function returns, if `Opts` is non-`Nil`, the `Opts` stringlist is filled with the passed valid options. If `NonOpts` is non-`nil`, it is filled with any non-option strings that were passed on the command-line.

The function returns an empty string if all specified options were valid options, and whether options requiring a value have a value. If an error was found during the check, the return value is a string describing the error.

Options are identified as command-line parameters which start with `OptionChar` (??) (by default the dash ('-') character).

Errors: if an error was found during the check, the return value is a string describing the error.

See also: `FindOptionIndex` (??), `GetOptionValue` (??), `HasOption` (??), `CaseSensitiveOptions` (??), `OptionChar` (??)

### 8.4.15 TCustomApplication.GetEnvironmentList

Synopsis: Return a list of environment variables.

Declaration: `procedure GetEnvironmentList(List: TStrings; NamesOnly: Boolean)`  
`procedure GetEnvironmentList(List: TStrings)`

Visibility: public

Description: `GetEnvironmentList` returns a list of environment variables in `List`. They are in the form `Name=Value`, one per item in `list`. If `NamesOnly` is `True`, then only the names are returned.

See also: `EnvironmentVariable` (??)

### 8.4.16 TCustomApplication.Log

Synopsis: Write a message to the event log

Declaration: `procedure Log(EventType: TEventType; const Msg: String)`

Visibility: public

Description: `Log` is meant for all applications to have a default logging mechanism. By default it does not do anything, descendent classes should override this method to provide appropriate logging: they should write the message `Msg` with type `EventType` to some log mechanism such as `#fcl.eventlog.TEventLog` (414)

Errors: None.

See also: `#rtl.sysutils.TEventType` (??)

### 8.4.17 TCustomApplication.ExeName

Synopsis: Name of the executable.

Declaration: `Property ExeName : String`

Visibility: public

Access: Read

**Description:** `ExeName` returns the full name of the executable binary (path+filename). This is equivalent to `ParamStr(0)`

Note that some operating systems do not return the full pathname of the binary.

See also: `ParamStr` (??)

### 8.4.18 TCustomApplication.HelpFile

**Synopsis:** Location of the application help file.

**Declaration:** `Property HelpFile : String`

**Visibility:** public

**Access:** Read,Write

**Description:** `HelpFile` is the location of the application help file. It is a simple string property which can be set by an IDE such as Lazarus, and is mainly provided for compatibility with Delphi's `TApplication` implementation.

See also: `TCustomApplication.Title` (??)

### 8.4.19 TCustomApplication.Terminated

**Synopsis:** Was `Terminate` called or not

**Declaration:** `Property Terminated : Boolean`

**Visibility:** public

**Access:** Read

**Description:** `Terminated` indicates whether `Terminate` (??) was called or not. Descendent classes should check `Terminated` at regular intervals in their implementation of `DoRun`, and if it is set to `True`, should exit gracefully the `DoRun` method.

See also: `Terminate` (??)

### 8.4.20 TCustomApplication.Title

**Synopsis:** Application title

**Declaration:** `Property Title : String`

**Visibility:** public

**Access:** Read,Write

**Description:** `Title` is a simple string property which can be set to any string describing the application. It does nothing by itself, and is mainly introduced for compatibility with Delphi's `TApplication` implementation.

See also: `HelpFile` (??)

### 8.4.21 TCustomApplication.OnException

Synopsis: Exception handling event

Declaration: `Property OnException : TExceptionEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnException` can be set to provide custom handling of events, instead of the default action, which is simply to show the event using `ShowEvent (??)`.

If set, `OnException` is called by the `HandleEvent (??)` routine. Do not use the `OnException` event directly, instead call `HandleEvent`

See also: `ShowEvent (??)`

### 8.4.22 TCustomApplication.ConsoleApplication

Synopsis: Is the application a console application or not

Declaration: `Property ConsoleApplication : Boolean`

Visibility: `public`

Access: `Read`

Description: `ConsoleApplication` returns `True` if the application is compiled as a console application (the default) or `False` if not. The result of this property is determined at compile-time by the settings of the compiler: it returns the value of the `IsConsole (??)` constant.

See also: `IsConsole (??)`

### 8.4.23 TCustomApplication.Location

Synopsis: Application location

Declaration: `Property Location : String`

Visibility: `public`

Access: `Read`

Description: `Location` returns the directory part of the application binary. This property works on most platforms, although some platforms do not allow to retrieve this information (Mac OS under certain circumstances). See the discussion of `Paramstr (??)` in the RTL documentation.

See also: `Paramstr (??)`, `Params (??)`

### 8.4.24 TCustomApplication.Params

Synopsis: Command-line parameters

Declaration: `Property Params[Index: Integer]: String`

Visibility: `public`

Access: `Read`

**Description:** `Params` gives access to the command-line parameters. They contain the value of the `Index`-th parameter, where `Index` runs from 0 to `ParamCount (??)`. It is equivalent to calling `ParamStr (??)`.

See also: `ParamCount (??)`, `Paramstr (??)`

### 8.4.25 TCustomApplication.ParamCount

**Synopsis:** Number of command-line parameters

**Declaration:** `Property ParamCount : Integer`

**Visibility:** `public`

**Access:** `Read`

**Description:** `ParamCount` returns the number of command-line parameters that were passed to the program. The actual parameters can be retrieved with the `Params (??)` property.

See also: `Params (??)`, `Paramstr (??)`, `ParamCount (??)`

### 8.4.26 TCustomApplication.EnvironmentVariable

**Synopsis:** Environment variable access

**Declaration:** `Property EnvironmentVariable[envName: String]: String`

**Visibility:** `public`

**Access:** `Read`

**Description:** `EnvironmentVariable` gives access to the environment variables of the application: It returns the value of the environment variable `EnvName`, or an empty string if no such value is available.

To use this property, the name of the environment variable must be known. To get a list of available names (and values), `GetEnvironmentList (??)` can be used.

See also: `GetEnvironmentList (??)`, `TCustomApplication.Params (??)`

### 8.4.27 TCustomApplication.OptionChar

**Synopsis:** Command-line switch character

**Declaration:** `Property OptionChar : Char`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `OptionChar` is the character used for command line switches. By default, this is the dash ('-') character, but it can be set to any other non-alphanumeric character (although no check is performed on this).

See also: `FindOptionIndex (??)`, `GetOptionValue (??)`, `HasOption (??)`, `CaseSensitiveOptions (??)`, `CheckOptions (??)`



### 8.4.28 TCustomApplication.CaseSensitiveOptions

Synopsis: Are options interpreted case sensitive or not

Declaration: Property CaseSensitiveOptions : Boolean

Visibility: public

Access: Read,Write

Description: CaseSensitiveOptions determines whether FindOptionIndex (??) and CheckOptions (??) perform searches in a case sensitive manner or not. By default, the search is case-sensitive. Setting this property to False makes the search case-insensitive.

See also: FindOptionIndex (??), GetOptionValue (??), HasOption (??), OptionChar (??), CheckOptions (??)

### 8.4.29 TCustomApplication.StopOnException

Synopsis: Should the program loop stop on an exception

Declaration: Property StopOnException : Boolean

Visibility: public

Access: Read,Write

Description: StopOnException controls the behaviour of the Run (??) and HandleException (??) procedures in case of an unhandled exception in the DoRun code. If StopOnException is True then Terminate (??) will be called after the exception was handled.

See also: Run (??), HandleException (??), Terminate (??)

### 8.4.30 TCustomApplication.EventLogFilter

Synopsis: Event to filter events, before they are sent to the system log

Declaration: Property EventLogFilter : TEventLogTypes

Visibility: public

Access: Read,Write

Description: EventLogFilter can be set to a set of event types that should be logged to the system log. If the set is empty, all event types are sent to the system log. If the set is non-empty, the TCustomApplication.Log (??) routine will check if the log event type is in the set, and if not, will not send the message to the system log.

See also: TCustomApplication.Log (??)

## Chapter 9

# Reference for unit 'daemonapp'

### 9.1 Used units

Table 9.1: Used units by unit 'daemonapp'

Name	Page
Classes	??
CustApp	<a href="#">166</a>
eventlog	<a href="#">412</a>
rtlconsts	??
System	??
sysutils	??

### 9.2 Overview

The `daemonapp` unit implements a `TApplication` class which encapsulates a daemon or service application. It handles installation where this is necessary, and does instantiation of the various daemons where necessary.

The unit consists of 3 separate classes which cooperate tightly:

**TDaemon** This is a class that implements the daemon's functionality. One or more descendents of this class can be implemented and instantiated in a single daemon application. For more information, see `TDaemon` ([193](#)).

**TDaemonApplication** This is the actual daemon application class. A global instance of this class is instantiated. It handles the command-line arguments, and instantiates the various daemons. For more information, see `TDaemonApplication` ([198](#)).

**TDaemonDef** This class defines the daemon in the operation system. The `TDaemonApplication` class has a collection of `TDaemonDef` instances, which it uses to start the various daemons. For more information, see `TDaemonDef` ([201](#)).

As can be seen, a single application can implement one ore more daemons (services). Each daemon will be run in a separate thread which is controlled by the application class.

The classes take care of logging through the `TEventLog` ([414](#)) class.

Many options are needed only to make the application behave as a windows service application on windows. These options are ignored in unix-like environment. The documentation will mention this.

## 9.3 Daemon application architecture

[Still needs to be completed]

## 9.4 Constants, types and variables

### 9.4.1 Resource strings

```
SControlFailed = '''Control code %s handling failed: %s'''
```

The control code was not handled correctly

```
SCustomCode = '''[Custom code %d]'''
```

A custom code was received

```
SDaemonStatus = '''Daemon %s current status: %s'''
```

Daemon status report log message

```
SErrApplicationAlreadyCreated = '''An application instance of class %s was already c
```

A second application instance is created

```
SErrDaemonStartFailed = '''Failed to start daemon %s : %s'''
```

The application failed to start the daemon

```
SErrDuplicateName = '''Duplicate daemon name: %s'''
```

Duplicate service name

```
SErrNoDaemonDefForStatus = '''%s: No daemon definition for status report'''
```

Internal error: no daemon definition to report status for

```
SErrNoDaemonForStatus = '''%s: No daemon for status report'''
```

Internal error: no daemon to report status for

```
SErrNoServiceMapper = '''No daemon mapper class registered.'''
```

No service mapper was found.

```
SErrNothingToDo = '''No command given, use ''''%s -h'''' for usage.'''
```

No operation can be performed

```
SErrOnlyOneMapperAllowed = '''Not changing daemon mapper class %s with %s: Only 1 map
```

An attempt was made to install a second service mapper

```
SErrServiceManagerStartFailed = '''Failed to start service manager: %s'''
```

Unable to start or contact the service manager

```
SErrUnknownDaemonClass = '''Unknown daemon class name: %s'''
```

Unknown daemon class requested

```
SErrWindowClass = '''Could not register window class'''
```

Could not register window class

```
SHelpCommand = '''Where command is one of the following:'''
```

Options message displayed when writing help to the console

```
SHelpInstall = '''To install the program as a service'''
```

Install option message displayed when writing help to the console

```
SHelpRun = '''To run the service'''
```

Run option message displayed when writing help to the console

```
SHelpUnInstall = '''To uninstall the service'''
```

Uninstall option message displayed when writing help to the console

```
SHelpUsage = '''Usage: %s [command]'''
```

Usage message displayed when writing help to the console

## 9.4.2 Types

```
TCurrentStatus = (csStopped, csStartPending, csStopPending, csRunning,
                  csContinuePending, csPausePending, csPaused)
```

Table 9.2: Enumeration values for type TCurrentStatus

Value	Explanation
csContinuePending	The daemon is continuing, but not yet running
csPaused	The daemon is paused: running but not active.
csPausePending	The daemon is about to be paused.
csRunning	The daemon is running (it is operational).
csStartPending	The daemon is starting, but not yet fully running.
csStopped	The daemon is stopped, i.e. inactive.
csStopPending	The daemon is stopping, but not yet fully stopped.

TCurrentStatus indicates the current state of the daemon. It changes from one state to the next during the time the instance is active. The daemon application changes the state of the daemon, depending on signals it gets from the operating system, by calling the appropriate methods.

```
TCustomControlCodeEvent = procedure(Sender: TCustomDaemon; ACode: DWord;
                                   var Handled: Boolean) of object
```

In case the system sends a non-standard control code to the daemon, an event handler is executed with this prototype.

```
TCustomDaemonApplicationClass = Class of TCustomDaemonApplication
```

Class pointer for TCustomDaemonApplication

```
TCustomDaemonClass = Class of TCustomDaemon
```

The class type is needed in the TDaemonDef (201) definition.

```
TCustomDaemonMapperClass = Class of TCustomDaemonMapper
```

TCustomDaemonMapperClass is the class of TCustomDaemonMapper. It is used in the RegisterDaemonMapper (183) call.

```
TDaemonClass = Class of TDaemon
```

Class type of TDaemon

```
TDaemonEvent = procedure(Sender: TCustomDaemon) of object
```

TDaemonEvent is used in event handling. The Sender is the TCustomDaemon (184) instance that has initiated the event.

```
TDaemonOKEvent = procedure(Sender: TCustomDaemon; var OK: Boolean)
                  of object
```

TDaemonOKEvent is used in event handling, when a boolean result must be obtained, for instance, to see if an operation was performed successfully.

```
TDaemonOption = (doAllowStop, doAllowPause, doInteractive)
```

Table 9.3: Enumeration values for type TDaemonOption

Value	Explanation
doAllowPause	The daemon can be paused.
doAllowStop	The daemon can be stopped.
doInteractive	The daemon interacts with the desktop.

Enumerated that enumerates the various daemon operation options.

```
TDaemonOptions= Set of (doAllowPause, doAllowStop, doInteractive)
```

TDaemonOption enumerates the various options a daemon can have.

`TDaemonRunMode = (drmUnknown, drmInstall, drmUninstall, drmRun)`

Table 9.4: Enumeration values for type `TDaemonRunMode`

Value	Explanation
<code>drmInstall</code>	Daemon install mode (windows only)
<code>drmRun</code>	Daemon is running normally
<code>drmUninstall</code>	Daemon uninstall mode (windows only)
<code>drmUnknown</code>	Unknown mode

`TDaemonRunMode` indicates in what mode the daemon application (as a whole) is currently running.

`TErrorSeverity = (esIgnore, esNormal, esSevere, esCritical)`

Table 9.5: Enumeration values for type `TErrorSeverity`

Value	Explanation
<code>esCritical</code>	Error is logged, and startup is stopped if last known good configuration is active, or system is restarted using last known good configuration
<code>esIgnore</code>	Ignore startup errors
<code>esNormal</code>	Error is logged, but startup continues
<code>esSevere</code>	Error is logged, and startup is continued if last known good configuration is active, or system is restarted using last known good configuration

`TErrorSeverity` determines what action windows takes when the daemon fails to start. It is used on windows only, and is ignored on other platforms.

`TGuiLoopEvent = procedure of object`

`TGuiLoopEvent` is the main GUI loop event procedure prototype. It is called by the application instance in case the daemon has a visual part, which needs to handle visual events. It is run in the main application thread.

`TServiceType = (stWin32, stDevice, stFileSystem)`

Table 9.6: Enumeration values for type `TServiceType`

Value	Explanation
<code>stDevice</code>	Device driver
<code>stFileSystem</code>	File system driver
<code>stWin32</code>	Regular win32 service

The type of service. This type is used on windows only, to signal the operating system what kind of service is being installed or run.

`TStartType = (stBoot, stSystem, stAuto, stManual, stDisabled)`

Table 9.7: Enumeration values for type TStartType

Value	Explanation
stAuto	Started automatically by service manager during system startup
stBoot	During system boot
stDisabled	Service is not started, it is disabled
stManual	Started manually by the user or other processes.
stSystem	During load of device drivers

TStartType can be used to define when the service must be started on windows. This type is not used on other platforms.

### 9.4.3 Variables

`AppClass` : TCustomDaemonApplicationClass

`AppClass` can be set to the class of a TCustomDaemonApplication (186) descendant. When the `Application` (182) function needs to create an application instance, this class will be used. If `Application` was already called, the value of `AppClass` will be ignored.

`CurrentStatusNames` : Array[TCurrentStatus] of String = (''Stopped'', ''Start Pending'')

Names for various service statuses

`DefaultDaemonOptions` : TDaemonOptions = [doAllowStop, doAllowPause]

`DefaultDaemonOptions` are the default options with which a daemon definition (TDaemonDef (201)) is created.

`SStatus` : Array[1..5] of String = (''Stop'', ''Pause'', ''Continue'', ''Interrogation'')

Status message

## 9.5 Procedures and functions

### 9.5.1 Application

Synopsis: `Application` instance

Declaration: `function Application` : TCustomDaemonApplication

Visibility: default

Description: `Application` is the TCustomDaemonApplication (186) instance used by this application. The instance is created at the first invocation of this function, so it is possible to use `RegisterDaemonApplicationClass` (183) to register an alternative TCustomDaemonApplication class to run the application.

See also: TCustomDaemonApplication (186), RegisterDaemonApplicationClass (183)

### 9.5.2 DaemonError

Synopsis: Raise an EDaemon exception

Declaration: `procedure DaemonError(Msg: String)`  
`procedure DaemonError(Fmt: String; Args: Array of const)`

Visibility: default

Description: `DemonError` raises an EDaemon (184) exception with message `Msg` or it formats the message using `Fmt` and `Args`.

See also: EDaemon (184)

### 9.5.3 RegisterDaemonApplicationClass

Synopsis: Register alternative TCustomDaemonApplication class.

Declaration: `procedure RegisterDaemonApplicationClass`  
`(AClass: TCustomDaemonApplicationClass)`

Visibility: default

Description: `RegisterDaemonApplicationClass` can be used to register an alternative TCustomDaemonApplication (186) descendent which will be used when creating the global Application (182) instance. Only the last registered class pointer will be used.

See also: TCustomDaemonApplication (186), Application (182)

### 9.5.4 RegisterDaemonClass

Synopsis: Register daemon

Declaration: `procedure RegisterDaemonClass(AClass: TCustomDaemonClass)`

Visibility: default

Description: `RegisterDaemonClass` must be called for each TCustomDaemon (184) descendent that is used in the class: the class pointer and class name are used by the TCustomDaemonMapperClass (180) class to create a TCustomDaemon instance when a daemon is required.

See also: TCustomDaemonMapperClass (180), TCustomDaemon (184)

### 9.5.5 RegisterDaemonMapper

Synopsis: Register a daemon mapper class

Declaration: `procedure RegisterDaemonMapper(AMapperClass: TCustomDaemonMapperClass)`

Visibility: default

Description: `RegisterDaemonMapper` can be used to register an alternative class for the global daemon-mapper. The daemonmapper will be used only when the application is being run, by the TCustomDaemonApplication (186) code, so registering an alternative mapping class should happen in the initialization section of the application units.

See also: TCustomDaemonApplication (186), TCustomDaemonMapperClass (180)



## 9.6 EDaemon

### 9.6.1 Description

EDaemon is the exception class used by all code in the DaemonApp unit.

See also: DaemonError ([183](#))

## 9.7 TCustomDaemon

### 9.7.1 Description

TCustomDaemon implements all the basic calls that are needed for a daemon to function. Descendents of TCustomDaemon can override these calls to implement the daemon-specific behaviour.

TCustomDaemon is an abstract class, it should never be instantiated. Either a descendent of it must be created and instantiated, or a descendent of TDaemon ([193](#)) can be designed to implement the behaviour of the daemon.

See also: TDaemon ([193](#)), TDaemonDef ([201](#)), TDaemonController ([198](#)), TDaemonApplication ([198](#))

### 9.7.2 Method overview

Page	Property	Description
<a href="#">184</a>	LogMessage	Log a message to the system log
<a href="#">185</a>	ReportStatus	Report the current status to the operating system

### 9.7.3 Property overview

Page	Property	Access	Description
<a href="#">186</a>	Controller	r	TDaemonController instance controlling this daemon instance
<a href="#">185</a>	DaemonThread	r	Thread in which daemon is running
<a href="#">185</a>	Definition	r	The definition used to instantiate this daemon instance
<a href="#">186</a>	Logger	r	TEventLog instance used to send messages to the system log
<a href="#">186</a>	Status	rw	Current status of the daemon

### 9.7.4 TCustomDaemon.LogMessage

Synopsis: Log a message to the system log

Declaration: `procedure LogMessage(const Msg: String)`

Visibility: public

Description: LogMessage can be used to send a message Msg to the system log. A TEventLog ([414](#)) instance is used to actually send messages to the system log.

The message is sent with an 'error' flag (using TEventLog.Error ([417](#))).

Errors: None.

See also: ReportStatus ([??](#))

### 9.7.5 TCustomDaemon.ReportStatus

Synopsis: Report the current status to the operating system

Declaration: `procedure ReportStatus`

Visibility: `public`

Description: `ReportStatus` can be used to report the current status to the operating system. The start and stop or pause and continue operations can be slow to start up. This call can (and should) be used to report the current status to the operating system during such lengthy operations, or else it may conclude that the daemon has died.

This call is mostly important on windows operating systems, to notify the service manager that the operation is still in progress.

The implementation of `ReportStatus` simply calls `ReportStatus` in the controller.

Errors: None.

See also: `LogMessage` (??)

### 9.7.6 TCustomDaemon.Definition

Synopsis: The definition used to instantiate this daemon instance

Declaration: `Property Definition : TDaemonDef`

Visibility: `public`

Access: `Read`

Description: `Definition` is the `TDaemonDef` (201) definition that was used to start the daemon instance. It can be used to retrieve additional information about the intended behaviour of the daemon.

See also: `TDaemonDef` (201)

### 9.7.7 TCustomDaemon.DaemonThread

Synopsis: Thread in which daemon is running

Declaration: `Property DaemonThread : TThread`

Visibility: `public`

Access: `Read`

Description: `DaemonThread` is the thread in which the daemon instance is running. Each daemon instance in the application runs in it's own thread, none of which are the main thread of the application. The application main thread is used to handle control messages coming from the operating system.

See also: `Controller` (??)

### 9.7.8 TCustomDaemon.Controller

Synopsis: TDaemonController instance controlling this daemon instance

Declaration: Property Controller : TDaemonController

Visibility: public

Access: Read

Description: Controller points to the TDaemonController instance that was created by the application instance to control this daemon.

See also: DaemonThread (??)

### 9.7.9 TCustomDaemon.Status

Synopsis: Current status of the daemon

Declaration: Property Status : TCurrentStatus

Visibility: public

Access: Read,Write

Description: Status indicates the current status of the daemon. It is set by the various operations that the controller operates on the daemon, and should not be set manually.

Status is the value which ReportStatus will send to the operating system.

See also: ReportStatus (??)

### 9.7.10 TCustomDaemon.Logger

Synopsis: TEventLog instance used to send messages to the system log

Declaration: Property Logger : TEventLog

Visibility: public

Access: Read

Description: Logger is the TEventLog (414) instance used to send messages to the system log. It is used by the LogMessage (??) call, but is accessible through the Logger property in case more configurable logging is needed than offered by LogMessage.

See also: LogMessage (??), TEventLog (414)

## 9.8 TCustomDaemonApplication

### 9.8.1 Description

TCustomDaemonApplication is a TCustomApplication (167) descendent which is the main application instance for a daemon. It handles the command-line and decides what to do when the application is started, depending on the command-line options given to the application, by calling the various methods.

It creates the necessary TDaemon (193) instances by checking the TCustomDaemonMapperClass (180) instance that contains the daemon maps.

See also: TCustomApplication (167), TCustomDaemonMapperClass (180)

### 9.8.2 Method overview

Page	Property	Description
<a href="#">187</a>	CreateDaemon	Create daemon instance
<a href="#">189</a>	CreateForm	Create a component
<a href="#">187</a>	Destroy	Clean up the TCustomDaemonApplication instance
<a href="#">188</a>	InstallDaemons	Install all daemons.
<a href="#">188</a>	RunDaemons	Run all daemons.
<a href="#">187</a>	ShowException	Show an exception
<a href="#">189</a>	ShowHelp	Display a help message
<a href="#">188</a>	StopDaemons	Stop all daemons
<a href="#">188</a>	UnInstallDaemons	Uninstall all daemons

### 9.8.3 Property overview

Page	Property	Access	Description
<a href="#">190</a>	EventLog	r	Event logger instance
<a href="#">190</a>	GuiHandle	rw	Handle of GUI loop main application window handle
<a href="#">190</a>	GUIMainLoop	rw	GUI main loop callback
<a href="#">189</a>	OnRun	rw	Event executed when the daemon is run.
<a href="#">190</a>	RunMode	r	Application mode

### 9.8.4 TCustomDaemonApplication.Destroy

Synopsis: Clean up the TCustomDaemonApplication instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the event log instance and then calls the inherited `destroy`.

See also: `TCustomDaemonApplication.EventLog` (??)

### 9.8.5 TCustomDaemonApplication.ShowException

Synopsis: Show an exception

Declaration: `procedure ShowException(E: Exception); Override`

Visibility: `public`

Description: `ShowException` is overridden by `TCustomDaemonApplication`, it sends the exception message to the system log.

### 9.8.6 TCustomDaemonApplication.CreateDaemon

Synopsis: Create daemon instance

Declaration: `function CreateDaemon(DaemonDef: TDaemonDef) : TCustomDaemon`

Visibility: `public`

Description: `CreateDaemon` is called whenever a `TCustomDaemon` ([184](#)) instance must be created from a `TDaemonDef` ([201](#)) daemon definition, passed in `DaemonDef`. It initializes the `TCustomDaemon` instance, and creates a controller instance of type `TDaemonController` ([198](#)) to control the daemon. Finally, it assigns the created daemon to the `TDaemonDef.Instance` (??) property.

Errors: In case of an error, an exception may be raised.

See also: `TDaemonController` (198), `TCustomDaemon` (184), `TDaemonDef` (201), `TDaemonDef.Instance` (??)

### 9.8.7 `TCustomDaemonApplication.StopDaemons`

Synopsis: Stop all daemons

Declaration: `procedure StopDaemons(Force: Boolean)`

Visibility: public

Description: `StopDaemons` sends the `STOP` control code to all daemons, or the `SHUTDOWN` control code in case `Force` is `True`.

See also: `TDaemonController.Controller` (??), `TCustomDaemonApplication.UnInstallDaemons` (??), `TCustomDaemonApplication.RunDaemons` (??)

### 9.8.8 `TCustomDaemonApplication.InstallDaemons`

Synopsis: Install all daemons.

Declaration: `procedure InstallDaemons`

Visibility: public

Description: `InstallDaemons` installs all known daemons, i.e. registers them with the service manager on Windows. This method is called if the application is run with the `-i` or `-install` or `/install` command-line option.

See also: `TCustomDaemonApplication.UnInstallDaemons` (??), `TCustomDaemonApplication.RunDaemons` (??), `TCustomDaemonApplication.StopDaemons` (??)

### 9.8.9 `TCustomDaemonApplication.RunDaemons`

Synopsis: Run all daemons.

Declaration: `procedure RunDaemons`

Visibility: public

Description: `RunDaemons` runs (starts) all known daemons. This method is called if the application is run with the `-r` or `-run` methods.

See also: `TCustomDaemonApplication.UnInstallDaemons` (??), `TCustomDaemonApplication.InstallDaemons` (??), `TCustomDaemonApplication.StopDaemons` (??)

### 9.8.10 `TCustomDaemonApplication.UnInstallDaemons`

Synopsis: Uninstall all daemons

Declaration: `procedure UnInstallDaemons`

Visibility: public

**Description:** `UnInstallDaemons` uninstalls all known daemons, i.e. deregisters them with the service manager on Windows. This method is called if the application is run with the `-u` or `-uninstall` or `/uninstall` command-line option.

**See also:** `TCustomDaemonApplication.RunDaemons (??)`, `TCustomDaemonApplication.InstallDaemons (??)`, `TCustomDaemonApplication.StopDaemons (??)`

### 9.8.11 TCustomDaemonApplication.ShowHelp

**Synopsis:** Display a help message

**Declaration:** `procedure ShowHelp`

**Visibility:** `public`

**Description:** `ShowHelp` displays a help message explaining the command-line options on standard output.

### 9.8.12 TCustomDaemonApplication.CreateForm

**Synopsis:** Create a component

**Declaration:** `procedure CreateForm(InstanceClass: TComponentClass; var Reference)  
; Virtual`

**Visibility:** `public`

**Description:** `CreateForm` creates an instance of `InstanceClass` and fills `Reference` with the class instance pointer. It's main purpose is to give an IDE a means of assuring that forms or datamodules are created on application startup: the IDE will generate calls for all modules that are auto-created.

**Errors:** An exception may arise if the instance wants to stream itself from resources, but no resources are found.

**See also:** `TCustomDaemonApplication.CreateDaemon (??)`

### 9.8.13 TCustomDaemonApplication.OnRun

**Synopsis:** Event executed when the daemon is run.

**Declaration:** `Property OnRun : TNotifyEvent`

**Visibility:** `public`

**Access:** `Read, Write`

**Description:** `OnRun` is triggered when the daemon application is run and no appropriate options (one of `install`, `uninstall` or `run`) was given.

**See also:** `TCustomDaemonApplication.RunDaemons (??)`, `TCustomDaemonApplication.InstallDaemons (??)`, `TCustomDaemonApplication.UnInstallDaemons (??)`

### 9.8.14 TCustomDaemonApplication.EventLog

Synopsis: Event logger instance

Declaration: `Property EventLog : TEventLog`

Visibility: public

Access: Read

Description: `EventLog` is the `TEventLog` (414) instance which is used to log events to the system log with the `Log (??)` method. It is created when the application instance is created, and destroyed when the application is destroyed.

See also: `TEventLog` (414), `Log (??)`

### 9.8.15 TCustomDaemonApplication.GUIMainLoop

Synopsis: GUI main loop callback

Declaration: `Property GUIMainLoop : TGuiLoopEvent`

Visibility: public

Access: Read, Write

Description: `GUIMainLoop` contains a reference to a method that can be called to process a main GUI loop. The procedure should return only when the main GUI has finished and the application should exit. It is called when the daemons are running.

See also: `TCustomDaemonApplication.GuiHandle (??)`

### 9.8.16 TCustomDaemonApplication.GuiHandle

Synopsis: Handle of GUI loop main application window handle

Declaration: `Property GuiHandle : THandle`

Visibility: public

Access: Read, Write

Description: `GuiHandle` is the handle of a GUI window which can be used to run a message handling loop on. It is created when no `GUIMainLoop (??)` procedure exists, and the application creates and runs a message loop by itself.

See also: `GUIMainLoop (??)`

### 9.8.17 TCustomDaemonApplication.RunMode

Synopsis: Application mode

Declaration: `Property RunMode : TDaemonRunMode`

Visibility: public

Access: Read

Description: `RunMode` indicates in which mode the application is running currently. It is set automatically by examining the command-line, and when set, one of `InstallDaemons (??)`, `RunDaemons (??)` or `UnInstallDaemons (??)` is called.

See also: `InstallDaemons (??)`, `RunDaemons (??)`, `UnInstallDaemons (??)`

## 9.9 TCustomDaemonMapper

### 9.9.1 Description

The TCustomDaemonMapper class is responsible for mapping a daemon definition to an actual TDaemon instance. It maintains a TDaemonDefs (205) collection with daemon definitions, which can be used to map the definition of a daemon to a TDaemon descendent class.

An IDE such as Lazarus can design a TCustomDaemonMapper instance visually, to help establish the relationship between various TDaemonDef (201) definitions and the actual TDaemon (193) instances that will be used to run the daemons.

The TCustomDaemonMapper class has no support for streaming. The TDaemonMapper (207) class has support for streaming (and hence visual designing).

See also: TDaemon (193), TDaemonDef (201), TDaemonDefs (205), TDaemonMapper (207)

### 9.9.2 Method overview

Page	Property	Description
<a href="#">191</a>	Create	Create a new instance of TCustomDaemonMapper
<a href="#">191</a>	Destroy	Clean up and destroy a TCustomDaemonMapper instance.

### 9.9.3 Property overview

Page	Property	Access	Description
<a href="#">192</a>	DaemonDefs	rw	Collection of daemons
<a href="#">192</a>	OnCreate	rw	Event called when the daemon mapper is created
<a href="#">192</a>	OnDestroy	rw	Event called when the daemon mapper is freed.
<a href="#">193</a>	OnInstall	rw	Event called when the daemons are installed
<a href="#">192</a>	OnRun	rw	Event called when the daemons are executed.
<a href="#">193</a>	OnUnInstall	rw	Event called when the daemons are uninstalled

### 9.9.4 TCustomDaemonMapper.Create

Synopsis: Create a new instance of TCustomDaemonMapper

Declaration: constructor Create(AOwner: TComponent); Override

Visibility: public

Description: Create creates a new instance of a TCustomDaemonMapper. It creates the TDaemonDefs (205) collection and then calls the inherited constructor. It should never be necessary to create a daemon mapper manually, the application will create a global TCustomDaemonMapper instance.

See also: TDaemonDefs (205), TCustomDaemonApplication (186), TCustomDaemonMapper.Destroy (??)

### 9.9.5 TCustomDaemonMapper.Destroy

Synopsis: Clean up and destroy a TCustomDaemonMapper instance.

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy frees the DaemonDefs (??) collection and calls the inherited destructor.



See also: [TDaemonDefs \(205\)](#), [TCustomDaemonMapper.Create \(??\)](#)

### 9.9.6 TCustomDaemonMapper.DaemonDefs

Synopsis: Collection of daemons

Declaration: `Property DaemonDefs : TDaemonDefs`

Visibility: published

Access: Read,Write

Description: `DaemonDefs` is the application's global collection of daemon definitions. This collection will be used to decide at runtime which `TDaemon` class must be created to run or install a daemon.

See also: [TCustomDaemonApplication \(186\)](#)

### 9.9.7 TCustomDaemonMapper.OnCreate

Synopsis: Event called when the daemon mapper is created

Declaration: `Property OnCreate : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnCreate` is an event that is called when the `TCustomDaemonMapper` instance is created. It can for instance be used to dynamically create daemon definitions at runtime.

See also: [OnDestroy \(??\)](#), [OnUnInstall \(??\)](#), [OnCreate \(??\)](#), [OnDestroy \(??\)](#)

### 9.9.8 TCustomDaemonMapper.OnDestroy

Synopsis: Event called when the daemon mapper is freed.

Declaration: `Property OnDestroy : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnDestroy` is called when the global daemon mapper instance is destroyed. it can be used to release up any resources that were allocated when the instance was created, in the `OnCreate (??)` event.

See also: [OnCreate \(??\)](#), [OnInstall \(??\)](#), [OnUnInstall \(??\)](#), [OnCreate \(??\)](#)

### 9.9.9 TCustomDaemonMapper.OnRun

Synopsis: Event called when the daemons are executed.

Declaration: `Property OnRun : TNotifyEvent`

Visibility: published

Access: Read,Write

**Description:** `OnRun` is the event called when the daemon application is executed to run the daemons (with command-line parameter `'-r'`). it is called exactly once.

See also: `OnInstall` (??), `OnUnInstall` (??), `OnCreate` (??), `OnDestroy` (??)

### 9.9.10 TCustomDaemonMapper.OnInstall

**Synopsis:** Event called when the daemons are installed

**Declaration:** `Property OnInstall : TNotifyEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnInstall` is the event called when the daemon application is executed to install the daemons (with command-line parameter `'-i'` or `'/install'`). it is called exactly once.

See also: `OnRun` (??), `OnUnInstall` (??), `OnCreate` (??), `OnDestroy` (??)

### 9.9.11 TCustomDaemonMapper.OnUnInstall

**Synopsis:** Event called when the daemons are uninstalled

**Declaration:** `Property OnUnInstall : TNotifyEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnUnInstall` is the event called when the daemon application is executed to uninstall the daemons (with command-line parameter `'-u'` or `'/uninstall'`). it is called exactly once.

See also: `OnRun` (??), `OnInstall` (??), `OnCreate` (??), `OnDestroy` (??)

## 9.10 TDaemon

### 9.10.1 Description

`TDaemon` is a `TCustomDaemon` (184) descendent which is meant for development in a visual environment: it contains event handlers for all major operations. Whenever a `TCustomDaemon` method is executed, it's execution is shunted to the event handler, which can be filled with code in the IDE.

All the events of the daemon are executed in the thread in which the daemon's controller is running (as given by `DaemonThread` (??)), which is not the main program thread.

See also: `TCustomDaemon` (184), `TDaemonController` (198)

### 9.10.2 Property overview

Page	Property	Access	Description
<a href="#">197</a>	AfterInstall	rw	Called after the daemon was installed
<a href="#">197</a>	AfterUnInstall	rw	Called after the daemon is uninstalled
<a href="#">196</a>	BeforeInstall	rw	Called before the daemon will be installed
<a href="#">197</a>	BeforeUnInstall	rw	Called before the daemon is uninstalled
<a href="#">194</a>	Definition		
<a href="#">195</a>	OnContinue	rw	Daemon continue
<a href="#">197</a>	OnControlCode	rw	Called when a control code is received for the daemon
<a href="#">196</a>	OnExecute	rw	Daemon execute event
<a href="#">195</a>	OnPause	rw	Daemon pause event
<a href="#">196</a>	OnShutDown	rw	Daemon shutdown
<a href="#">194</a>	OnStart	rw	Daemon start event
<a href="#">195</a>	OnStop	rw	Daemon stop event
<a href="#">194</a>	Status		

### 9.10.3 TDaemon.Definition

Declaration: `Property Definition` :

Visibility: public

Access:

### 9.10.4 TDaemon.Status

Declaration: `Property Status` :

Visibility: public

Access:

### 9.10.5 TDaemon.OnStart

Synopsis: Daemon start event

Declaration: `Property OnStart` : `TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnStart` is the event called when the daemon must be started. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus (??)` method.

If the start of the daemon should do some continuous action, then this action should be performed in a new thread: this thread should then be created and started in the `OnExecute (??)` event handler, so the event handler can return at once.

See also: `TDaemon.OnStop (??)`, `TDaemon.OnExecute (??)`, `TDaemon.OnContinue (??)`, `ReportStatus (??)`

### 9.10.6 TDaemon.OnStop

Synopsis: Daemon stop event

Declaration: `Property OnStop : TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnStart` is the event called when the daemon must be stopped. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus (??)` method.

If a thread was started in the `OnExecute (??)` event, this is the place where the thread should be stopped.

See also: `TDaemon.OnStart (??)`, `TDaemon.OnPause (??)`, `ReportStatus (??)`

### 9.10.7 TDaemon.OnPause

Synopsis: Daemon pause event

Declaration: `Property OnPause : TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnPause` is the event called when the daemon must be stopped. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus (??)` method.

If a thread was started in the `OnExecute (??)` event, this is the place where the thread's execution should be suspended.

See also: `TDaemon.OnStop (??)`, `TDaemon.OnContinue (??)`, `ReportStatus (??)`

### 9.10.8 TDaemon.OnContinue

Synopsis: Daemon continue

Declaration: `Property OnContinue : TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnPause` is the event called when the daemon must be stopped. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus (??)` method.

If a thread was started in the `OnExecute (??)` event and it was suspended in a `OnPause (??)` event, this is the place where the thread's executed should be resumed.

See also: `TDaemon.OnStart (??)`, `TDaemon.OnPause (??)`, `ReportStatus (??)`

### 9.10.9 TDaemon.OnShutDown

Synopsis: Daemon shutdown

Declaration: `Property OnShutDown : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `OnShutDown` is the event called when the daemon must be shut down. When the system is being shut down and the daemon does not respond to stop signals, then a shutdown message is sent to the daemon. This event can be used to respond to such a message. The daemon process will simply be stopped after this event.

If a thread was started in the `OnExecute` (??), this is the place where the thread's executed should be stopped or the thread freed from memory.

See also: `TDaemon.OnStart` (??), `TDaemon.OnPause` (??), `ReportStatus` (??)

### 9.10.10 TDaemon.OnExecute

Synopsis: Daemon execute event

Declaration: `Property OnExecute : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `OnExecute` is executed once after the daemon was started. If assigned, it should perform whatever operation the daemon is designed.

If the daemon's action is event based, then no `OnExecute` handler is needed, and the events will control the daemon's execution: the daemon thread will then go in a loop, passing control messages to the daemon.

If an `OnExecute` event handler is present, the checking for control messages must be done by the implementation of the `OnExecute` handler.

See also: `TDaemon.OnStart` (??), `TDaemon.OnStop` (??)

### 9.10.11 TDaemon.BeforeInstall

Synopsis: Called before the daemon will be installed

Declaration: `Property BeforeInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `BeforeInstall` is called before the daemon is installed. It can be done to specify extra dependencies, or change the daemon description etc.

See also: `AfterInstall` (??), `BeforeUnInstall` (??), `AfterUnInstall` (??)

### 9.10.12 TDaemon.AfterInstall

Synopsis: Called after the daemon was installed

Declaration: `Property AfterInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `AfterInstall` is called after the daemon was successfully installed.

See also: `BeforeInstall` (??), `BeforeUnInstall` (??), `AfterUnInstall` (??)

### 9.10.13 TDaemon.BeforeUnInstall

Synopsis: Called before the daemon is uninstalled

Declaration: `Property BeforeUnInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `BeforeUnInstall` is called before the daemon is uninstalled.

See also: `BeforeInstall` (??), `AfterInstall` (??), `AfterUnInstall` (??)

### 9.10.14 TDaemon.AfterUnInstall

Synopsis: Called after the daemon is uninstalled

Declaration: `Property AfterUnInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `AfterUnInstall` is called after the daemon is successfully uninstalled.

See also: `BeforeInstall` (??), `AfterInstall` (??), `BeforeUnInstall` (??)

### 9.10.15 TDaemon.OnControlCode

Synopsis: Called when a control code is received for the daemon

Declaration: `Property OnControlCode : TCustomControlCodeEvent`

Visibility: published

Access: Read,Write

Description: `OnControlCode` is called when the daemon receives a control code. If the daemon has not handled the control code, it should set the `Handled` parameter to `False`. By default it is set to `True`.

See also: `Architecture` (??)

## 9.11 TDaemonApplication

### 9.11.1 Description

`TDaemonApplication` is the default `TCustomDaemonApplication` (186) descendent that is used to run the daemon application. It is possible to register an alternative `TCustomDaemonApplication` class (using `RegisterDaemonApplicationClass` (183)) to run the application in a different manner.

See also: `TCustomDaemonApplication` (186), `RegisterDaemonApplicationClass` (183)

## 9.12 TDaemonController

### 9.12.1 Description

`TDaemonController` is a class that is used by the `TDaemonApplication` (198) class to control the daemon during runtime. The `TDaemonApplication` class instantiates an instance of `TDaemonController` for each daemon in the application and communicates with the daemon through the `TDaemonController` instance. It should rarely be necessary to access or use this class.

See also: `TCustomDaemon` (184), `TDaemonApplication` (198)

### 9.12.2 Method overview

Page	Property	Description
<a href="#">199</a>	Controller	Controller
<a href="#">198</a>	Create	Create a new instance of the <code>TDaemonController</code> class
<a href="#">199</a>	Destroy	Free a <code>TDaemonController</code> instance.
<a href="#">199</a>	Main	Daemon main entry point
<a href="#">200</a>	ReportStatus	Report the status to the operating system.
<a href="#">199</a>	StartService	Start the service

### 9.12.3 Property overview

Page	Property	Access	Description
<a href="#">201</a>	CheckPoint		Send checkpoint signal to the operating system
<a href="#">200</a>	Daemon	r	Daemon instance this controller controls.
<a href="#">200</a>	LastStatus	r	Last reported status
<a href="#">200</a>	Params	r	Parameters passed to the daemon

### 9.12.4 TDaemonController.Create

Synopsis: Create a new instance of the `TDaemonController` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TDaemonController` class. It should never be necessary to create a new instance manually, because the controllers are created by the global `TDaemonApplication` (198) instance, and `AOwner` will be set to the global `TDaemonApplication` (198) instance.

See also: `TDaemonApplication` (198), `Destroy` (??)

### 9.12.5 TDaemonController.Destroy

Synopsis: Free a TDaemonController instance.

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy deallocates some resources allocated when the instance was created.

See also: Create (??)

### 9.12.6 TDaemonController.StartService

Synopsis: Start the service

Declaration: procedure StartService; Virtual

Visibility: public

Description: StartService starts the service controlled by this instance.

Errors: None.

See also: TDaemonController.Main (??)

### 9.12.7 TDaemonController.Main

Synopsis: Daemon main entry point

Declaration: procedure Main(Argc: DWord; Args: PPChar); Virtual

Visibility: public

Description: Main is the service's main entry point, called when the system wants to start the service. The global application will call this function whenever required, with the appropriate arguments.

The standard implementation starts the daemon thread, and waits for it to stop. All other daemon action - such as responding to control code events - is handled by the thread.

Errors: If the daemon thread cannot be created, an exception is raised.

See also: TDaemonThread ([208](#))

### 9.12.8 TDaemonController.Controller

Synopsis: Controller

Declaration: procedure Controller(ControlCode: DWord; EventType: DWord;  
EventData: Pointer); Virtual

Visibility: public

Description: Controller is responsible for sending the control code to the daemon thread so it can be processed.

This routine is currently only used on windows, as there is no service manager on linux. Later on this may be changed to respond to signals on linux as well.

See also: TDaemon.OnControlCode (??)



### 9.12.9 TDaemonController.ReportStatus

Synopsis: Report the status to the operating system.

Declaration: `function ReportStatus : Boolean; Virtual`

Visibility: `public`

Description: `ReportStatus` reports the status of the daemon to the operating system. On windows, this sends the current service status to the service manager. On other operating systems, this sends a message to the system log.

Errors: If an error occurs, an error message is sent to the system log.

See also: `TDaemon.ReportStatus (??)`, `TDaemonController.LastStatus (??)`

### 9.12.10 TDaemonController.Daemon

Synopsis: Daemon instance this controller controls.

Declaration: `Property Daemon : TCustomDaemon`

Visibility: `public`

Access: `Read`

Description: `Daemon` is the daemon instance that is controller by this instance of the `TDaemonController` class.

### 9.12.11 TDaemonController.Params

Synopsis: Parameters passed to the daemon

Declaration: `Property Params : TStrings`

Visibility: `public`

Access: `Read`

Description: `Params` contains the parameters passed to the daemon application by the operating system, comparable to the application's command-line parameters. The property is set by the `Main (??)` method.

### 9.12.12 TDaemonController.LastStatus

Synopsis: Last reported status

Declaration: `Property LastStatus : TCurrentStatus`

Visibility: `public`

Access: `Read`

Description: `LastStatus` is the last status reported to the operating system.

See also: `ReportStatus (??)`

### 9.12.13 TDaemonController.CheckPoint

Synopsis: Send checkpoint signal to the operating system

Declaration: `Property CheckPoint : DWord`

Visibility: public

Access:

Description: `CheckPoint` can be used to send a checkpoint signal during lengthy operations, to signal that a lengthy operation is in progress. This should be used mainly on windows, to signal the service manager that the service is alive.

See also: `ReportStatus` (??)

## 9.13 TDaemonDef

### 9.13.1 Description

`TDaemonDef` contains the definition of a daemon in the application: The name of the daemon, which `TCustomDaemon` (184) descendent should be started to run the daemon, a description, and various other options should be set in this class. The global `TDaemonApplication` instance maintains a collection of `TDaemonDef` instances and will use these definitions to install or start the various daemons.

See also: `TDaemonApplication` (198), `TDaemon` (193)

### 9.13.2 Method overview

Page	Property	Description
<a href="#">201</a>	Create	Create a new <code>TDaemonDef</code> instance
<a href="#">202</a>	Destroy	Free a <code>TDaemonDef</code> from memory

### 9.13.3 Property overview

Page	Property	Access	Description
<a href="#">202</a>	<code>DaemonClass</code>	r	<code>TDaemon</code> class to use for this daemon
<a href="#">202</a>	<code>DaemonClassName</code>	rw	Name of the <code>TDaemon</code> class to use for this daemon
<a href="#">203</a>	<code>Description</code>	rw	Description of the daemon
<a href="#">203</a>	<code>DisplayName</code>	rw	Displayed name of the daemon (service)
<a href="#">204</a>	<code>Enabled</code>	rw	Is the daemon enabled or not
<a href="#">202</a>	<code>Instance</code>	rw	Instance of the daemon class
<a href="#">205</a>	<code>LogStatusReport</code>	rw	Log the status report to the system log
<a href="#">203</a>	<code>Name</code>	rw	Name of the daemon (service)
<a href="#">204</a>	<code>OnCreateInstance</code>	rw	Event called when a daemon is instantiated
<a href="#">204</a>	<code>Options</code>	rw	Service options
<a href="#">203</a>	<code>RunArguments</code>	rw	Additional command-line arguments when running daemon.
<a href="#">204</a>	<code>WinBindings</code>	rw	Windows-specific bindings (windows only)

### 9.13.4 TDaemonDef.Create

Synopsis: Create a new `TDaemonDef` instance

**Declaration:** `constructor Create(ACollection: TCollection); Override`

**Visibility:** `public`

**Description:** `Create` initializes a new `TDaemonDef` instance. It should not be necessary to instantiate a definition manually, it is handled by the collection.

**See also:** `TDaemonDefs` ([205](#))

### 9.13.5 TDaemonDef.Destroy

**Synopsis:** Free a `TDaemonDef` from memory

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` removes the `TDaemonDef` from memory.

### 9.13.6 TDaemonDef.DaemonClass

**Synopsis:** `TDaemon` class to use for this daemon

**Declaration:** `Property DaemonClass : TCustomDaemonClass`

**Visibility:** `public`

**Access:** `Read`

**Description:** `DaemonClass` is the `TDaemon` class that is used when this service is requested. It is looked up in the application's global daemon mapper by it's name in `DaemonClassName` ([??](#)).

**See also:** `DaemonClassName` ([??](#)), `TDaemonMapper` ([207](#))

### 9.13.7 TDaemonDef.Instance

**Synopsis:** Instance of the daemon class

**Declaration:** `Property Instance : TCustomDaemon`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Instance` points to the `TDaemon` ([193](#)) instance that is used when the service is in operation at runtime.

**See also:** `TDaemonDef.DaemonClass` ([??](#))

### 9.13.8 TDaemonDef.DaemonClassName

**Synopsis:** Name of the `TDaemon` class to use for this daemon

**Declaration:** `Property DaemonClassName : String`

**Visibility:** `published`

**Access:** `Read,Write`

**Description:** `DaemonClassName` is the name of the `TDaemon` class that will be used whenever the service is needed. The name is used to look up the class pointer registered in the daemon mapper, when `TCustomDaemonApplication.CreateDaemonInstance (??)` creates an instance of the daemon.

See also: `TDaemonDef.Instance (??)`, `TDaemonDef.DaemonClass (??)`, `RegisterDaemonClass` ([183](#))

### 9.13.9 TDaemonDef.Name

**Synopsis:** Name of the daemon (service)

**Declaration:** `Property Name : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `Name` is the internal name of the daemon as it is known to the operating system.

See also: `TDaemonDef.DisplayName (??)`

### 9.13.10 TDaemonDef.Description

**Synopsis:** Description of the daemon

**Declaration:** `Property Description : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `Description` is the description shown in the Windows service manager when managing this service. It is supplied to the windows service manager when the daemon is installed.

### 9.13.11 TDaemonDef.DisplayName

**Synopsis:** Displayed name of the daemon (service)

**Declaration:** `Property DisplayName : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `DisplayName` is the displayed name of the daemon as it is known to the operating system.

See also: `TDaemonDef.Name (??)`

### 9.13.12 TDaemonDef.RunArguments

**Synopsis:** Additional command-line arguments when running daemon.

**Declaration:** `Property RunArguments : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `RunArguments` specifies any additional command-line arguments that should be specified when running the daemon: these arguments will be passed to the service manager when registering the service on windows.

### 9.13.13 TDaemonDef.Options

Synopsis: Service options

Declaration: `Property Options : TDaemonOptions`

Visibility: published

Access: Read,Write

Description: `Options` tells the operating system which operations can be performed on the daemon while it is running.

This option is only used during the installation of the daemon.

### 9.13.14 TDaemonDef.Enabled

Synopsis: Is the daemon enabled or not

Declaration: `Property Enabled : Boolean`

Visibility: published

Access: Read,Write

Description: `Enabled` specifies whether a daemon should be installed, run or uninstalled. Disabled daemons are not installed, run or uninstalled.

### 9.13.15 TDaemonDef.WinBindings

Synopsis: Windows-specific bindings (windows only)

Declaration: `Property WinBindings : TWinBindings`

Visibility: published

Access: Read,Write

Description: `WinBindings` is used to group together the windows-specific properties of the daemon. This property is totally ignored on other platforms.

See also: `TWinBindings` ([212](#))

### 9.13.16 TDaemonDef.OnCreateInstance

Synopsis: Event called when a daemon is instantiated

Declaration: `Property OnCreateInstance : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnCreateInstance` is called whenever an instance of the daemon is created. This can be used for instance when a single `TDaemon` class is used to run several services, to correctly initialize the `TDaemon`.

### 9.13.17 TDaemonDef.LogStatusReport

Synopsis: Log the status report to the system log

Declaration: `Property LogStatusReport : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `LogStatusReport` can be set to `True` to send the status reports also to the system log. This can be used to track the progress of the daemon.

See also: `TDaemon.ReportStatus` (??)

## 9.14 TDaemonDefs

### 9.14.1 Description

`TDaemonDefs` is the class of the global list of daemon definitions. It contains an item for each daemon in the application.

Normally it is not necessary to create an instance of `TDaemonDefs` manually. The global `TCustomDaemonMapper` (191) instance will create a collection and maintain it.

See also: `TCustomDaemonMapper` (191), `TDaemonDef` (201)

### 9.14.2 Method overview

Page	Property	Description
<a href="#">205</a>	<code>Create</code>	Create a new instance of a <code>TDaemonDefs</code> collection.
<a href="#">206</a>	<code>DaemonDefByName</code>	Find and return instance of daemon definition with given name.
<a href="#">206</a>	<code>FindDaemonDef</code>	Find and return instance of daemon definition with given name.
<a href="#">206</a>	<code>IndexOfDaemonDef</code>	Return index of daemon definition

### 9.14.3 Property overview

Page	Property	Access	Description
<a href="#">206</a>	<code>Daemons</code>	<code>rw</code>	Indexed access to <code>TDaemonDef</code> instances

### 9.14.4 TDaemonDefs.Create

Synopsis: Create a new instance of a `TDaemonDefs` collection.

Declaration: `constructor Create(AOwner: TPersistent; AClass: TCollectionItemClass)`

Visibility: `public`

Description: `Create` creates a new instance of the `TDaemonDefs` collection. It keeps the `AOwner` parameter for future reference and calls the inherited constructor.

Normally it is not necessary to create an instance of `TDaemonDefs` manually. The global `TCustomDaemonMapper` (191) instance will create a collection and maintain it.

See also: `TDaemonDef` (201)

### 9.14.5 TDaemonDefs.IndexOfDaemonDef

Synopsis: Return index of daemon definition

Declaration: `function IndexOfDaemonDef(const DaemonName: String) : Integer`

Visibility: public

Description: `IndexOfDaemonDef` searches the collection for a `TDaemonDef` (201) instance with a name equal to `DaemonName`, and returns it's index. It returns -1 if no definition was found with this name. The search is case insensitive.

See also: `TDaemonDefs.FindDaemonDef` (??), `TDaemonDefs.DaemonDefByName` (??)

### 9.14.6 TDaemonDefs.FindDaemonDef

Synopsis: Find and return instance of daemon definition with given name.

Declaration: `function FindDaemonDef(const DaemonName: String) : TDaemonDef`

Visibility: public

Description: `FindDaemonDef` searches the list of daemon definitions and returns the `TDaemonDef` (201) instance whose name matches `DaemonName`. If no definition is found, `Nil` is returned.

See also: `TDaemonDefs.IndexOfDaemonDef` (??), `TDaemonDefs.DaemonDefByName` (??)

### 9.14.7 TDaemonDefs.DaemonDefByName

Synopsis: Find and return instance of daemon definition with given name.

Declaration: `function DaemonDefByName(const DaemonName: String) : TDaemonDef`

Visibility: public

Description: `FindDaemonDef` searches the list of daemon definitions and returns the `TDaemonDef` (201) instance whose name matches `DaemonName`. If no definition is found, an `EDaemon` (184) exception is raised.

The `FindDaemonDef` (??) call does not raise an error, but returns `Nil` instead.

Errors: If no definition is found, an `EDaemon` (184) exception is raised.

See also: `TDaemonDefs.IndexOfDaemonDef` (??), `TDaemonDefs.FindDaemonDef` (??)

### 9.14.8 TDaemonDefs.Daemons

Synopsis: Indexed access to `TDaemonDef` instances

Declaration: `Property Daemons[Index: Integer]: TDaemonDef; default`

Visibility: public

Access: Read,Write

Description: `Daemons` is the default property of `TDaemonDefs`, it gives access to the `TDaemonDef` instances in the collection.

See also: `TDaemonDef` (201)

## 9.15 TDaemonMapper

### 9.15.1 Description

`TDaemonMapper` is a direct descendent of `TCustomDaemonMapper` (191), but introduces no new functionality. Its sole purpose is to make it possible for an IDE to stream the `TDaemonMapper` instance.

For this purpose, it overrides the `Create` constructor and tries to find a resource with the same name as the class name, and tries to stream the instance from this resource.

If the instance should not be streamed, the `CreateNew (??)` constructor can be used instead.

See also: `CreateNew (??)`, `Create (??)`

### 9.15.2 Method overview

Page	Property	Description
<a href="#">207</a>	<code>Create</code>	Create a new <code>TDaemonMapper</code> instance and initializes it from streamed resources.
<a href="#">207</a>	<code>CreateNew</code>	Create a new <code>TDaemonMapper</code> instance without initialization

### 9.15.3 TDaemonMapper.Create

**Synopsis:** Create a new `TDaemonMapper` instance and initializes it from streamed resources.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** default

**Description:** `Create` initializes a new instance of `TDaemonMapper` and attempts to read the component from resources compiled in the application.

If the instance should not be streamed, the `CreateNew (??)` constructor can be used instead.

**Errors:** If no streaming system is found, or no resource exists for the class, an exception is raised.

See also: `CreateNew (??)`

### 9.15.4 TDaemonMapper.CreateNew

**Synopsis:** Create a new `TDaemonMapper` instance without initialization

**Declaration:** `constructor CreateNew(AOwner: TComponent; Dummy: Integer)`

**Visibility:** default

**Description:** `CreateNew` initializes a new instance of `TDaemonMapper`. In difference with the `Create` constructor, it does not attempt to read the component from a stream.

See also: `Create (??)`



## 9.16 TDaemonThread

### 9.16.1 Description

TDaemonThread is the thread in which the daemons in the application are run. Each daemon is run in it's own thread.

It should not be necessary to create these threads manually, the TDaemonController (198) class will take care of this.

See also: TDaemonController (198), TDaemon (193)

### 9.16.2 Method overview

Page	Property	Description
<a href="#">209</a>	CheckControlMessage	Check if a control message has arrived
<a href="#">209</a>	ContinueDaemon	Continue the daemon
<a href="#">208</a>	Create	Create a new thread
<a href="#">208</a>	Execute	Run the daemon
<a href="#">210</a>	InterrogateDaemon	Report the daemon status
<a href="#">209</a>	PauseDaemon	Pause the daemon
<a href="#">210</a>	ShutDownDaemon	Shut down daemon
<a href="#">209</a>	StopDaemon	Stops the daemon

### 9.16.3 Property overview

Page	Property	Access	Description
<a href="#">210</a>	Daemon	r	Daemon instance

### 9.16.4 TDaemonThread.Create

Synopsis: Create a new thread

Declaration: `constructor Create (ADaemon: TCustomDaemon)`

Visibility: public

Description: `Create` creates a new thread instance. It initializes the `Daemon` property with the passed `ADaemon`. The thread is created suspended.

See also: TDaemonThread.Daemon (??)

### 9.16.5 TDaemonThread.Execute

Synopsis: Run the daemon

Declaration: `procedure Execute; Override`

Visibility: public

Description: `Execute` starts executing the daemon and waits till the daemon stops. It also listens for control codes for the daemon.

See also: TDaemon.Execute (??)

### 9.16.6 TDaemonThread.CheckControlMessage

Synopsis: Check if a control message has arrived

Declaration: `procedure CheckControlMessage (WaitForMessage: Boolean)`

Visibility: `public`

Description: `CheckControlMessage` checks if a control message has arrived for the daemon and executes the appropriate daemon message. If the parameter `WaitForMessage` is `True`, then the routine waits for the message to arrive. If it is `False` and no message is present, it returns at once.

### 9.16.7 TDaemonThread.StopDaemon

Synopsis: Stops the daemon

Declaration: `function StopDaemon : Boolean; Virtual`

Visibility: `public`

Description: `StopDaemon` attempts to stop the daemon using its `TDaemon.Stop (??)` method, and terminates the thread.

See also: `TDaemon.Stop (??)`, `TDaemonThread.PauseDaemon (??)`, `TDaemonThread.ShutDownDaemon (??)`

### 9.16.8 TDaemonThread.PauseDaemon

Synopsis: Pause the daemon

Declaration: `function PauseDaemon : Boolean; Virtual`

Visibility: `public`

Description: `PauseDaemon` attempts to stop the daemon using its `TDaemon.Pause (??)` method, and suspends the thread. It returns `True` if the attempt was successful.

See also: `TDaemon.Pause (??)`, `TDaemonThread.StopDaemon (??)`, `TDaemonThread.ContinueDaemon (??)`, `TDaemonThread.ShutDownDaemon (??)`

### 9.16.9 TDaemonThread.ContinueDaemon

Synopsis: Continue the daemon

Declaration: `function ContinueDaemon : Boolean; Virtual`

Visibility: `public`

Description: `ContinueDaemon` attempts to stop the daemon using its `TDaemon.Continue (??)` method. It returns `True` if the attempt was successful.

See also: `TDaemon.Continue (??)`, `TDaemonThread.StopDaemon (??)`, `TDaemonThread.PauseDaemon (??)`, `TDaemonThread.ShutDownDaemon (??)`

### 9.16.10 TDaemonThread.ShutDownDaemon

Synopsis: Shut down daemon

Declaration: `function ShutDownDaemon : Boolean; Virtual`

Visibility: `public`

Description: `ShutDownDaemon` shuts down the daemon. This happens normally only when the system is shut down and the daemon didn't respond to the stop request. The return result is the result of the `TDaemon.Shutdown (??)` function. The thread is terminated by this method.

See also: `TDaemon.Shutdown (??)`, `TDaemonThread.StopDaemon (??)`, `TDaemonThread.PauseDaemon (??)`, `TDaemonThread.ContinueDaemon (??)`

### 9.16.11 TDaemonThread.InterrogateDaemon

Synopsis: Report the daemon status

Declaration: `function InterrogateDaemon : Boolean; Virtual`

Visibility: `public`

Description: `InterrogateDaemon` simply calls `TDaemon.ReportStatus (??)` for the daemon that is running in this thread. It always returns `True`.

See also: `TDaemon.ReportStatus (??)`

### 9.16.12 TDaemonThread.Daemon

Synopsis: Daemon instance

Declaration: `Property Daemon : TCustomDaemon`

Visibility: `public`

Access: `Read`

Description: `Daemon` is the daemon instance which is running in this thread.

See also: `TDaemon` ([193](#))

## 9.17 TDependencies

### 9.17.1 Description

`TDependencies` is just a descendent of `TCollection` which contains a series of dependencies on other services. It overrides the default property of `TCollection` to return `TDependency` ([211](#)) instances.

See also: `TDependency` ([211](#))

### 9.17.2 Method overview

Page	Property	Description
<a href="#">211</a>	Create	Create a new instance of a <code>TDependencies</code> collection.

### 9.17.3 Property overview

Page	Property	Access	Description
<a href="#">211</a>	Items	rw	Default property override

### 9.17.4 TDependencies.Create

Synopsis: Create a new instance of a `TDependencies` collection.

Declaration: constructor `Create(AOwner: TPersistent)`

Visibility: public

Description: `Create` Create a new instance of a `TDependencies` collection.

### 9.17.5 TDependencies.Items

Synopsis: Default property override

Declaration: Property `Items[Index: Integer]: TDependency; default`

Visibility: public

Access: Read,Write

Description: `Items` overrides the default property of `TCollection` so the items are of type `TDependency` ([211](#)).

See also: `TDependency` ([211](#))

## 9.18 TDependency

### 9.18.1 Description

`TDependency` is a collection item used to specify dependencies on other daemons (services) in windows. It is used only on windows and when installing the daemon: changing the dependencies of a running daemon has no effect.

See also: `TDependencies` ([210](#)), `TDaemonDef` ([201](#))

### 9.18.2 Method overview

Page	Property	Description
<a href="#">212</a>	Assign	Assign <code>TDependency</code> instance to another

### 9.18.3 Property overview

Page	Property	Access	Description
<a href="#">212</a>	IsGroup	rw	Name refers to a service group
<a href="#">212</a>	Name	rw	Name of the service

### 9.18.4 TDependency.Assign

Synopsis: Assign TDependency instance to another

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: Assign is overridden by TDependency to copy all properties from one instance to another.

### 9.18.5 TDependency.Name

Synopsis: Name of the service

Declaration: `Property Name : String`

Visibility: `published`

Access: `Read,Write`

Description: Name is the name of a service or service group that the current daemon depends on.

See also: `TDependency.IsGroup (??)`

### 9.18.6 TDependency.IsGroup

Synopsis: Name refers to a service group

Declaration: `Property IsGroup : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: IsGroup can be set to `True` to indicate that Name refers to the name of a service group.

See also: `TDependency.Name (??)`

## 9.19 TWinBindings

### 9.19.1 Description

TWinBindings contains windows-specific properties for the daemon definition (in `TDaemonDef.WinBindings (??)`). If the daemon should not run on Windows, then the properties can be ignored.

See also: `TDaemonDef (201)`, `TDaemonDef.WinBindings (??)`

### 9.19.2 Method overview

Page	Property	Description
<a href="#">213</a>	Assign	Copies all properties
<a href="#">213</a>	Create	Create a new TWinBindings instance
<a href="#">213</a>	Destroy	Remove a TWinBindings instance from memory

### 9.19.3 Property overview

Page	Property	Access	Description
<a href="#">214</a>	Dependencies	rw	Service dependencies
<a href="#">213</a>	ErrCode	rw	Service specific error code
<a href="#">216</a>	ErrorSeverity	rw	Error severity in case of startup failure
<a href="#">214</a>	GroupName	rw	Service group name
<a href="#">216</a>	IDTag	rw	Location in the service group
<a href="#">215</a>	Password	rw	Password for service startup
<a href="#">216</a>	ServiceType	rw	Type of service
<a href="#">215</a>	StartType	rw	Service startup type.
<a href="#">215</a>	UserName	rw	Username to run service as
<a href="#">215</a>	WaitHint	rw	Timeout wait hint
<a href="#">214</a>	Win32ErrCode	rw	General windows error code

### 9.19.4 TWinBindings.Create

Synopsis: Create a new TWinBindings instance

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes various properties such as the dependencies.

See also: `TDaemonDef` ([201](#)), `TDaemonDef.WinBindings` (??), `TWinBindings.Dependencies` (??)

### 9.19.5 TWinBindings.Destroy

Synopsis: Remove a TWinBindings instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the TWinBindings instance.

See also: `TWinBindings.Dependencies` (??), `TWinBindings.Create` (??)

### 9.19.6 TWinBindings.Assign

Synopsis: Copies all properties

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` is overridden by `TWinBindings` so all properties are copied from `Source` to the `TWinBindings` instance.

### 9.19.7 TWinBindings.ErrCode

Synopsis: Service specific error code

Declaration: `Property ErrCode : DWord`

Visibility: `public`

Access: Read,Write

Description: `ErrCode` contains a service specific error code that is reported with `TDaemon.ReportStatus (??)` to the windows service manager. If it is zero, then the contents of `Win32ErrCode (??)` are reported. If it is nonzero, then the windows-errorcode is set to `ERROR_SERVICE_SPECIFIC_ERROR`.

See also: `TWinBindings.Win32ErrCode (??)`

### 9.19.8 `TWinBindings.Win32ErrCode`

Synopsis: General windows error code

Declaration: `Property Win32ErrCode : DWord`

Visibility: public

Access: Read,Write

Description: `Win32ErrCode` is a general windows service error code that can be reported with `TDaemon.ReportStatus (??)` to the windows service manager. It is sent if `ErrCode (??)` is zero.

See also: `ErrCode (??)`

### 9.19.9 `TWinBindings.Dependencies`

Synopsis: Service dependencies

Declaration: `Property Dependencies : TDependencies`

Visibility: published

Access: Read,Write

Description: `Dependencies` contains the list of other services (or service groups) that this service depends on. Windows will first attempt to start these services prior to starting this service. If they cannot be started, then the service will not be started either.

This property is only used during installation of the service.

### 9.19.10 `TWinBindings.GroupName`

Synopsis: Service group name

Declaration: `Property GroupName : String`

Visibility: published

Access: Read,Write

Description: `GroupName` specifies the name of a service group that the service belongs to. If it is empty, then the service does not belong to any group.

This property is only used during installation of the service.

See also: `TDependency.IsGroup (??)`

### 9.19.11 **TWinBindings.Password**

Synopsis: Password for service startup

Declaration: `Property Password : String`

Visibility: published

Access: Read,Write

Description: `Password` contains the service password: if the service is started with credentials other than one of the system users, then the password for the user must be entered here.

This property is only used during installation of the service.

See also: `UserName` (??)

### 9.19.12 **TWinBindings.UserName**

Synopsis: Username to run service as

Declaration: `Property UserName : String`

Visibility: published

Access: Read,Write

Description: `UserName` specifies the name of a user whose credentials should be used to run the service. If it is left empty, the service is run as the system user. The password can be set in the `Password` (??) property.

This property is only used during installation of the service.

See also: `Password` (??)

### 9.19.13 **TWinBindings.StartType**

Synopsis: Service startup type.

Declaration: `Property StartType : TStartType`

Visibility: published

Access: Read,Write

Description: `StartType` specifies when the service should be started during system startup.

This property is only used during installation of the service.

### 9.19.14 **TWinBindings.WaitHint**

Synopsis: Timeout wait hint

Declaration: `Property WaitHint : Integer`

Visibility: published

Access: Read,Write

Description: `WaitHint` specifies the estimated time for a start/stop/pause or continue operation (in milliseconds). `ReportStatus` should be called prior to this time to report the next status.

See also: `TDaemon.ReportStatus` (??)



### 9.19.15 TWinBindings.IDTag

Synopsis: Location in the service group

Declaration: `Property IDTag : DWord`

Visibility: published

Access: Read,Write

Description: `IDTag` contains the location of the service in the service group after installation of the service. It should not be set, it is reported by the service manager.

This property is only used during installation of the service.

### 9.19.16 TWinBindings.ServiceType

Synopsis: Type of service

Declaration: `Property ServiceType : TServiceType`

Visibility: published

Access: Read,Write

Description: `ServiceType` specifies what kind of service is being installed.

This property is only used during installation of the service.

### 9.19.17 TWinBindings.ErrorSeverity

Synopsis: Error severity in case of startup failure

Declaration: `Property ErrorSeverity : TErrorSeverity`

Visibility: published

Access: Read,Write

Description: `ErrorSeverity` can be used at installation time to tell the windows service manager how to behave when the service fails to start during system startup.

This property is only used during installation of the service.

## Chapter 10

# Reference for unit 'db'

### 10.1 Used units

Table 10.1: Used units by unit 'db'

Name	Page
Classes	??
FmtBCD	??
MaskUtils	??
System	??
sysutils	??
Variants	??

### 10.2 Overview

The `db` unit provides the basis for all database access mechanisms. It introduces abstract classes, on which all database access mechanisms are based: `TDataset` (267) representing a set of records from a database, `TField` (315) which represents the contents of a field in a record, `TDataSource` (303) which acts as an event distributor on behalf of a dataset and `TParams` (388) which can be used to parametrize queries. The databases connections themselves are abstracted in the `TDatabase` (257) class.

### 10.3 Constants, types and variables

#### 10.3.1 Constants

```
DefaultFieldClasses : Array[TFieldType] of TFieldClass = (Tfield, TStringField, TSma
```

`DefaultFieldClasses` contains the `TField` (315) descendent class to use when a `TDataset` instance needs to create fields based on the `TFieldDefs` (343) field definitions when opening the dataset. The entries can be set to create customized `TField` descendents for certain field datatypes in all datasets.

```
dsEditModes = [dsEdit, dsInsert, dsSetKey]
```

`dsEditModes` contains the various values of `TDataset.State` (??) for which the dataset is in edit mode, i.e. states in which it is possible to set field values for that dataset.

```
dsMaxBufferCount = MAXINT div 8
```

Maximum data buffers count for dataset

```
dsMaxStringSize = 8192
```

Maximum size of string fields

```
dsWriteModes = [dsEdit, dsInsert, dsSetKey, dsCalcFields, dsFilter, dsNewValue, dsIn
```

`dsWriteModes` contains the various values of `TDataset.State` (??) for which data can be written to the dataset buffer.

```
Fieldtypenames : Array[TFieldType] of String = ('Unknown', 'String', 'Smallint', 'In
```

`FieldTypeNames` contains the names (in english) for the various field data types.

```
FieldTypetoVariantMap : Array[TFieldType] of Integer = (varError, varOleStr, varSma
```

`FieldTypetoVariantMap` contains for each field datatype the variant value type that corresponds to it. If a field type cannot be expressed by a variant type, then `varError` is stored in the variant value.

```
SQLDelimiterCharacters = [';', ' ', ' ', ' ', ' ', '(', ')', #13, #10, #9]
```

SQL statement delimiter token characters

```
YesNoChars : Array[Boolean] of Char = ('N', 'Y')
```

Array of characters mapping a boolean to Y/N

### 10.3.2 Types

```
LargeInt = Int64
```

Large (64-bit) integer

```
PBookmarkFlag = ^TBookmarkFlag
```

`PBookmarkFlag` is a convenience type, defined for internal use in `TDataset` (267) or one of its descendents.

```
PBufferList = ^TBufferList
```

`PBufferList` is a pointer to a structure of type `TBufferList` (220). It is an internal type, and should not be used in end-user code.

```
PDateTimeRec = ^TdateTimeRec
```

Pointer to TDateTimeRec record

PLargeInt = ^LargeInt

Pointer to Large (64-bit) integer

PLookupListRec = ^TLookupListRec

Pointer to TLookupListRec record

TBlobData = String

TBlobData should never be used directly in application code.

TBlobStreamMode = (bmRead, bmWrite, bmReadWrite)

Table 10.2: Enumeration values for type TBlobStreamMode

Value	Explanation
bmRead	Read blob data
bmReadWrite	Read and write blob data
bmWrite	Write blob data

TBlobStramMode is used when creating a stream for redaing BLOB data. It indicates what the data will be used for: reading, writing or both.

TBlobType = ftBlob..ftWideMemo

TBlobType is a subrange type, indicating the various datatypes of BLOB fields.

TBookmark = Pointer

TBookMark is the type used by the TDataset.SetBookMark (??) method. It is an opaque type, and should not be used any more, it is superseded by the TBookmarkStr (220) type.

TBookmarkFlag = (bfCurrent, bfBOF, bfEOF, bfInserted)

Table 10.3: Enumeration values for type TBookmarkFlag

Value	Explanation
bfBOF	First record in the dataset.
bfCurrent	Buffer used for the current record
bfEOF	Last record in the dataset
bfInserted	Buffer used for insert

TBookmarkFlag is used internally by TDataset (267) and it's descendent types to mark the internal memory buffers. It should not be used in end-user applications.

`TBookmarkStr = String`

`TBookmarkStr` is the type used by the `TDataset.Bookmark` (??) property. It can be used as a string, but should in fact be considered an opaque type.

`TBufferArray = ^pchar`

`TBufferArray` is an internally used type. It can change in future implementations, and should not be used in application code.

`TBufferList = Array[0..dsMaxBufferCount-1] of PChar`

`TBufferList` is used internally by the `TDataset` (267) class to manage the memory buffers for the data. It should not be necessary to use this type in end-user applications.

`TDataAction = (daFail, daAbort, daRetry)`

Table 10.4: Enumeration values for type `TDataAction`

Value	Explanation
<code>daAbort</code>	The operation should be aborted (edits are undone, and an <code>EAbort</code> exception is raised)
<code>daFail</code>	The operation should fail (an exception will be raised)
<code>daRetry</code>	Retry the operation.

`TDataAction` is used by the `TDataSetErrorEvent` (221) event handler prototype. The parameter `Action` of this event handler is of `TDataAction` type, and should indicate what action must be taken by the dataset.

`TDatabaseClass = Class of TDataBase`

`TDatabaseClass` is the class pointer for the `TDatabase` (257) class.

`TDataChangeEvent = procedure(Sender: TObject; Field: TField) of object`

`TDataChangeEvent` is the event handler prototype for the `TDatasource.OnDataChange` (??) event. The sender parameter is the `TDatasource` instance that triggered the event, and the `Field` parameter is the field whose data has changed. If the dataset has scrolled, then the `Field` parameter is `Nil`.

`TDataEvent = (deFieldChange, deRecordChange, deDataSetChange, deDataSetScroll, deLayoutChange, deUpdateRecord, deUpdateState, deCheckBrowseMode, dePropertyChange, deFieldListChange, deFocusControl, deParentScroll, deConnectChange, deReconcileError, deDisabledStateChange)`

Table 10.5: Enumeration values for type TDataEvent

Value	Explanation
deCheckBrowseMode	The browse mode is being checked
deConnectChange	Unused
deDataSetChange	The dataset property changed
deDataSetScroll	The dataset scrolled to another record
deDisabledStateChange	Unused
deFieldChange	A field value changed
deFieldListChange	Event sent when the list of fields of a dataset changes
deFocusControl	Event sent whenever a control connected to a field should be focused
deLayoutChange	The layout properties of one of the fields changed
deParentScroll	Unused
dePropertyChange	Unused
deReconcileError	Unused
deRecordChange	The current record changed
deUpdateRecord	The record is being updated
deUpdateState	The dataset state is updated

TDataEvent describes the various events that can be sent to TDataSource (303) instances connected to a TDataSet (267) instance.

TDataOperation = procedure of object

TDataOperation is a prototype handler used internally in TDataSet. It can be changed at any time, so it should not be used in end-user code.

TDatasetClass = Class of TDataSet

TDatasetClass is the class type for the TDataSet (267) class. It is currently unused in the DB unit and is defined for the benefit of other units.

```
TDatasetErrorEvent = procedure (DataSet: TDataSet; E: EDatabaseError;
                                var DataAction: TDataAction) of object
```

TDatasetErrorEvent is used by the TDataSet.OnEditError (??), TDataSet.OnPostError (??) and TDataSet.OnDeleteError (??) event handlers to allow the programmer to specify what should be done if an update operation fails with an exception: The DataSet parameter indicates what dataset triggered the event, the E parameter contains the exception object. The DataAction must be set by the event handler, and based on its return value, the dataset instance will take appropriate action. The default value is daFail, i.e. the exception will be raised again. For a list of available return values, see TDataAction (220).

```
TDataSetNotifyEvent = procedure (DataSet: TDataSet) of object
```

TDataSetNotifyEvent is used in most of the TDataSet (267) event handlers. It differs from the more general TNotifyEvent (defined in the Classes unit) in that the Sender parameter of the latter is replaced with the DataSet parameter. This avoids typecasts, the available TDataSet methods can be used directly.

```
TDataSetState = (dsInactive, dsBrowse, dsEdit, dsInsert, dsSetKey,
                 dsCalcFields, dsFilter, dsNewValue, dsOldValue, dsCurValue,
                 dsBlockRead, dsInternalCalc, dsOpening)
```

Table 10.6: Enumeration values for type TDataSetState

Value	Explanation
dsBlockRead	The dataset is open, but no events are transferred to datasources.
dsBrowse	The dataset is active, and the cursor can be used to navigate the data.
dsCalcFields	The dataset is calculating it's calculated fields.
dsCurValue	The dataset is showing the current values of a record.
dsEdit	The dataset is in editing mode: the current record can be modified.
dsFilter	The dataset is filtering records.
dsInactive	The dataset is not active. No data is available.
dsInsert	The dataset is in insert mode: the current record is a new record which can be edited.
dsInternalCalc	The dataset is calculating it's internally calculated fields.
dsNewValue	The dataset is showing the new values of a record.
dsOldValue	The dataset is showing the old values of a record.
dsOpening	The dataset is currently opening, but is not yet completely open.
dsSetKey	The dataset is calculating the primary key.

TDataSetState describes the current state of the dataset. During it's lifetime, the dataset's state is described by these enumerated values.

Some state are not used in the default TDataset implementation, and are only used by certain descendants.

```
TDateTimeAlias = TDateTime
```

TDateTimeAlias is no longer used.

```
TDateTimeRec = record
end
```

TDateTimeRec was used by older TDataset (267) implementations to store date/time values. Newer implementations use the TDateTime. This type should no longer be used.

```
TDBDatasetClass = Class of TDBDataset
```

TDBDatasetClass is the class pointer for TDBDataset (309)

```
TDBTransactionClass = Class of TDBTransaction
```

TDBTransactionClass is the class pointer for the TDBTransaction (310) class.

```
TFieldAttribute = (faHiddenCol, faReadonly, faRequired, faLink, faUnNamed,
faFixed)
```

Table 10.7: Enumeration values for type TFieldAttribute

Value	Explanation
faFixed	Fixed length field
faHiddenCol	Field is a hidden column (used to construct a unique key)
faLink	Field is a link field for other datasets
faReadOnly	Field is read-only
faRequired	Field is required
faUnNamed	Field has no original name

TFieldAttribute is used to denote some attributes of a field in a database. It is used in the Attributes (??) property of TFieldDef (339).

```
TFieldAttributes= Set of (faFixed, faHiddenCol, faLink, faReadOnly,
                           faRequired, faUnNamed)
```

TFieldAttributes is used in the TFieldDef.Attributes (??) property to denote additional attributes of the underlying field.

```
TFieldChars = Set of Char
```

TFieldChars is a type used in the TField.ValidChars (??) property. It's a simple set of characters.

```
TFieldClass = Class of TField
```

```
TFieldGetTextEvent = procedure(Sender: TField; var aText: String;
                               DisplayText: Boolean) of object
```

TFieldGetTextEvent is the prototype for the TField.OnGetText (??) event handler. It should be used when the text of a field requires special formatting. The event handler should return the contents of the field in formatted form in the AText parameter. The DisplayText is True if the text is used for displaying purposes or is False if it will be used for editing purposes.

```
TFieldKind = (fkData, fkCalculated, fkLookup, fkInternalCalc)
```

Table 10.8: Enumeration values for type TFieldKind

Value	Explanation
fkCalculated	The field is calculated on the fly.
fkData	Field represents actual data in the underlying data structure.
fkInternalCalc	Field is calculated but stored in an underlying buffer.
fkLookup	The field is a lookup field.

TFieldKind indicates the type of a TField instance. Besides TField instances that represent fields present in the underlying data records, there can also be calculated or lookup fields. To distinguish between these kind of fields, TFieldKind is introduced.

```
TFieldKinds= Set of (fkCalculated, fkData, fkInternalCalc, fkLookup)
```



TFieldKinds is a set of TFieldKind (223) values. It is used internally by the classes of the DB unit.

TFieldMap = Array[TFieldType] of Byte

TFieldMap is no longer used.

TFieldNotifyEvent = procedure(Sender: TField) of object

TFieldNotifyEvent is a prototype for the event handlers in the TField (315) class. Its Sender parameter is the field instance that triggered the event.

TFieldRef = ^TField

Pointer to a TField instance

TFieldSetTextEvent = procedure(Sender: TField; const aText: String)  
of object

TFieldSetTextEvent is the prototype for an event handler used to set the contents of a field based on a user-edited text. It should be used when the text of a field is entered with special formatting. The event handler should set the contents of the field based on the formatted text in the AText parameter.

TFieldType = (ftUnknown, ftString, ftSmallint, ftInteger, ftWord, ftBoolean,  
ftFloat, ftCurrency, ftBCD, ftDate, ftTime, ftDateTime, ftBytes,  
ftVarBytes, ftAutoInc, ftBlob, ftMemo, ftGraphic, ftFmtMemo,  
ftParadoxOle, ftDBaseOle, ftTypedBinary, ftCursor,  
ftFixedChar, ftWideString, ftLargeint, ftADT, ftArray,  
ftReference, ftDataSet, ftOraBlob, ftOraClob, ftVariant,  
ftInterface, ftIDispatch, ftGuid, ftTimeStamp, ftFMTBcd,  
ftFixedWideChar, ftWideMemo)

Table 10.9: Enumeration values for type TFieldType

Value	Explanation
ftADT	ADT value
ftArray	Array data
ftAutoInc	Auto-increment integer value (4 bytes)
ftBCD	Binary Coded Decimal value (DECIMAL and NUMERIC SQL types)
ftBlob	Binary data value (no type, no size)
ftBoolean	Boolean value
ftBytes	Array of bytes value, fixed size (untyped)
ftCurrency	Currency value (4 decimal points)
ftCursor	Cursor data value (no size)
ftDataSet	Dataset data (blob)
ftDate	Date value
ftDateTime	Date/Time (timestamp) value
ftDBaseOle	Paradox OLE field data
ftFixedChar	Fixed character array (string)
ftFixedWideChar	Fixed wide character data (2 bytes per character)
ftFloat	Floating point value (double)
ftFMTBcd	Formatted BCD (Binary Coded Decimal) value.
ftFmtMemo	Formatted memo ata value (no size)
ftGraphic	Graphical data value (no size)
ftGuid	GUID data value
ftIDispatch	Dispatch data value
ftInteger	Regular integer value (4 bytes, signed)
ftInterface	interface data value
ftLargeint	Large integer value (8-byte)
ftMemo	Binary text data (no size)
ftOraBlob	Oracle BLOB data
ftOraClob	Oracle CLOB data
ftParadoxOle	Paradox OLE field data (no size)
ftReference	Reference data
ftSmallint	Small integer value(1 byte, signed)
ftString	String data value (ansistring)
ftTime	Time value
ftTimeStamp	Timestamp data value
ftTypedBinary	Binary typed data (no size)
ftUnknown	Unknown data type
ftVarBytes	Array of bytes value, variable size (untyped)
ftVariant	Variant data value
ftWideMemo	Widestring memo data
ftWideString	Widestring (2 bytes per character)
ftWord	Word-sized value(2 bytes, unsigned)

TFieldType indicates the type of a TField (315) underlying data, in the DataType (??) property.

TFilterOption = (foCaseInsensitive, foNoPartialCompare)

Table 10.10: Enumeration values for type TFilterOption

Value	Explanation
foCaseInsensitive	Filter case insensitively.
foNoPartialCompare	Do not compare values partially, always compare completely.

TFilterOption enumerates the various options available when filtering a dataset. The TFilterOptions (226) set is used in the TDataset.FilterOptions (??) property to indicate which of the options should be used when filtering the data.

```
TFilterOptions= Set of (foCaseInsensitive,foNoPartialCompare)
```

TFilterOption is the set of filter options to use when filtering a dataset. This set type is used in the TDataset.FilterOptions (??) property. The available values are described in the TFilterOption (225) type.

```
TFilterRecordEvent = procedure (DataSet: TDataSet; var Accept: Boolean)
                        of object
```

TFilterRecordEvent is the prototype for the TDataset.OnFilterRecord (??) event handler. The DataSet parameter indicates which dataset triggered the event, and the Accept parameter must be set to true if the current record should be shown, False should be used when the record should be hidden.

```
TGetMode = (gmCurrent,gmNext,gmPrior)
```

Table 10.11: Enumeration values for type TGetMode

Value	Explanation
gmCurrent	Retrieve the current record
gmNext	Retrieve the next record.
gmPrior	Retrieve the previous record.

TGetMode is used internally by TDataset (267) when it needs to fetch more data for its buffers (using GetRecord). It tells the descendent dataset what operation must be performed.

```
TGetResult = (grOK,grBOF,grEOF,grError)
```

Table 10.12: Enumeration values for type TGetResult

Value	Explanation
grBOF	The beginning of the recordset is reached
grEOF	The end of the recordset is reached.
grError	An error occurred
grOK	The operation was completed succesfully

TGetResult is used by descendents of TDataset (267) when they have to communicate the result of the GetRecord operation back to the TDataset record.

```
TIndexOption = (ixPrimary, ixUnique, ixDescending, ixCaseInsensitive,
                ixExpression, ixNonMaintained)
```

Table 10.13: Enumeration values for type TIndexOption

Value	Explanation
ixCaseInsensitive	The values in the index are sorted case-insensitively
ixDescending	The values in the index are sorted descending.
ixExpression	The values in the index are based on a calculated expression.
ixNonMaintained	The index is non-maintained, i.e. changing the data will not update the index.
ixPrimary	The index is the primary index for the data
ixUnique	The index is a unique index, i.e. each index value can occur only once

TIndexOption describes the various properties that an index can have. It is used in the TIndexOptions (227) set type to describe all properties of an index definition as in TIndexDef (357).

```
TIndexOptions= Set of (ixCaseInsensitive, ixDescending, ixExpression,
                       ixNonMaintained, ixPrimary, ixUnique)
```

TIndexOptions contains the set of properties that an index can have. It is used in the TIndexDef.Options (??) property to describe all properties of an index definition as in TIndexDef (357).

```
TLocateOption = (loCaseInsensitive, loPartialKey)
```

Table 10.14: Enumeration values for type TLocateOption

Value	Explanation
loCaseInsensitive	Perform a case-insensitive search
loPartialKey	Accept partial key matches

TLocateOption is used in the TDataset.Locate (??) call to enumerate the possible options available when locating a record in the dataset.

```
TLocateOptions= Set of (loCaseInsensitive, loPartialKey)
```

TLocateOptions is used in the TDataset.Locate (??) call: It should contain the actual options to use when locating a record in the dataset.

```
TLoginEvent = procedure(Sender: TObject; Username: String;
                        Password: String) of object
```

TLoginEvent is the prototype for a the the TCustomConnection.OnLogin (??) event handler. It gets passed the TCustomConnection instance that is trying to login, and the initial username and password.

```
TLookupListRec = record
    Key : Variant;
    Value : Variant;
end
```

`TLookupListRec` is used by lookup fields to store lookup results, if the results should be cached. Its two fields keep the key value and associated lookup value.

`TParamBinding` = Array of Integer

`TParamBinding` is an auxiliary type used when parsing and binding parameters in SQL statements. It should never be used directly in application code.

`TParamStyle` = (psInterbase, psPostgreSQL, psSimulated)

Table 10.15: Enumeration values for type `TParamStyle`

Value	Explanation
psInterbase	Parameters are specified by a ? character
psPostgreSQL	Parameters are specified by a \$N character.
psSimulated	Parameters are specified by a \$N character.

`TParamStyle` denotes the style in which parameters are specified in a query. It is used in the `TParams.ParseSQL` (??) method, and can have the following values:

**psInterbase** Parameters are specified by a ? character

**psPostgreSQL** Parameters are specified by a \$N character.

**psSimulated** Parameters are specified by a \$N character.

`TParamType` = (ptUnknown, ptInput, ptOutput, ptInputOutput, ptResult)

Table 10.16: Enumeration values for type `TParamType`

Value	Explanation
ptInput	Input parameter
ptInputOutput	Input/output parameter
ptOutput	Output parameter, filled on result
ptResult	Result parameter
ptUnknown	Unknown type

`TParamType` indicates the kind of parameter represented by a `TParam` (376) instance. it has one of the following values:

**ptUnknown** Unknown type

**ptInput** Input parameter

**ptOutput** Output parameter, filled on result

**ptInputOutput** Input/output parameter

**ptResult** Result parameter

TParamTypes= Set of (ptInput,ptInputOutput,ptOutput,ptResult,ptUnknown)

TParamTypes is defined for completeness: a set of TParamType (228) values.

TProviderFlag = (pfInUpdate,pfInWhere,pfInKey,pfHidden)

Table 10.17: Enumeration values for type TProviderFlag

Value	Explanation
pfHidden	
pfInKey	Field is a key field and used in the WHERE clause of an update statement
pfInUpdate	Changes to the field should be propagated to the database.
pfInWhere	Field should be used in the WHERE clause of an update statement in case of upWhereChanged.

TProviderFlag describes how the field should be used when applying updates from a dataset to the database. Each field of a TDataset (267) has one or more of these flags.

TProviderFlags= Set of (pfHidden,pfInKey,pfInUpdate,pfInWhere)

TProviderFlags is used for the TField.ProviderFlags (??) property to describe the role of the field when applying updates to a database.

TPSCommandType = (ctUnknown,ctQuery,ctTable,ctStoredProc,ctSelect,ctInsert,ctUpdate,ctDelete,ctDDL)

Table 10.18: Enumeration values for type TPSCommandType

Value	Explanation
ctDDL	
ctDelete	
ctInsert	
ctQuery	
ctSelect	
ctStoredProc	
ctTable	
ctUnknown	
ctUpdate	

TResolverResponse = (rrSkip,rrAbort,rrMerge,rrApply,rrIgnore)

Table 10.19: Enumeration values for type TResolverResponse

Value	Explanation
rrAbort	Abor the whole update process
rrApply	Replace the update with new values applied by the event handler
rrIgnore	Ignore the error and remove update from change log
rrMerge	Merge the update with existing changes on the server
rrSkip	Skip the current update, leave it in the change log

TResolverResponse is used to indicate what should happen to a pending change that could not be resolved. It is used in callbacks.

TResyncMode= Set of (rmExact,rmCenter)

TResyncMode is used internally by various TDataset (267) navigation and data manipulation methods such as the TDataset.Refresh(??) method when they need to reset the cursor position in the dataset's buffer.

TStringFieldBuffer = Array[0..dsMaxStringSize] of Char

Type to access string field content buffers as an array of characters

TUpdateAction = (uaFail,uaAbort,uaSkip,uaRetry,uaApplied)

Table 10.20: Enumeration values for type TUpdateAction

Value	Explanation
uaAbort	The whole update operation should abort
uaApplied	Consider the update as applied
uaFail	Update operation should fail
uaRetry	Retry the update operation
uaSkip	The update of the current record should be skipped. (but not discarded)

TUpdateAction indicates what action must be taken in case the applying of updates on the underlying database fails. This type is not used in the TDataset (267) class, but is defined on behalf of TDataset descendents that implement caching of updates: It indicates what should be done when the (delayed) applying of the updates fails. This event occurs long after the actual post or delete operation.

TUpdateKind = (ukModify,ukInsert,ukDelete)

Table 10.21: Enumeration values for type TUpdateKind

Value	Explanation
ukDelete	Delete a record in the database.
ukInsert	insert a new record in the database.
ukModify	Modify an existing record in the database.

TUpdateKind indicates what kind of update operation is in progress when applying updates.

TUpdateMode = (upWhereAll,upWhereChanged,upWhereKeyOnly)

Table 10.22: Enumeration values for type TUpdateMode

Value	Explanation
upWhereAll	Use all old field values
upWhereChanged	Use only old field values of modified fields
upWhereKeyOnly	Only use key fields in the where clause.

`TUpdateMode` determines how the `WHERE` clause of update queries for SQL databases should be constructed.

`TUpdateStatus = (usUnmodified, usModified, usInserted, usDeleted)`

Table 10.23: Enumeration values for type `TUpdateStatus`

Value	Explanation
<code>usDeleted</code>	Record exists in the database, but is locally deleted.
<code>usInserted</code>	Record does not yet exist in the database, but is locally inserted
<code>usModified</code>	Record exists in the database but is locally modified
<code>usUnmodified</code>	Record is unmodified

`TUpdateStatus` determines the current state of the record buffer, if updates have not yet been applied to the database.

`TUpdateStatusSet = Set of (usDeleted, usInserted, usModified, usUnmodified)`

`TUpdateStatusSet` is a set of `TUpdateStatus` (231) values.

## 10.4 Procedures and functions

### 10.4.1 BuffersEqual

**Synopsis:** Check whether 2 memory buffers are equal

**Declaration:** `function BuffersEqual (Buf1: Pointer; Buf2: Pointer; Size: Integer)  
: Boolean`

**Visibility:** default

**Description:** `BuffersEqual` compares the memory areas pointed to by the `Buf1` and `Buf2` pointers and returns `True` if the contents are equal. The memory areas are compared for the first `Size` bytes. If all bytes in the indicated areas are equal, then `True` is returned, otherwise `False` is returned.

**Errors:** If `Buf1` or `Buf2` do not point to a valid memory area or `Size` is too large, then an exception may occur

**See also:** `#rtl.sysutils.Comparemem` (??)

### 10.4.2 DatabaseError

**Synopsis:** Raise an `EDatabaseError` exception.

**Declaration:** `procedure DatabaseError (const Msg: String); Overload  
procedure DatabaseError (const Msg: String; Comp: TComponent); Overload`

**Visibility:** default

**Description:** `DatabaseError` raises an `EDatabaseError` (233) exception, passing it `Msg`. If `Comp` is specified, the name of the component is prepended to the message.

**See also:** `DatabaseErrorFmt` (232), `EDatabaseError` (233)



### 10.4.3 DatabaseErrorFmt

**Synopsis:** Raise an `EDatabaseError` exception with a formatted message

**Declaration:** `procedure DatabaseErrorFmt(const Fmt: String; Args: Array of const)  
; Overload  
procedure DatabaseErrorFmt(const Fmt: String; Args: Array of const;  
Comp: TComponent); Overload`

**Visibility:** default

**Description:** `DatabaseErrorFmt` raises an `EDatabaseError` (233) exception, passing it a message made by calling `#rtl.sysutils.format` (??) with the `fmt` and `Args` arguments. If `Comp` is specified, the name of the component is prepended to the message.

See also: `DatabaseError` (231), `EDatabaseError` (233)

### 10.4.4 DateTimeRecToDateTime

**Synopsis:** Convert `TDateTimeRec` record to a `TDateTime` value.

**Declaration:** `function DateTimeRecToDateTime(DT: TFieldType; Data: TDateTimeRec)  
: TDateTime`

**Visibility:** default

**Description:** `DateTimeRecToDateTime` examines `Data` and `Dt` and uses `dt` to convert the timestamp in `Data` to a `TDateTime` value.

See also: `TFieldType` (224), `TDateTimeRec` (222), `DateTimeToDateTimeRec` (232)

### 10.4.5 DateTimeToDateTimeRec

**Synopsis:** Convert `TDateTime` value to a `TDateTimeRec` record.

**Declaration:** `function DateTimeToDateTimeRec(DT: TFieldType; Data: TDateTime)  
: TDateTimeRec`

**Visibility:** default

**Description:** `DateTimeToDateTimeRec` examines `Data` and `Dt` and uses `dt` to convert the date/time value in `Data` to a `TDateTimeRec` record.

See also: `TFieldType` (224), `TDateTimeRec` (222), `DateTimeRecToDateTime` (232)

### 10.4.6 DisposeMem

**Synopsis:** Dispose of a heap memory block and `Nil` the pointer (deprecated)

**Declaration:** `procedure DisposeMem(var Buffer; Size: Integer)`

**Visibility:** default

**Description:** `DisposeMem` disposes of the heap memory area pointed to by `Buffer` (`Buffer` must be of type `Pointer`). The `Size` parameter indicates the size of the memory area (it is, in fact, ignored by the heap manager). The pointer `Buffer` is set to `Nil`. If `Buffer` is `Nil`, then nothing happens. Do not use `DisposeMem` on objects, because their destructor will not be called.

**Errors:** If `Buffer` is not pointing to a valid heap memory block, then memory corruption may occur.

See also: `#rtl.system.FreeMem` (??), `#rtl.sysutils.freeandnil` (??)

### 10.4.7 ExtractFieldName

Synopsis: Extract the field name at position

Declaration: `function ExtractFieldName(const Fields: String; var Pos: Integer)  
: String`

Visibility: default

Description: `ExtractFieldName` returns the string starting at position `Pos` till the next semicolon (;) character or the end of the string. On return, `Pos` contains the position of the first character after the semicolon character (or one more than the length of the string).

See also: `TFields.GetFieldList` (??)

### 10.4.8 SkipComments

Synopsis: Skip SQL comments

Declaration: `function SkipComments(var p: PChar; EscapeSlash: Boolean;  
EscapeRepeat: Boolean) : Boolean`

Visibility: default

Description: `SkipComments` examines the null-terminated string in `P` and skips any SQL comment or string literal found at the start. It returns `P` the first non-comment or non-string literal position. The `EscapeSlash` parameter determines whether the backslash character (\) functions as an escape character (i.e. the following character is not considered a delimiter). `EscapeRepeat` must be set to `True` if the quote character is repeated to indicate itself.

The function returns `True` if a comment was found and skipped, `False` otherwise.

Errors: No checks are done on the validity of `P`.

See also: `TParams.ParseSQL` (??)

## 10.5 EDatabaseError

### 10.5.1 Description

`EDatabaseError` is the base class from which database-related exception classes should derive. It is raised by the `DatabaseError` (231) call.

See also: `DatabaseError` (231), `DatabaseErrorFmt` (232)

## 10.6 EUpdateError

### 10.6.1 Description

`EupdateError` is an exception used by the `TProvider` database support. It should never be raised directly.

See also: `EDatabaseError` (233)

### 10.6.2 Method overview

Page	Property	Description
<a href="#">234</a>	Create	Create a new EUpdateError instance
<a href="#">234</a>	Destroy	Free the EupdateError instance

### 10.6.3 Property overview

Page	Property	Access	Description
<a href="#">234</a>	Context	r	Context in which exception occurred.
<a href="#">235</a>	ErrorCode	r	Numerical error code.
<a href="#">235</a>	OriginalException	r	Original exception object, if available.
<a href="#">235</a>	PreviousError	r	Previous error number

### 10.6.4 EUpdateError.Create

Synopsis: Create a new EUpdateError instance

Declaration: `constructor Create (NativeError: String; Context: String; ErrCode: Integer; PrevError: Integer; E: Exception)`

Visibility: public

Description: `Create` instantiates a new `EUpdateError` object and populates the various properties with the `NativeError`, `Context`, `ErrCode` and `PrevError` parameters. The `E` parameter is the actual exception that occurred while the update operation was attempted. The exception object `E` will be freed if the `EUpdateError` instance is freed.

See also: `EDatabaseError` ([233](#))

### 10.6.5 EUpdateError.Destroy

Synopsis: Free the EupdateError instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` frees the original exception object (if there was one) and then calls the inherited destructor.

Errors: If the original exception object was already freed, an error will occur.

See also: `EUpdateError.OriginalException` (??)

### 10.6.6 EUpdateError.Context

Synopsis: Context in which exception occurred.

Declaration: `Property Context : String`

Visibility: public

Access: Read

Description: A description of the context in which the original exception was raised.

See also: `EUpdateError.OriginalException` (??), `EUpdateError.ErrorCode` (??), `EUpdateError.PreviousError` (??)

### 10.6.7 EUpdateError.ErrorCode

Synopsis: Numerical error code.

Declaration: `Property ErrorCode : Integer`

Visibility: `public`

Access: `Read`

Description: `ErrorCode` is a numerical error code, provided by the native data access layer, to describe the error. It may or not be filled.

See also: `EUpdateError.OriginalException (??)`, `EUpdateError.Context (??)`, `EUpdateError.PreviousError (??)`

### 10.6.8 EUpdateError.OriginalException

Synopsis: Original exception object, if available.

Declaration: `Property OriginalException : Exception`

Visibility: `public`

Access: `Read`

Description: `OriginalException` is the original exception object as raised by the database access layer. It may or may not be available.

See also: `EUpdateError.ErrorCode (??)`, `EUpdateError.Context (??)`, `EUpdateError.PreviousError (??)`

### 10.6.9 EUpdateError.PreviousError

Synopsis: Previous error number

Declaration: `Property PreviousError : Integer`

Visibility: `public`

Access: `Read`

Description: `PreviousError` is used to order the errors which occurred during an update operation.

See also: `EUpdateError.ErrorCode (??)`, `EUpdateError.Context (??)`, `EUpdateError.OriginalException (??)`

## 10.7 IProviderSupport

### 10.7.1 Method overview

Page	Property	Description
<a href="#">236</a>	PSEndTransaction	
<a href="#">236</a>	PSExecute	
<a href="#">236</a>	PSExecuteStatement	
<a href="#">236</a>	PSGetAttributes	
<a href="#">237</a>	PSGetCommandText	
<a href="#">237</a>	PSGetCommandType	
<a href="#">237</a>	PSGetDefaultOrder	
<a href="#">237</a>	PSGetIndexDefs	
<a href="#">237</a>	PSGetKeyFields	
<a href="#">237</a>	PSGetParams	
<a href="#">237</a>	PSGetQuoteChar	
<a href="#">237</a>	PSGetTableName	
<a href="#">237</a>	PSGetUpdateException	
<a href="#">238</a>	PSInTransaction	
<a href="#">238</a>	PSIsSQLBased	
<a href="#">238</a>	PSIsSQLSupported	
<a href="#">238</a>	PSReset	
<a href="#">238</a>	PSSetCommandText	
<a href="#">238</a>	PSSetParams	
<a href="#">238</a>	PSStartTransaction	
<a href="#">238</a>	PSUpdateRecord	

### 10.7.2 IProviderSupport.PSEndTransaction

Declaration: `procedure PSEndTransaction(ACommit: Boolean)`

Visibility: default

### 10.7.3 IProviderSupport.PSExecute

Declaration: `procedure PSExecute`

Visibility: default

### 10.7.4 IProviderSupport.PSExecuteStatement

Declaration: `function PSExecuteStatement(const ASQL: String; AParams: TParams;  
ResultSet: Pointer) : Integer`

Visibility: default

### 10.7.5 IProviderSupport.PSGetAttributes

Declaration: `procedure PSGetAttributes(List: TList)`

Visibility: default

### 10.7.6 IProviderSupport.PSGetCommandText

Declaration: `function PSGetCommandText : String`

Visibility: default

### 10.7.7 IProviderSupport.PSGetCommandType

Declaration: `function PSGetCommandType : TPSCommandType`

Visibility: default

### 10.7.8 IProviderSupport.PSGetDefaultOrder

Declaration: `function PSGetDefaultOrder : TIndexDef`

Visibility: default

### 10.7.9 IProviderSupport.PSGetIndexDefs

Declaration: `function PSGetIndexDefs(IndexTypes: TIndexOptions) : TIndexDefs`

Visibility: default

### 10.7.10 IProviderSupport.PSGetKeyFields

Declaration: `function PSGetKeyFields : String`

Visibility: default

### 10.7.11 IProviderSupport.PSGetParams

Declaration: `function PSGetParams : TParams`

Visibility: default

### 10.7.12 IProviderSupport.PSGetQuoteChar

Declaration: `function PSGetQuoteChar : String`

Visibility: default

### 10.7.13 IProviderSupport.PSGetTableName

Declaration: `function PSGetTableName : String`

Visibility: default

### 10.7.14 IProviderSupport.PSGetUpdateException

Declaration: `function PSGetUpdateException(E: Exception;Prev: EUpdateError)  
: EUpdateError`

Visibility: default

### **10.7.15 IProviderSupport.PSInTransaction**

Declaration: `function PSInTransaction : Boolean`

Visibility: default

### **10.7.16 IProviderSupport.PSIsSQLBased**

Declaration: `function PSIsSQLBased : Boolean`

Visibility: default

### **10.7.17 IProviderSupport.PSIsSQLSupported**

Declaration: `function PSIsSQLSupported : Boolean`

Visibility: default

### **10.7.18 IProviderSupport.PSReset**

Declaration: `procedure PSReset`

Visibility: default

### **10.7.19 IProviderSupport.PSSetCommandText**

Declaration: `procedure PSSetCommandText (const CommandText: String)`

Visibility: default

### **10.7.20 IProviderSupport.PSSetParams**

Declaration: `procedure PSSetParams (AParams: TParams)`

Visibility: default

### **10.7.21 IProviderSupport.PSStartTransaction**

Declaration: `procedure PSStartTransaction`

Visibility: default

### **10.7.22 IProviderSupport.PSUpdateRecord**

Declaration: `function PSUpdateRecord (UpdateKind: TUpdateKind; Delta: TDataSet)  
: Boolean`

Visibility: default

## 10.8 TAutoIncField

### 10.8.1 Description

`TAutoIncField` is the class created when a dataset must manage 32-bit signed integer data, of datatype `ftAutoInc`: This field gets it's data automatically by the database engine. It exposes no new properties, but simply overrides some methods to manage 32-bit signed integer data.

It should never be necessary to create an instance of `TAutoIncField` manually, a field of this class will be instantiated automatically for each auto-incremental field when a dataset is opened.

See also: `TField` (315)

### 10.8.2 Method overview

Page	Property	Description
<a href="#">239</a>	Create	Create a new instance of the <code>TAutoIncField</code> class.

### 10.8.3 TAutoIncField.Create

Synopsis: Create a new instance of the `TAutoIncField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TAutoIncField` class. It simply calls the inherited constructor and then sets up some of the `TField` (315) class' fields.

See also: `TField` (315)

## 10.9 TBCDField

### 10.9.1 Description

`TBCDField` is the class used when a dataset must manage data of Binary Coded Decimal type. (`TField.DataType` (??) equals `ftBCD`). It initializes some of the properties of the `TField` (315) class, and overrides some of its methods to be able to work with BCD fields.

`TBCDField` assumes that the field's contents can be stored in a currency type, i.e. the maximum number of decimals after the decimal separator that can be stored in a `TBCDField` is 4. Fields that need to store a larger amount of decimals should be represented by a `TFMTBCDField` (354) instance.

It should never be necessary to create an instance of `TBCDField` manually, a field of this class will be instantiated automatically for each BCD field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TFMTBCDField` (354)

### 10.9.2 Method overview

Page	Property	Description
<a href="#">240</a>	CheckRange	Check whether a values falls within the allowed range
<a href="#">240</a>	CheckTypeSize	
<a href="#">240</a>	Create	Create a new instance of a <code>TBCDField</code> class.



### 10.9.3 Property overview

Page	Property	Access	Description
<a href="#">241</a>	Currency	rw	Does the field represent a currency amount
<a href="#">241</a>	MaxValue	rw	Maximum value for the field
<a href="#">242</a>	MinValue	rw	Minimum value for the field
<a href="#">241</a>	Precision	rw	Precision of the BCD field
<a href="#">242</a>	Size		Number of decimals after the decimal separator
<a href="#">240</a>	Value	rw	Value of the field contents as a Currency type

### 10.9.4 TBCDField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(AValue: LongInt); Override`

Visibility: default

### 10.9.5 TBCDField.Create

Synopsis: Create a new instance of a TBCDField class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of the TBCDField class. It calls the inherited destructor, and then sets some TField ([315](#)) properties to configure the instance for working with BCD data values.

See also: TField ([315](#))

### 10.9.6 TBCDField.CheckRange

Synopsis: Check whether a values falls within the allowed range

Declaration: `function CheckRange(AValue: Currency) : Boolean`

Visibility: public

Description: `CheckRange` returns `True` if `AValue` lies within the range defined by the `MinValue` (??) and `MaxValue` (??) properties. If the value lies outside of the allowed range, then `False` is returned.

See also: `MaxValue` (??), `MinValue` (??)

### 10.9.7 TBCDField.Value

Synopsis: Value of the field contents as a Currency type

Declaration: `Property Value : Currency`

Visibility: public

Access: Read,Write

Description: `Value` is overridden from the TField.Value (??) property to a currency type field. It returns the same value as the TField.AsCurrency (??) field.

See also: TField.Value (??), TField.AsCurrency (??)

### 10.9.8 TBCDField.Precision

Synopsis: Precision of the BCD field

Declaration: `Property Precision : LongInt`

Visibility: published

Access: Read,Write

Description: `Precision` is the total number of decimals in the BCD value. It is not the same as `TBCDField.Size` (??), which is the number of decimals after the decimal point. The `Precision` property should be set by the descendent classes when they initialize the field, and should be considered read-only. Changing the value will influence the values returned by the various `AsXXX` properties.

See also: `TBCDField.Size` (??), `TBCDField.Value` (??)

### 10.9.9 TBCDField.Currency

Synopsis: Does the field represent a currency amount

Declaration: `Property Currency : Boolean`

Visibility: published

Access: Read,Write

Description: `Currency` can be set to `True` to indicate that the field contains data representing an amount of currency. This affects the way the `TField.DisplayText` (??) and `TField.Text` (??) properties format the value of the field: if the `Currency` property is `True`, then these properties will format the value as a currency value (generally appending the currency sign) and if the `Currency` property is `False`, then they will format it as a normal floating-point value.

See also: `TField.DisplayText` (??), `TField.Text` (??)

### 10.9.10 TBCDField.MaxValue

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : Currency`

Visibility: published

Access: Read,Write

Description: `MaxValue` can be set to a value different from zero, it is then the maximum value for the field if set to any value different from zero. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals 0, i.e. any floating-point value is allowed.

If `MaxValue` is set, `MinValue` (??) should also be set, because it will also be checked.

See also: `TBCDField.MinValue` (??), `TBCDField.CheckRange` (??)

### 10.9.11 TBCDField.MinValue

Synopsis: Minimum value for the field

Declaration: Property MinValue : Currency

Visibility: published

Access: Read,Write

Description: MinValue can be set to a value different from zero, then it is the minimum value for the field.

When setting the field's value, the value may not be less than MinValue. Any attempt to write a smaller value as the field's content will result in an exception. By default MinValue equals 0, i.e. any floating-point value is allowed.

If MinValue is set, TBCDField.MaxValue (??) should also be set, because it will also be checked.

See also: TBCDField.MaxValue (??), TBCDField.CheckRange (??)

### 10.9.12 TBCDField.Size

Synopsis: Number of decimals after the decimal separator

Declaration: Property Size :

Visibility: published

Access:

Description: Size is the number of decimals after the decimal separator. It is not the total number of decimals, which is stored in the TBCDField.Precision (??) field.

See also: TBCDField.Precision (??)

## 10.10 TBinaryField

### 10.10.1 Description

TBinaryField is an abstract class, designed to handle binary data of variable size. It overrides some of the properties and methods of the TField (315) class to be able to work with binary field data, such as retrieving the contents as a string or as a variant.

One must never create an instance of TBinaryField manually, it is an abstract class. Instead, a descendent class such as TBytesField (249) or TVarBytesField (397) should be created.

See also: TDataset (267), TField (315), TBytesField (249), TVarBytesField (397)

### 10.10.2 Method overview

Page	Property	Description
<a href="#">243</a>	CheckTypeSize	
<a href="#">243</a>	Create	Create a new instance of a TBinaryField class.

### 10.10.3 Property overview

Page	Property	Access	Description
<a href="#">243</a>	Size		Size of the binary data

### 10.10.4 TBinaryField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(AValue: LongInt); Override`

Visibility: default

### 10.10.5 TBinaryField.Create

Synopsis: Create a new instance of a TBinaryField class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of the TBinaryField class. It simply calls the inherited destructor.

See also: TField (315)

### 10.10.6 TBinaryField.Size

Synopsis: Size of the binary data

Declaration: `Property Size :`

Visibility: published

Access:

Description: `Size` is simply redeclared published with a default value of 16.

See also: TField.Size (??)

## 10.11 TBlobField

### 10.11.1 Description

TBlobField is the class used when a dataset must manage BLOB data. (TField.DataType (??) equals `ftBLOB`). It initializes some of the properties of the TField (315) class, and overrides some of its methods to be able to work with BLOB fields. It also serves as parent class for some specialized blob-like field types such as TMemoField (372), TWideMemoField (398) or TGraphicField (356)

It should never be necessary to create an instance of TBlobField manually, a field of this class will be instantiated automatically for each BLOB field when a dataset is opened.

See also: TDataSet (267), TField (315), TMemoField (372), TWideMemoField (398), TGraphicField (356)

### 10.11.2 Method overview

Page	Property	Description
<a href="#">244</a>	Clear	Clear the BLOB field's contents
<a href="#">244</a>	Create	Create a new instance of a TBlobField class.
<a href="#">244</a>	IsBlob	Is the field a blob field
<a href="#">244</a>	LoadFromFile	Load the contents of the field from a file
<a href="#">245</a>	LoadFromStream	Load the field's contents from stream
<a href="#">245</a>	SaveToFile	Save field contents to a file
<a href="#">245</a>	SaveToStream	Save the field's contents to stream
<a href="#">246</a>	SetFieldType	Set field type

### 10.11.3 Property overview

Page	Property	Access	Description
<a href="#">246</a>	BlobSize	r	Size of the current blob
<a href="#">247</a>	BlobType	rw	Type of blob
<a href="#">246</a>	Modified	rw	Has the field's contents been modified.
<a href="#">247</a>	Size		Size of the blob field
<a href="#">247</a>	Transliterate	rw	Should the contents of the field be transliterated
<a href="#">246</a>	Value	rw	Return the field's contents as a string

### 10.11.4 TBlobField.Create

Synopsis: Create a new instance of a TBlobField class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the TBlobField class. It calls the inherited destructor, and then sets some TField (315) properties to configure the instance for working with BLOB data.

See also: TField (315)

### 10.11.5 TBlobField.Clear

Synopsis: Clear the BLOB field's contents

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: `Clear` overrides the TField implementation of TField.Clear (??). It creates and immediately releases an empty blob stream in write mode, effectively clearing the contents of the BLOB field.

See also: TField.Clear (??), TField.IsNull (??)

### 10.11.6 TBlobField.IsBlob

Synopsis: Is the field a blob field

Declaration: `class function IsBlob; Override`

Visibility: `default`

Description: `IsBlob` is overridden by TBlobField to return `True`

See also: TField.IsBlob (??)

### 10.11.7 TBlobField.LoadFromFile

Synopsis: Load the contents of the field from a file

Declaration: `procedure LoadFromFile(const FileName: String)`

Visibility: `public`

**Description:** `LoadFromFile` creates a file stream with `FileName` as the name of the file to open, en then calls `LoadFromStream (??)` to read the contents of the blob field from the file. The file is opened in read-only mode.

**Errors:** If the file does not exist or is nor available for reading, an exception will be raised.

**See also:** `LoadFromStream (??)`, `SaveToFile (??)`

### 10.11.8 TBlobField.LoadFromStream

**Synopsis:** Load the field's contents from stream

**Declaration:** `procedure LoadFromStream(Stream: TStream)`

**Visibility:** public

**Description:** `LoadFromStream` can be used to load the contents of the field from a `TStream (??)` descendent. The entire data of the stream will be copied, and the stream will be positioned on the first byte of data, so it must be seekable.

**Errors:** If the stream is not seekable, an exception will be raised.

**See also:** `SaveToStream (??)`, `LoadFromFile (??)`

### 10.11.9 TBlobField.SaveToFile

**Synopsis:** Save field contents to a file

**Declaration:** `procedure SaveToFile(const FileName: String)`

**Visibility:** public

**Description:** `SaveToFile` creates a file stream with `FileName` as the name of the file to open, en then calls `SaveToStream (??)` to write the contents of the blob field to the file. The file is opened in write mode and is created if it does not yet exist.

**Errors:** If the file cannot be created or is not available for writing, an exception will be raised.

**See also:** `LoadFromFile (??)`, `SaveToStream (??)`

### 10.11.10 TBlobField.SaveToStream

**Synopsis:** Save the field's contents to stream

**Declaration:** `procedure SaveToStream(Stream: TStream)`

**Visibility:** public

**Description:** `SaveToStream` can be used to save the contents of the field to a `TStream (??)` descendent. The entire data of the field will be copied. The stream must of course support writing.

**Errors:** If the stream is not writable, an exception will be raised.

**See also:** `SaveToFile (??)`, `LoadFromStream (??)`

### 10.11.11 TBlobField.SetFieldType

Synopsis: Set field type

Declaration: `procedure SetFieldType(AValue: TFieldType); Override`

Visibility: public

Description: `SetFieldType` is overridden by `TBlobField` to check whether a valid Blob field type is set. If so, it calls the inherited method.

See also: `TField.DataType` (??)

### 10.11.12 TBlobField.BlobSize

Synopsis: Size of the current blob

Declaration: `Property BlobSize : LongInt`

Visibility: public

Access: Read

Description: `BlobSize` is the size (in bytes) of the current contents of the field. It will vary as the dataset's current record moves from record to record.

See also: `TField.Size` (??), `TField.DataSize` (??)

### 10.11.13 TBlobField.Modified

Synopsis: Has the field's contents been modified.

Declaration: `Property Modified : Boolean`

Visibility: public

Access: Read,Write

Description: `Modified` indicates whether the field's contents have been modified for the current record.

See also: `TBlobField.LoadFromStream` (??)

### 10.11.14 TBlobField.Value

Synopsis: Return the field's contents as a string

Declaration: `Property Value : String`

Visibility: public

Access: Read,Write

Description: `Value` is redefined by `TBlobField` as a string value: getting or setting this value will convert the BLOB data to a string, it will return the same value as the `TField.AsString` (??) property.

See also: `TField.Value` (??), `TField.AsString` (??)

**10.11.15 TBlobField.Transliterate**

Synopsis: Should the contents of the field be transliterated

Declaration: `Property Transliterate : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: `Transliterate` indicates whether the contents of the field should be transliterated (i.e. changed from OEM to non OEM codepage and vice versa) when reading or writing the value. The actual transliteration must be done in the `TDataset.Translate` (??) method of the dataset to which the field belongs. By default this property is `False`, but it can be set to `True` for BLOB data which contains text in another codepage.

See also: `TStringField.Transliterate` (??), `TDataset.Translate` (??)

**10.11.16 TBlobField.BlobType**

Synopsis: Type of blob

Declaration: `Property BlobType : TBlobType`

Visibility: `published`

Access: `Read, Write`

Description: `BlobType` is an alias for `TField.DataType` (??), but with a restricted set of values. Setting `BlobType` is equivalent to setting the `TField.DataType` (??) property.

See also: `TField.DataType` (??)

**10.11.17 TBlobField.Size**

Synopsis: Size of the blob field

Declaration: `Property Size :`

Visibility: `published`

Access:

Description: `Size` is the size of the blob in the internal memory buffer. It defaults to 0, as the BLOB data is not stored in the internal memory buffer. To get the size of the data in the current record, use the `BlobSize` (??) property instead.

See also: `BlobSize` (??)

**10.12 TBooleanField****10.12.1 Description**

`TBooleanField` is the field class used by `TDataset` (267) whenever it needs to manage boolean data (`TField.DataType` (??) equals `ftBoolean`). It overrides some properties and methods of `TField` (315) to be able to work with boolean data.

It should never be necessary to create an instance of `TBooleanField` manually, a field of this class will be instantiated automatically for each boolean field when a dataset is opened.



See also: TDataSet (267), TField (315)

### 10.12.2 Method overview

Page	Property	Description
<a href="#">248</a>	Create	Create a new instance of the TBooleanField class.

### 10.12.3 Property overview

Page	Property	Access	Description
<a href="#">248</a>	DisplayValues	rw	Textual representation of the true and false values
<a href="#">248</a>	Value	rw	Value of the field as a boolean value

### 10.12.4 TBooleanField.Create

Synopsis: Create a new instance of the TBooleanField class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of the TBooleanField class. It calls the inherited constructor and then sets some TField (315) properties to configure it for working with boolean values.

See also: TField (315)

### 10.12.5 TBooleanField.Value

Synopsis: Value of the field as a boolean value

Declaration: `Property Value : Boolean`

Visibility: public

Access: Read,Write

Description: `Value` is redefined from TField.Value (??) by TBooleanField as a boolean value. It returns the same value as the TField.AsBoolean (??) property.

See also: TField.AsBoolean (??), TField.Value (??)

### 10.12.6 TBooleanField.DisplayValues

Synopsis: Textual representation of the true and false values

Declaration: `Property DisplayValues : String`

Visibility: published

Access: Read,Write

Description: `DisplayValues` contains 2 strings, separated by a semicolon (;) which are used to display the True and False values of the fields. The first string is used for True values, the second value is used for False values. If only one value is given, it will serve as the representation of the True value, the False value will be represented as an empty string.

A value of `Yes;No` will result in `True` values being displayed as 'Yes', and `False` values as 'No'. When writing the value of the field as a string, the string will be compared (case insensitively) with the value for `True`, and if it matches, the field's value will be set to `True`. After this it will be compared to the value for `False`, and if it matches, the field's value will be set to `False`. If the text matches neither of the two values, an exception will be raised.

See also: `TField.AsString` (??), `TField.Text` (??)

## 10.13 TBytesField

### 10.13.1 Description

`TBytesField` is the class used when a dataset must manage data of fixed-size binary type. (`TField.DataType` (??) equals `ftBytes`). It initializes some of the properties of the `TField` (315) class to be able to work with fixed-size byte fields.

It should never be necessary to create an instance of `TBytesField` manually, a field of this class will be instantiated automatically for each binary data field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TVarBytesField` (397)

### 10.13.2 Method overview

Page	Property	Description
<a href="#">249</a>	<code>Create</code>	Create a new instance of a <code>TBytesField</code> class.

### 10.13.3 TBytesField.Create

Synopsis: Create a new instance of a `TBytesField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TBytesField` class. It calls the inherited destructor, and then sets some `TField` (315) properties to configure the instance for working with binary data values.

See also: `TField` (315)

## 10.14 TCheckConstraint

### 10.14.1 Description

`TCheckConstraint` can be used to store the definition of a record-level constraint. It does not enforce the constraint, it only stores the constraint's definition. The constraint can come from several sources: an imported constraints from the database, usually stored in the `TCheckConstraint.ImportedConstraint` (??) property, or a constraint enforced by the user on a particular dataset instance stored in `TCheckConstraint.CustomConstraint` (??)

See also: `TCheckConstraints` (251), `TCheckConstraint.ImportedConstraint` (??), `TCheckConstraint.CustomConstraint` (??)

### 10.14.2 Method overview

Page	Property	Description
<a href="#">250</a>	Assign	Assign one constraint to another

### 10.14.3 Property overview

Page	Property	Access	Description
<a href="#">250</a>	CustomConstraint	rw	User-defined constraint
<a href="#">250</a>	ErrorMessage	rw	Message to display when the constraint is violated
<a href="#">251</a>	FromDictionary	rw	True if the constraint is imported from a datadictionary
<a href="#">251</a>	ImportedConstraint	rw	Constraint imported from the database engine

### 10.14.4 TCheckConstraint.Assign

Synopsis: Assign one constraint to another

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: public

Description: Assign is overridden by TCheckConstraint to copy all published properties if Source is also a TCheckConstraint instance.

Errors: If Source is not an instance of TCheckConstraint, an exception may be thrown.

See also: TCheckConstraint.ImportedConstraint (??), TCheckConstraint.CustomConstraint (??)

### 10.14.5 TCheckConstraint.CustomConstraint

Synopsis: User-defined constraint

Declaration: `Property CustomConstraint : String`

Visibility: published

Access: Read,Write

Description: CustomConstraint is an SQL expression with an additional user-defined constraint. The expression should be enforced by a TDataset ([267](#)) descendent when data is posted to the dataset. If the constraint is violated, then the dataset should raise an exception, with message as specified in TCheckConstraint.ErrorMessage (??)

See also: TCheckConstraint.ErrorMessage (??)

### 10.14.6 TCheckConstraint.ErrorMessage

Synopsis: Message to display when the constraint is violated

Declaration: `Property ErrorMessage : String`

Visibility: published

Access: Read,Write

Description: ErrorMessage is used as the message when the dataset instance raises an exception if the constraint is violated.

See also: TCheckConstraint.CustomConstraint (??)

### 10.14.7 TCheckConstraint.FromDictionary

Synopsis: True if the constraint is imported from a datadictionary

Declaration: `Property FromDictionary : Boolean`

Visibility: published

Access: Read,Write

Description: `FromDictionary` indicates whether a constraint is imported from a data dictionary. This can be set by `TDataset` (267) descendents to indicate the source of the constraint, but is otherwise ignored.

See also: `TCheckConstraint.ImportedConstraint` (??)

### 10.14.8 TCheckConstraint.ImportedConstraint

Synopsis: Constraint imported from the database engine

Declaration: `Property ImportedConstraint : String`

Visibility: published

Access: Read,Write

Description: `ImportedConstraint` is a constraint imported from the database engine: it will not be enforced locally by the `TDataset` (267) descendent.

See also: `TCheckConstraint.CustomConstraint` (??)

## 10.15 TCheckConstraints

### 10.15.1 Description

`TCheckConstraints` is a `TCollection` descendent which keeps a collection of `TCheckConstraint` (249) items. It overrides the `Add` (??) method to return a `TCheckConstraint` instance.

See also: `TCheckConstraint` (249)

### 10.15.2 Method overview

Page	Property	Description
<a href="#">252</a>	Add	Add new <code>TCheckConstraint</code> item to the collection
<a href="#">252</a>	Create	Create a new instance of the <code>TCheckConstraints</code> class.

### 10.15.3 Property overview

Page	Property	Access	Description
<a href="#">252</a>	Items	rw	Indexed access to the items in the collection

### 10.15.4 TCheckConstraints.Create

Synopsis: Create a new instance of the `TCheckConstraints` class.

Declaration: `constructor Create(AOwner: TPersistent)`

Visibility: `public`

Description: `Create` initializes a new instance of the `TCheckConstraints` class. The `AOwner` argument is usually the `TDataset` (267) instance for which the data is managed. It is kept for future reference. After storing the owner, the inherited constructor is called with the `TCheckConstraint` (249) class pointer.

See also: `TCheckConstraint` (249), `TDataset` (267)

### 10.15.5 TCheckConstraints.Add

Synopsis: Add new `TCheckConstraint` item to the collection

Declaration: `function Add : TCheckConstraint`

Visibility: `public`

Description: `Add` is overridden by `TCheckConstraint` to add a new `TCheckConstraint` (249) instance to the collection. it returns the newly added instance.

See also: `TCheckConstraint` (249), `#rtl.classes.TCollection.Add` (??)

### 10.15.6 TCheckConstraints.Items

Synopsis: Indexed access to the items in the collection

Declaration: `Property Items[Index: LongInt]: TCheckConstraint; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` is overridden by `TCheckConstraints` to provide type-safe access to the items in the collection. The `index` is zero-based, so it runs from 0 to `Count-1`.

See also: `#rtl.classes.TCollection.Items` (??)

## 10.16 TCurrencyField

### 10.16.1 Description

`TCurrencyField` is the field class used by `TDataset` (267) when it needs to manage currency-valued data. (`TField.Datatype` (??) equals `ftCurrency`). It simply sets some `Tfield` (315) properties to be able to work with currency data.

It should never be necessary to create an instance of `TCurrencyField` manually, a field of this class will be instantiated automatically for each currency field when a dataset is opened.

See also: `TField` (315), `TDataset` (267)

### 10.16.2 Method overview

Page	Property	Description
<a href="#">253</a>	Create	Create a new instance of a <code>TCurrencyField</code> .

### 10.16.3 Property overview

Page	Property	Access	Description
<a href="#">253</a>	Currency		Is the field a currency field

### 10.16.4 `TCurrencyField.Create`

Synopsis: Create a new instance of a `TCurrencyField`.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of `TCurrencyField`. It calls the inherited constructor and then sets some properties (`TCurrencyField.Currency (??)`) to be able to work with currency data.

See also: `TField` ([315](#)), `TCurrencyField.Currency (??)`

### 10.16.5 `TCurrencyField.Currency`

Synopsis: Is the field a currency field

Declaration: `Property Currency :`

Visibility: `published`

Access:

Description: `Currency` is inherited from `TFloatField.Currency (??)` but is initialized to `True` by the `TCurrencyField` constructor. It can be set to `False` if the contents of the field is of type currency, but does not represent an amount of currency.

See also: `TFloatField.Currency (??)`

## 10.17 `TCustomConnection`

### 10.17.1 Description

`TCustomConnection` must be used for all database classes that need a connection to a server. The class introduces some methods and classes to activate the connection (`Open (??)`) and to deactivate the connection (`TCustomConnection.Close (??)`), plus a property to inspect the state (`Connected (??)`) of the connected.

See also: `TCustomConnection.Open (??)`, `TCustomConnection.Close (??)`, `TCustomConnection.Connected (??)`

### 10.17.2 Method overview

Page	Property	Description
<a href="#">254</a>	Close	Close the connection
<a href="#">254</a>	Destroy	Remove the <code>TCustomconnection</code> instance from memory
<a href="#">254</a>	Open	Makes the connection to the server

### 10.17.3 Property overview

Page	Property	Access	Description
<a href="#">256</a>	AfterConnect	rw	Event triggered after a connection is made.
<a href="#">256</a>	AfterDisconnect	rw	Event triggered after a connection is closed
<a href="#">256</a>	BeforeConnect	rw	Event triggered before a connection is made.
<a href="#">257</a>	BeforeDisconnect	rw	Event triggered before a connection is closed
<a href="#">255</a>	Connected	rw	Is the connection established or not
<a href="#">255</a>	DataSetCount	r	Number of datasets connected to this connection
<a href="#">255</a>	DataSets	r	Datasets linked to this connection
<a href="#">256</a>	LoginPrompt	rw	Should the <code>OnLogin</code> be triggered
<a href="#">257</a>	OnLogin	rw	Event triggered when a login prompt is shown.

### 10.17.4 TCustomConnection.Close

Synopsis: Close the connection

Declaration: `procedure Close`

Visibility: `public`

Description: `Close` closes the connection with the server if it was connected. Calling this method first triggers the `BeforeDisconnect` (??) event. If an exception is raised during the execution of that event handler, the disconnect process is aborted. After calling this event, the connection is actually closed. After the connection was closed, the `AfterDisconnect` (??) event is triggered.

Calling the `Close` method is equivalent to setting the `Connected` (??) property to `False`.

Errors: If the connection cannot be broken for some reason, an `EDatabaseError` ([233](#)) exception will be raised.

See also: `TCustomConnection.BeforeDisconnect` (??), `TCustomConnection.AfterDisconnect` (??), `TCustomConnection.Open` (??), `TCustomConnection.Connected` (??)

### 10.17.5 TCustomConnection.Destroy

Synopsis: Remove the `TCustomconnection` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` closes the connection, and then calls the inherited destructor.

Errors: If an exception is raised during the disconnect process, an exception will be raise, and the instance is not removed from memory.

See also: `TCustomConnection.Close` (??)

### 10.17.6 TCustomConnection.Open

Synopsis: Makes the connection to the server

Declaration: `procedure Open`

Visibility: `public`

**Description:** `Open` establishes the connection with the server if it was not yet connected. Calling this method first triggers the `BeforeConnect (??)` event. If an exception is raised during the execution of that event handler, the connect process is aborted. If `LoginPrompt (??)` is `True`, the `OnLogin (??)` event handler is called. Only after this event, the connection is actually established. After the connection was established, the `AfterConnect (??)` event is triggered.

Calling the `Open` method is equivalent to setting the `Connected (??)` property to `True`.

**Errors:** If an exception is raised during the `BeforeConnect` or `OnLogin` handlers, the connection is not actually established.

**See also:** `TCustomConnection.BeforeConnect (??)`, `TCustomConnection.LoginPrompt (??)`, `TCustomConnection.OnLogin (??)`, `TCustomConnection.AfterConnect (??)`, `TCustomConnection.Connected (??)`

### 10.17.7 TCustomConnection.DataSetCount

**Synopsis:** Number of datasets connected to this connection

**Declaration:** `Property DataSetCount : LongInt`

**Visibility:** `public`

**Access:** `Read`

**Description:** `DataSetCount` is the number of datasets connected to this connection component. The actual datasets are available through the `Datasets (??)` array property. As implemented in `TCustomConnection`, this property is always zero. Descendent classes implement the actual count.

**See also:** `TDataset (267)`, `TCustomConnection.Datasets (??)`

### 10.17.8 TCustomConnection.DataSets

**Synopsis:** Datasets linked to this connection

**Declaration:** `Property DataSets[Index: LongInt]: TDataset`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Datasets` allows indexed access to the datasets connected to this connection. `Index` is a zero-based indexed, it's maximum value is `DataSetCount-1 (??)`.

**See also:** `DataSetCount (??)`

### 10.17.9 TCustomConnection.Connected

**Synopsis:** Is the connection established or not

**Declaration:** `Property Connected : Boolean`

**Visibility:** `published`

**Access:** `Read, Write`

**Description:** `Connected` is `True` if the connection to the server is established, `False` if it is disconnected. The property can be set to `True` to establish a connection (equivalent to calling `TCustomConnection.Open (??)`), or to `False` to break it (equivalent to calling `TCustomConnection.Close (??)`).

**See also:** `TCustomConnection.Open (??)`, `TCustomConnection.Close (??)`



### 10.17.10 TCustomConnection.LoginPrompt

Synopsis: Should the OnLogin be triggered

Declaration: Property LoginPrompt : Boolean

Visibility: published

Access: Read,Write

Description: LoginPrompt can be set to True if the OnLogin handler should be called when the Open method is called. If it is not True, then the event handler is not called.

See also: TCustomConnection.OnLogin (??)

### 10.17.11 TCustomConnection.AfterConnect

Synopsis: Event triggered after a connection is made.

Declaration: Property AfterConnect : TNotifyEvent

Visibility: published

Access: Read,Write

Description: AfterConnect is called after a connection is successfully established in TCustomConnection.Open (??). It can be used to open datasets, or indicate a connection status change.

See also: TCustomConnection.Open (??), TCustomConnection.BeforeConnect (??), TCustomConnection.OnLogin (??)

### 10.17.12 TCustomConnection.AfterDisconnect

Synopsis: Event triggered after a connection is closed

Declaration: Property AfterDisconnect : TNotifyEvent

Visibility: published

Access: Read,Write

Description: AfterDisConnect is called after a connection is successfully closed in TCustomConnection.Close (??). It can be used for instance to indicate a connection status change.

See also: TCustomConnection.Close (??), TCustomConnection.BeforeDisconnect (??)

### 10.17.13 TCustomConnection.BeforeConnect

Synopsis: Event triggered before a connection is made.

Declaration: Property BeforeConnect : TNotifyEvent

Visibility: published

Access: Read,Write

Description: BeforeConnect is called before a connection is attempted in TCustomConnection.Open (??). It can be used to set connection parameters, or to abort the establishing of the connection: if an exception is raised during this event, the connection attempt is aborted.

See also: TCustomConnection.Open (??), TCustomConnection.AfterConnect (??), TCustomConnection.OnLogin (??)

### 10.17.14 TCustomConnection.BeforeDisconnect

Synopsis: Event triggered before a connection is closed

Declaration: `Property BeforeDisconnect : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `BeforeDisConnect` is called before a connection is closed in `TCustomConnection.Close` (??).

It can be used for instance to check for unsaved changes, to save these changes, or to abort the disconnect operation: if an exception is raised during the event handler, the disconnect operation is aborted entirely.

See also: `TCustomConnection.Close` (??), `TCustomConnection.AfterDisconnect` (??)

### 10.17.15 TCustomConnection.OnLogin

Synopsis: Event triggered when a login prompt is shown.

Declaration: `Property OnLogin : TLoginEvent`

Visibility: published

Access: Read,Write

Description: `OnLogin` is triggered when the connection needs a login prompt during the call: it is triggered when the `LoginPrompt` (??) property is `True`, after the `TCustomConnection.BeforeConnect` (??) event, but before the connection is actually established.

See also: `TCustomConnection.BeforeConnect` (??), `TCustomConnection.LoginPrompt` (??), `TCustomConnection.Open` (??)

## 10.18 TDatabase

### 10.18.1 Description

`TDatabase` is a component whose purpose is to provide a connection to an external database engine, not to provide the database itself. This class provides generic methods for attachment to databases and querying their contents; the details of the actual connection are handled by database-specific components (such as `SQLDb` for SQL-based databases, or `DBA` for `DBASE/FoxPro` style databases).

Like `TDataset` (267), `TDatabase` is an abstract class. It provides methods to keep track of datasets connected to the database, and to close these datasets when the connection to the database is closed. To this end, it introduces a `Connected` (??) boolean property, which indicates whether a connection to the database is established or not. The actual logic to establish a connection to a database must be implemented by descendent classes.

See also: `TDataset` (267), `TDatabase` (257)

### 10.18.2 Method overview

Page	Property	Description
<a href="#">258</a>	<code>CloseDataSets</code>	Close all connected datasets
<a href="#">259</a>	<code>CloseTransactions</code>	End all transactions
<a href="#">258</a>	<code>Create</code>	Initialize a new <code>TDatabase</code> class instance.
<a href="#">258</a>	<code>Destroy</code>	Remove a <code>TDatabase</code> instance from memory.
<a href="#">259</a>	<code>EndTransaction</code>	End an active transaction.
<a href="#">259</a>	<code>StartTransaction</code>	Start a new transaction.

### 10.18.3 Property overview

Page	Property	Access	Description
<a href="#">261</a>	<code>Connected</code>	rw	Is the database connected
<a href="#">261</a>	<code>DatabaseName</code>	rw	Database name or path
<a href="#">260</a>	<code>Directory</code>	rw	Directory for the database
<a href="#">260</a>	<code>IsSQLBased</code>	r	Is the database SQL based.
<a href="#">261</a>	<code>KeepConnection</code>	rw	Should the connection be kept active
<a href="#">261</a>	<code>Params</code>	rw	Connection parameters
<a href="#">259</a>	<code>TransactionCount</code>	r	Number of transaction components connected to this database.
<a href="#">260</a>	<code>Transactions</code>	r	Indexed access to all transaction components connected to this database.

### 10.18.4 TDatabase.Create

Synopsis: Initialize a new `TDatabase` class instance.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TDatabase` class. It allocates some resources and then calls the inherited constructor.

See also: `TDBDataset` ([309](#)), `TDBTransaction` ([310](#)), `TDatabase.Destroy` (??)

### 10.18.5 TDatabase.Destroy

Synopsis: Remove a `TDatabase` instance from memory.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` starts by disconnecting the database (thus closing all datasets and ending all transactions), then notifies all connected datasets and transactions that it is about to be released. After this, it releases all resources used by the `TDatabase` instance

See also: `TDatabase.CloseDataSets` (??)

### 10.18.6 TDatabase.CloseDataSets

Synopsis: Close all connected datasets

Declaration: `procedure CloseDataSets`

Visibility: public

Description: `CloseDatasets` closes all connected datasets. It is called automatically when the connection is closed.

See also: `TCustomConnection.Close` (??), `TDatabase.CloseTransactions` (??)

### 10.18.7 TDatabase.CloseTransactions

Synopsis: End all transactions

Declaration: `procedure CloseTransactions`

Visibility: public

Description: `CloseTransaction` calls `TDBTransaction.EndTransaction` (??) on all connected transactions. It is called automatically when the connection is closed, after all datasets are closed.

See also: `TCustomConnection.Close` (??), `TDatabase.CloseDatasets` (??)

### 10.18.8 TDatabase.StartTransaction

Synopsis: Start a new transaction.

Declaration: `procedure StartTransaction; Virtual; Abstract`

Visibility: public

Description: `StartTransaction` must be implemented by descendent classes to start a new transaction. This method is provided for Delphi compatibility: new applications should use a `TDBTransaction` (310) component instead and invoke the `TDBTransaction.StartTransaction` (??) method.

See also: `TDBTransaction` (310), `TDBTransaction.StartTransaction` (??)

### 10.18.9 TDatabase.EndTransaction

Synopsis: End an active transaction.

Declaration: `procedure EndTransaction; Virtual; Abstract`

Visibility: public

Description: `EndTransaction` must be implemented by descendent classes to end an active transaction. This method is provided for Delphi compatibility: new applications should use a `TDBTransaction` (310) component instead and invoke the `TDBTransaction.EndTransaction` (??) method.

See also: `TDBTransaction` (310), `TDBTransaction.EndTransaction` (??)

### 10.18.10 TDatabase.TransactionCount

Synopsis: Number of transaction components connected to this database.

Declaration: `Property TransactionCount : LongInt`

Visibility: public

Access: Read

**Description:** `TransactionCount` is the number of transaction components which are connected to this database instance. It is the upper bound for the `TDatabase.Transactions` (??) array property.

See also: `TDatabase.Transactions` (??)

### 10.18.11 TDatabase.Transactions

**Synopsis:** Indexed access to all transaction components connected to this database.

**Declaration:** `Property Transactions[Index: LongInt]: TDBTransaction`

**Visibility:** public

**Access:** Read

**Description:** `Transactions` provides indexed access to the transaction components connected to this database. The `Index` is zero based: it runs from 0 to `TransactionCount-1`.

See also: `TDatabase.TransactionCount` (??)

### 10.18.12 TDatabase.Directory

**Synopsis:** Directory for the database

**Declaration:** `Property Directory : String`

**Visibility:** public

**Access:** Read, Write

**Description:** `Directory` is provided for Delphi compatibility: it indicates (for Paradox and dBase based databases) the directory where the database files are located. It is not used in the Free Pascal implementation of `TDatabase` (257).

See also: `TDatabase.Params` (??), `TDatabase.IsSQLBased` (??)

### 10.18.13 TDatabase.IsSQLBased

**Synopsis:** Is the database SQL based.

**Declaration:** `Property IsSQLBased : Boolean`

**Visibility:** public

**Access:** Read

**Description:** `IsSQLbased` is a read-only property which indicates whether a property is SQL-Based, i.e. whether the database engine accepts SQL commands.

See also: `TDatabase.Params` (??), `TDatabase.Directory` (??)

#### 10.18.14 TDatabase.Connected

Synopsis: Is the database connected

Declaration: `Property Connected : Boolean`

Visibility: published

Access: Read,Write

Description: `Connected` is simply promoted to published property from `TCustomConnection.Connected` (??).

See also: `TCustomConnection.Connected` (??)

#### 10.18.15 TDatabase.DatabaseName

Synopsis: Database name or path

Declaration: `Property DatabaseName : String`

Visibility: published

Access: Read,Write

Description: `DatabaseName` specifies the path of the database. For directory-based databases this will be the same as the `Directory` (??) property. For other databases this will be the name of a known pre-configured connection, or the location of the database file.

See also: `TDatabase.Directory` (??), `TDatabase.Params` (??)

#### 10.18.16 TDatabase.KeepConnection

Synopsis: Should the connection be kept active

Declaration: `Property KeepConnection : Boolean`

Visibility: published

Access: Read,Write

Description: `KeepConnection` is provided for Delphi compatibility, and is not used in the Free Pascal implementation of `TDatabase`.

See also: `TDatabase.Params` (??)

#### 10.18.17 TDatabase.Params

Synopsis: Connection parameters

Declaration: `Property Params : TStrings`

Visibility: published

Access: Read,Write

Description: `Params` is a catch-all storage mechanism for database connection parameters. It is a list of strings in the form of `Name=Value` pairs. Which name/value pairs are supported depends on the `TDatabase` descendent, but the `user_name` and `password` parameters are commonly used to store the login credentials for the database.

See also: `TDatabase.Directory` (??), `TDatabase.DatabaseName` (??)

## 10.19 TDataLink

### 10.19.1 Description

TDataLink is used by GUI controls or datasets in a master-detail relationship to handle data events coming from a TDataSource (303) instance. It is a class that exists for component programmers, application coders should never need to use TDataLink or one of its descendents.

DB-Aware Component coders must use a TDataLink instance to handle all communication with a TDataSet (267) instance, rather than communicating directly with the dataset. TDataLink contains methods which are called by the various events triggered by the dataset. Inversely, it has some methods to trigger actions in the dataset.

TDataLink is an abstract class; it is never used directly. Instead, a descendent class is used which overrides the various methods that are called in response to the events triggered by the dataset. Examples are .

See also: TDataSet (267), TDataSource (303), TDetailDataLink (314), TMasterDataLink (369)

### 10.19.2 Method overview

Page	Property	Description
<a href="#">262</a>	Create	Initialize a new instance of TDataLink
<a href="#">263</a>	Destroy	Remove an instance of TDataLink from memory
<a href="#">263</a>	Edit	Set the dataset in edit mode, if possible
<a href="#">263</a>	ExecuteAction	Execute action
<a href="#">264</a>	UpdateAction	Update handler for actions
<a href="#">263</a>	UpdateRecord	Called when the data in the dataset must be updated

### 10.19.3 Property overview

Page	Property	Access	Description
<a href="#">264</a>	Active	r	Is the link active
<a href="#">264</a>	ActiveRecord	rw	Currently active record
<a href="#">264</a>	BOF	r	Is the dataset at the first record
<a href="#">265</a>	BufferCount	rw	Set to the number of record buffers this datalink needs.
<a href="#">265</a>	DataSet	r	Dataset this datalink is connected to
<a href="#">265</a>	DataSource	rw	Datasource this datalink is connected to
<a href="#">265</a>	DataSourceFixed	rw	Can the datasource be changed
<a href="#">266</a>	Editing	r	Is the dataset in edit mode
<a href="#">266</a>	Eof	r	
<a href="#">266</a>	ReadOnly	rw	Is the link readonly
<a href="#">266</a>	RecordCount	r	Number of records in the buffer of the dataset

### 10.19.4 TDataLink.Create

Synopsis: Initialize a new instance of TDataLink

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` calls the inherited constructor and then initializes some fields. In particular, it sets the `buffercount` to 1.

See also: TDataLink.Destroy (??)

### 10.19.5 TDataLink.Destroy

Synopsis: Remove an instance of TDataLink from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the TDataLink instance (in particular, it removes itself from the datasource it is coupled to), and then calls the inherited destructor.

See also: TDataLink.Destroy (??)

### 10.19.6 TDataLink.Edit

Synopsis: Set the dataset in edit mode, if possible

Declaration: `function Edit : Boolean`

Visibility: `public`

Description: `Edit` attempts to put the dataset in edit mode. It returns `True` if this operation succeeded, `False` if not. To this end, it calls the `Edit (??)` method of the `DataSource (??)` to which the datalink instance is coupled. If the `TDataSource.AutoEdit (??)` property is `False` then this operation will not succeed, unless the dataset is already in edit mode. GUI controls should always respect the result of this function, and not allow the user to edit data if this function returned `false`.

See also: TDataSource (303), TDataLink.DataSource (??), TDataSource.Edit (??), TDataSource.AutoEdit (??)

### 10.19.7 TDataLink.UpdateRecord

Synopsis: Called when the data in the dataset must be updated

Declaration: `procedure UpdateRecord`

Visibility: `public`

Description: `Updaterecord` is called when the dataset expects the GUI controls to post any pending changes to the dataset. This method guards against recursive behaviour: while an `UpdateRecord` is in progress, the `TDataLink.RecordChange (??)` notification (which could result from writing data to the dataset) will be blocked.

See also: TDataLink.RecordChange (??)

### 10.19.8 TDataLink.ExecuteAction

Synopsis: Execute action

Declaration: `function ExecuteAction(Action: TBasicAction) : Boolean; Virtual`

Visibility: `public`

Description: `ExecuteAction` implements action support. It should never be necessary to call `ExecuteAction` from program code, as it is called automatically whenever a target control needs to handle an action. This method must be overridden in case any additional action must be taken when the action must be executed. The implementation in `TDataLink` checks if the action handles the datasource, and then calls `Action.ExecuteTarget`, passing it the datasource. If so, it returns `True`.

See also: TDataLink.UpdateAction (??)



### 10.19.9 TDataLink.UpdateAction

Synopsis: Update handler for actions

Declaration: `function UpdateAction(Action: TBasicAction) : Boolean; Virtual`

Visibility: `public`

Description: `UpdateAction` implements action update support. It should never be necessary to call `UpdateAction` from program code, as it is called automatically whenever a target control needs to update an action. This method must be overridden in case any specific action must be taken when the action must be updated. The implementation in `TDataLink` checks if the action handles the datasource, and then calls `Action.UpdateTarget`, passing it the datasource. If so, it returns `True`.

See also: `TDataLink.ExecuteAction` (??)

### 10.19.10 TDataLink.Active

Synopsis: Is the link active

Declaration: `Property Active : Boolean`

Visibility: `public`

Access: `Read`

Description: `Active` determines whether the events of the dataset are passed on to the control connected to the actionlink. If it is set to `False`, then no events are passed between control and dataset. It is set to `TDataset.Active` (??) whenever the `DataSource` (??) property is set.

See also: `TDataLink.DataSource` (??), `TDataLink.ReadOnly` (??), `TDataset.Active` (??)

### 10.19.11 TDataLink.ActiveRecord

Synopsis: Currently active record

Declaration: `Property ActiveRecord : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `ActiveRecord` returns the index of the active record in the dataset's record buffer for this datalink.

See also: `TDataLink.BOF` (??), `TDataLink.EOF` (??)

### 10.19.12 TDataLink.BOF

Synopsis: Is the dataset at the first record

Declaration: `Property BOF : Boolean`

Visibility: `public`

Access: `Read`

Description: `BOF` returns `TDataset.BOF` (??) if the dataset is available, `True` otherwise.

See also: `TDataLink.EOF` (??), `TDataset.BOF` (??)

**10.19.13 TDataLink.BufferCount**

Synopsis: Set to the number of record buffers this datalink needs.

Declaration: `Property BufferCount : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `BufferCount` can be set to the number of buffers that the dataset should manage on behalf of the control connected to this datalink. By default, this is 1. Controls that must display more than 1 buffer (such as grids) can set this to a higher value.

See also: `TDataset.ActiveBuffer` (??), `TDatalink.ActiveRecord` (??)

**10.19.14 TDataLink.DataSet**

Synopsis: Dataset this datalink is connected to

Declaration: `Property DataSet : TDataset`

Visibility: `public`

Access: `Read`

Description: `DataSet` equals `Datasource.Dataset` if the datasource is set, or `Nil` otherwise.

See also: `TDatalink.DataSource` (??), `TDataset` (267)

**10.19.15 TDataLink.DataSource**

Synopsis: Datasource this datalink is connected to

Declaration: `Property DataSource : TDataSource`

Visibility: `public`

Access: `Read,Write`

Description: `DataSource` should be set to a `TDataSource` (303) instance to get access to the dataset it is connected to. A datalink never points directly to a `TDataset` (267) instance, always to a datasource. When the datasource is enabled or disabled, all `TDatalink` instances connected to it are enabled or disabled at once.

See also: `TDataset` (267), `TDataSource` (303)

**10.19.16 TDataLink.DataSourceFixed**

Synopsis: Can the datasource be changed

Declaration: `Property DataSourceFixed : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `DataSourceFixed` can be set to `True` to prevent changing of the `DataSource` (??) property. When lengthy operations are in progress, this can be done to prevent user code (e.g. event handlers) from changing the datasource property which might interfere with the operation in progress.

See also: `TDataLink.DataSource` (??)

### 10.19.17 TDataLink.Editing

Synopsis: Is the dataset in edit mode

Declaration: `Property Editing : Boolean`

Visibility: `public`

Access: `Read`

Description: `Editing` determines whether the dataset is in one of the edit states (`dsEdit`, `dsInsert`). It can be set into this mode by calling the `TDatalink.Edit (??)` method. Never attempt to set the dataset in editing mode directly. The `Edit` method will perform the needed checks prior to setting the dataset in edit mode and will return `True` if the dataset was successfully set in the editing state.

See also: `TDatalink.Edit (??)`, `TDataset.Edit (??)`

### 10.19.18 TDataLink.Eof

Synopsis:

Declaration: `Property Eof : Boolean`

Visibility: `public`

Access: `Read`

Description: `EOF` returns `TDataset.EOF (??)` if the dataset is available, `True` otherwise.

See also: `TDatalink.BOF (??)`, `TDataset.EOF (??)`

### 10.19.19 TDataLink.ReadOnly

Synopsis: Is the link readonly

Declaration: `Property ReadOnly : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: `ReadOnly` can be set to `True` to indicate that the link is read-only, i.e. the connected control will not modify the dataset. Methods as `TDatalink.Edit (??)` will check this property and fail if the link is read-only. This setting has no effect on the communication of dataset events to the datalink: the `TDatalink.Active (??)` property can be used to disable delivery of events to the datalink.

See also: `TDatalink.Active (??)`, `TDatalink.edit (??)`

### 10.19.20 TDataLink.RecordCount

Synopsis: Number of records in the buffer of the dataset

Declaration: `Property RecordCount : Integer`

Visibility: `public`

Access: `Read`

Description: `RecordCount` returns the number of records in the dataset's buffer. It is limited by the `TDatalink.BufferCount (??)` property: `RecordCount` is always less than `Buffercount`.

See also: `TDatalink.BufferCount (??)`

## 10.20 TDataSet

### 10.20.1 Description

`TDataSet` is the main class of the `db` unit. This abstract class provides all basic functionality to access data stored in tabular format: The data consists of records, and the data in each record is organised in several fields.

`TDataSet` has a buffer to cache a few records in memory, this buffer is used by `TDataSource` to create the ability to use data-aware components.

`TDataSet` is an abstract class, which provides the basic functionality to access, navigate through the data and - in case read-write access is available, edit existing or add new records.

`TDataSet` is an abstract class: it does not have the knowledge to store or load the records from whatever medium the records are stored on. Descendants add the functionality to load and save the data. Therefore `TDataSet` is never used directly, one always instantiates a descendent class.

Initially, no data is available: the dataset is inactive. The `Open (??)` method must be used to fetch data into memory. After this command, the data is available in memory for browsing or editing purposes: The dataset is active (indicated by the `TDataSet.Active (??)` property). Likewise, the `Close (??)` method can be used to remove the data from memory. Any changes not yet saved to the underlying medium will be lost.

Data is expected to be in tabular format, where each row represents a record. The dataset has an idea of a cursor: this is the current position of the data cursor in the set of rows. Only the data of the current record is available for display or editing purposes. Through the `Next (??)`, `Prev (??)`, `First (??)` and `Last (??)` methods, it is possible to navigate through the records. The `EOF (??)` property will be `True` if the last row has been reached. Likewise, the `BOF (??)` property will return `True` if the first record in the dataset has been reached when navigating backwards. If both properties are empty, then there is no data available. For dataset descendants that support counting the number of records, the `RecordCount (??)` will be zero.

The `Append (??)` and `Insert (??)` methods can be used to insert new records to the set of records. The `TDataSet.Delete (??)` statement is used to delete the current record, and the `Edit (??)` command must be used to set the dataset in editing mode: the contents of the current record can then be changed. Any changes made to the current record (be it a new or existing record) must be saved by the `Post (??)` method, or can be undone using the `Cancel (??)` method.

The data in the various fields properties is available through the `Fields (??)` array property, giving indexed access to all the fields in a record. The contents of a field is always readable. If the dataset is in one of the editing modes, then the fields can also be written to.

See also: [TField \(315\)](#)



**10.20.2 Method overview**

Page	Property	Description
271	ActiveBuffer	Currently active memory buffer
272	Append	Append a new record to the data
272	AppendRecord	Append a new record to the dataset and fill with data
273	BookmarkValid	Test whether ABookMark is a valid bookmark.
273	Cancel	Cancel the current editing operation
273	CheckBrowseMode	Check whether the dataset is in browse mode.
273	ClearFields	Clear the values of all fields
274	Close	Close the dataset
274	CompareBookmarks	Compare two bookmarks
274	ControlsDisabled	Check whether the controls are disabled
271	Create	Create a new TDataset instance
275	CreateBlobStream	Create blob stream
275	CursorPosChanged	Indicate a change in cursor position
275	DataConvert	Convert data from/to native format
275	Delete	Delete the current record.
271	Destroy	Free a TDataset instance
276	DisableControls	Disable event propagation of controls
276	Edit	Set the dataset in editing mode.
277	EnableControls	Enable event propagation of controls
277	FieldByName	Search a field by name
277	FindField	Find a field by name
278	FindFirst	Find the first active record (deprecated)
278	FindLast	Find the last active record (deprecated)
278	FindNext	Find the next active record (deprecated)
278	FindPrior	Find the previous active record (deprecated)
279	First	Position the dataset on the first record.
279	FreeBookmark	Free a bookmark obtained with GetBookmark (deprecated)
279	GetBookmark	Get a bookmark pointer (deprecated)
280	GetCurrentRecord	Copy the data for the current record in a memory buffer
271	GetFieldData	Get the data for a field
280	GetFieldList	Return field instances in a list
280	GetFieldNames	Return a list of all available field names
280	GotoBookmark	Jump to bookmark
281	Insert	Insert a new record at the current position.
281	InsertRecord	Insert a new record with given values.
281	IsEmpty	Check if the dataset contains no data
281	IsLinkedTo	Check whether a datasource is linked to the dataset
282	IsSequenced	Is the data sequenced
282	Last	Navigate forward to the last record
282	Locate	Locate a record based on some key values
283	Lookup	Search for a record and return matching values.
283	MoveBy	Move the cursor position
283	Next	Go to the next record in the dataset.
284	Open	Activate the dataset: Fetch data into memory.
284	Post	Post pending edits to the database.
285	Prior	Go to the previous record
285	Refresh	Refresh the records in the dataset
285	Resync	Resynchronize the data buffer
272	SetFieldData	Store the data for a field
285	SetFields	Set a number of field values at once
286	Translate	Transliterate a buffer
286	UpdateCursorPos	Update cursor position
286	UpdateRecord	Indicate that the record contents have changed
287	UpdateStatus	Get the update status for the current record

### 10.20.3 Property overview

Page	Property	Access	Description
294	Active	rw	Is the dataset open or closed.
299	AfterCancel	rw	Event triggered after a Cancel operation.
296	AfterClose	rw	Event triggered after the dataset is closed
299	AfterDelete	rw	
297	AfterEdit	rw	Event triggered after the dataset is put in edit mode.
297	AfterInsert	rw	Event triggered after the dataset is put in insert mode.
296	AfterOpen	rw	Event triggered after the dataset is opened.
298	AfterPost	rw	Event called after changes have been posted to the underlying database
300	AfterRefresh	rw	Event triggered after the data has been refreshed.
300	AfterScroll	rw	Event triggered after the cursor has changed position.
295	AutoCalcFields	rw	How often should the value of calculated fields be calculated
298	BeforeCancel	rw	Event triggered before a Cancel operation.
296	BeforeClose	rw	Event triggered before the dataset is closed.
299	BeforeDelete	rw	Event triggered before a Delete operation.
297	BeforeEdit	rw	Event triggered before the dataset is put in edit mode.
296	BeforeInsert	rw	Event triggered before the dataset is put in insert mode.
295	BeforeOpen	rw	Event triggered before the dataset is opened.
298	BeforePost	rw	Event called before changes are posted to the underlying database
300	BeforeRefresh	rw	Event triggered before the data is refreshed.
299	BeforeScroll	rw	Event triggered before the cursor changes position.
287	BlockReadSize	rw	
287	BOF	r	Is the cursor at the beginning of the data (on the first record)
287	Bookmark	rw	Get or set the current cursor position
288	CanModify	r	Can the data in the dataset be modified
288	DataSource	r	Datasource this dataset is connected to.
289	DefaultFields	r	Is the dataset using persistent fields or not.
289	EOF	r	Indicates whether the last record has been reached.
290	FieldCount	r	Number of fields
290	FieldDefs	rw	Definitions of available fields in the underlying database
293	Fields	r	Indexed access to the fields of the dataset.
293	FieldValues	rw	Access to field values based on the field names.
293	Filter	rw	Filter to apply to the data in memory.
294	Filtered	rw	Is the filter active or not.
294	FilterOptions	rw	Options to apply when filtering
290	Found	r	Check success of one of the Find methods
291	IsUniDirectional	r	Is the dataset unidirectional (i.e. forward scrolling only)
291	Modified	rw	Was the current record modified ?
301	OnCalcFields	rw	Event triggered when values for calculated fields must be computed.
301	OnDeleteError	rw	Event triggered when a delete operation fails.
301	OnEditError	rw	Event triggered when an edit operation fails.
302	OnFilterRecord	rw	Event triggered to filter records.
302	OnNewRecord	rw	Event triggered when a new record is created.
303	OnPostError	rw	Event triggered when a post operation fails.
292	RecNo	rw	Current record number
291	RecordCount	r	Number of records in the dataset
292	RecordSize	r	Size of the record in memory
292	State	r	Current operational state of the dataset

#### 10.20.4 TDataSet.Create

Synopsis: Create a new TDataSet instance

Declaration: constructor Create(AOwner: TComponent); Override

Visibility: public

Description: Create initializes a new TDataSet (267) instance. It calls the inherited constructor, and then initializes the internal structures needed to manage the dataset (fielddefs, fieldlist, constraints etc.).

See also: TDataSet.Destroy (??)

#### 10.20.5 TDataSet.Destroy

Synopsis: Free a TDataSet instance

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy removes a TDataSet instance from memory. It closes the dataset if it was open, clears all internal structures and then calls the inherited destructor.

Errors: An exception may occur during the close operation, in that case, the dataset will not be removed from memory.

See also: TDataSet.Close (??), TDataSet.Create (??)

#### 10.20.6 TDataSet.ActiveBuffer

Synopsis: Currently active memory buffer

Declaration: function ActiveBuffer : PChar

Visibility: public

Description: ActiveBuffer points to the currently active memory buffer. It should not be used in application code.

#### 10.20.7 TDataSet.GetFieldData

Synopsis: Get the data for a field

```
Declaration: function GetFieldData(Field: TField; Buffer: Pointer) : Boolean; Virtual
                ; Overload
function GetFieldData(Field: TField; Buffer: Pointer;
                NativeFormat: Boolean) : Boolean; Virtual
                ; Overload
```

Visibility: public

Description: GetFieldData should copy the data for field Field from the internal dataset memory buffer into the memory pointed to by Buffer. This function is not intended for use by end-user applications, and should be used only in descendent classes, where it can be overridden. The function should return True if data was available and has been copied, or False if no data was available (in which case the field has value Null). The NativeFormat determines whether the data should be in native format (e.g. whether the date/time values should be in TDateTime format).



Errors: No checks are performed on the validity of the memory buffer

See also: TField.DisplayText (??)

### 10.20.8 TDataSet.SetFieldData

Synopsis: Store the data for a field

Declaration: `procedure SetFieldData(Field: TField; Buffer: Pointer); Virtual  
; Overload  
procedure SetFieldData(Field: TField; Buffer: Pointer;  
NativeFormat: Boolean); Virtual; Overload`

Visibility: public

Description: SetFieldData should copy the data from field `Field`, stored in the memory pointed to by `Buffer` to the dataset memory buffer for the current record. This function is not intended for use by end-user applications, and should be used only in descendent classes, where it can be overridden. The `NativeFormat` determines whether the data is in native format (e.g. whether the date/time values are in `TDateTime` format).

See also: TField.DisplayText (??)

### 10.20.9 TDataSet.Append

Synopsis: Append a new record to the data

Declaration: `procedure Append`

Visibility: public

Description: Append appends a new record at the end of the dataset. It is functionally equal to the `TDataSet.Insert (??)` call, but the cursor is positioned at the end of the dataset prior to performing the insert operation. The same events occur as when the `Insert` call is made.

See also: TDataSet.Insert (??), TDataSet.Edit (??)

### 10.20.10 TDataSet.AppendRecord

Synopsis: Append a new record to the dataset and fill with data

Declaration: `procedure AppendRecord(const Values: Array of const)`

Visibility: public

Description: AppendRecord first calls `Append` to add a new record to the dataset. It then copies the values in `Values` to the various fields (using `TDataSet.SetFields (??)`) and attempts to post the record using `TDataSet.Post (??)`. If all went well, the result is that the values in `Values` have been added as a new record to the dataset.

Errors: Various errors may occur (not supplying a value for all required fields, invalid values) and may cause an exception. This may leave the dataset in editing mode.

See also: TDataSet.Append (??), TDataSet.SetFields (??), TDataSet.Post (??)

**10.20.11 TDataSet.BookmarkValid**

Synopsis: Test whether ABookMark is a valid bookmark.

Declaration: `function BookmarkValid(ABookmark: TBookmark) : Boolean; Virtual`

Visibility: `public`

Description: `BookmarkValid` returns `True` if `ABookMark` is a valid bookmark for the dataset. Various operations can render a bookmark invalid: changing the sort order, closing and re-opening the dataset. `BookmarkValid` always returns `False` in `TDataSet`. Descendent classes must override this method to do an actual test.

Errors: If the bookmark is a completely arbitrary pointer, an exception may be raised.

See also: `TDataSet.GetBookmark` (??), `TDataSet.SetBookmark` (??), `TDataSet.FreeBookmark` (??), `TDataSet.BookmarkAvailable` (??)

**10.20.12 TDataSet.Cancel**

Synopsis: Cancel the current editing operation

Declaration: `procedure Cancel; Virtual`

Visibility: `public`

Description: `Cancel` cancels the current editing operation and sets the dataset again in browse mode. This operation triggers the `TDataSet.OnBeforeCancel` (??) and `TDataSet.OnAfterCancel` (??) events. If the dataset was in insert mode, then the `TDataSet.OnBeforeScroll` (??) and `TDataSet.OnAfterScroll` (??) events are triggered after and respectively before the `OnBeforeCancel` and `OnAfterCancel` events.

If the dataset was not in one of the editing modes when `Cancel` is called, then nothing will happen.

See also: `TDataSet.State` (??), `TDataSet.Append` (??), `TDataSet.Insert` (??), `TDataSet.Edit` (??)

**10.20.13 TDataSet.CheckBrowseMode**

Synopsis: Check whether the dataset is in browse mode.

Declaration: `procedure CheckBrowseMode`

Visibility: `public`

Description: `CheckBrowseMode` checks whether the dataset is in browse mode (`State=dsBrowse`). If it is not, an `EDatabaseError` (233) exception is raised.

See also: `TDataSet.State` (??)

**10.20.14 TDataSet.ClearFields**

Synopsis: Clear the values of all fields

Declaration: `procedure ClearFields`

Visibility: `public`

Description: `ClearFields` clears the values of all fields.

**Errors:** If the dataset is not in editing mode (`State` in `dsEditmodes`), then an `EDatabaseError` (233) exception will be raised.

See also: `TDataset.State` (??), `TField.Clear` (??)

### 10.20.15 `TDataset.Close`

**Synopsis:** Close the dataset

**Declaration:** `procedure Close`

**Visibility:** `public`

**Description:** `Close` closes the dataset if it is open (`Active=True`). This action triggers the `TDataset.OnBeforeClose` (??) and `TDataset.OnAfterClose` (??) events. If the dataset is not active, nothing happens.

**Errors:** If an exception occurs during the closing of the dataset, the `OnAfterClose` event will not be triggered.

See also: `TDataset.Active` (??), `TDataset.Open` (??)

### 10.20.16 `TDataset.ControlsDisabled`

**Synopsis:** Check whether the controls are disabled

**Declaration:** `function ControlsDisabled : Boolean`

**Visibility:** `public`

**Description:** `ControlsDisabled` returns `True` if the controls are disabled, i.e. no events are propagated to the controls connected to this dataset. The `TDataset.DisableControls` (??) call can be used to disable sending of data events to the controls. The sending can be re-enabled with `TDataset.EnableControls` (??). This mechanism has a counting mechanism: in order to enable sending of events to the controls, `EnableControls` must be called as much as `DisableControls` was called. The `ControlsDisabled` function will return true as long as the internal counter is not zero.

See also: `TDataset.DisableControls` (??), `TDataset.EnableControls` (??)

### 10.20.17 `TDataset.CompareBookmarks`

**Synopsis:** Compare two bookmarks

**Declaration:** `function CompareBookmarks(Bookmark1: TBookmark; Bookmark2: TBookmark)  
: LongInt; Virtual`

**Visibility:** `public`

**Description:** `CompareBookmarks` can be used to compare the relative positions of 2 bookmarks. It returns a negative value if `Bookmark1` is located before `Bookmark2`, zero if they refer to the same record, and a positive value if the second bookmark appears before the first bookmark. This function must be overridden by descendent classes of `TDataset`. The implementation in `TDataset` always returns zero.

**Errors:** No checks are performed on the validity of the bookmarks.

See also: `TDataset.BookmarkValid` (??), `TDataset.GetBookmark` (??), `TDataset.SetBookmark` (??)

**10.20.18 TDataSet.CreateBlobStream**

Synopsis: Create blob stream

Declaration: `function CreateBlobStream(Field: TField; Mode: TBlobStreamMode) : TStream  
; Virtual`

Visibility: public

Description: `CreateBlobStream` is not intended for use by application programmers. It creates a stream object which can be used to read or write data from a blob field. Instead, application programmers should use the `TBlobField.LoadFromStream` (??) and `TBlobField.SaveToStream` (??) methods when reading and writing data from/to BLOB fields. Which operation must be performed on the stream is indicated in the `Mode` parameter, and the `Field` parameter contains the field whose data should be read. The caller is responsible for freeing the stream created by this function.

See also: `TBlobField.LoadFromStream` (??), `TBlobField.SaveToStream` (??)

**10.20.19 TDataSet.CursorPosChanged**

Synopsis: Indicate a change in cursor position

Declaration: `procedure CursorPosChanged`

Visibility: public

Description: `CursorPosChanged` is not intended for internal use only, and serves to indicate that the current cursor position has changed. (it clears the internal cursor position).

**10.20.20 TDataSet.DataConvert**

Synopsis: Convert data from/to native format

Declaration: `procedure DataConvert(aField: TField; aSource: Pointer; aDest: Pointer;  
aToNative: Boolean); Virtual`

Visibility: public

Description: `DataConvert` converts the data from field `AField` in buffer `ASource` to native format and puts the result in `ADest`. If the `aToNative` parameter equals `False`, then the data is converted from native format to non-native format. Currently, only date/time/datetime and BCD fields are converted from/to native data. This means the routine handles conversion between `TDateTime` (the native format) and `TDateTimeRec`, and between `TBCD` and currency (the native format) for BCD fields. `DataConvert` is used internally by `TDataset` and descendent classes. There should be no need to use this routine in application code.

Errors: No checking on the validity of the buffer pointers is performed. If an invalid pointer is passed, an exception may be raised.

See also: `TDataset.GetFieldData` (??), `TDataset.SetFieldData` (??)

**10.20.21 TDataSet.Delete**

Synopsis: Delete the current record.

Declaration: `procedure Delete`

Visibility: public

**Description:** `Delete` will delete the current record. This action will trigger the `TDataset.BeforeDelete` (??), `TDataset.BeforeScroll` (??), `TDataset.AfterDelete` (??) and `TDataset.AfterScroll` (??) events. If the dataset was in edit mode, the edits will be canceled before the delete operation starts.

**Errors:** If the dataset is empty or read-only, then an `EDatabaseError` (233) exception will be raised.

**See also:** `TDataset.Cancel` (??), `TDataset.BeforeDelete` (??), `TDataset.BeforeScroll` (??), `TDataset.AfterDelete` (??), `TDataset.AfterScroll` (??)

### 10.20.22 TDataSet.DisableControls

**Synopsis:** Disable event propagation of controls

**Declaration:** `procedure DisableControls`

Visibility: public

**Description:** `DisableControls` tells the dataset to stop sending data-related events to the controls. This can be used before starting operations that will cause the current record to change a lot, or before any other lengthy operation that may cause a lot of events to be sent to the controls that show data from the dataset: each event will cause the control to update itself, which is a time-consuming operation that may also cause a lot of flicker on the screen.

The sending of events to the controls can be re-enabled with `Tdataset.EnableControls` (??). Note that for each call to `DisableControls`, a matching call to `EnableControls` must be made: an internal count is kept and only when the count reaches zero, the controls are again notified of changes to the dataset. It is therefore essential that the call to `EnableControls` is put in a `Finally` block:

```
MyDataset.DisableControls;
Try
    // Do some intensive stuff
Finally
    MyDataset.EnableControls
end;
```

**Errors:** Failure to call `enablecontrols` will prevent the controls from receiving updates. The state can be checked with `TDataset.ControlsDisabled` (??).

**See also:** `TDataset.EnableControls` (??), `TDataset.ControlsDisabled` (??)

### 10.20.23 TDataSet.Edit

**Synopsis:** Set the dataset in editing mode.

**Declaration:** `procedure Edit`

Visibility: public

**Description:** `Edit` will set the dataset in edit mode: the contents of the current record can then be changed. This action will call the `TDataset.BeforeEdit` (??) and `TDataset.AfterEdit` (??) events. If the dataset was already in insert or edit mode, nothing will happen (the events will also not be triggered). If the dataset is empty, this action will execute `TDataset.Append` (??) instead.

**Errors:** If the dataset is read-only or not opened, then an `EDatabaseError` (233) exception will be raised.

**See also:** `TDataset.State` (??), `TDataset.EOF` (??), `TDataset.BOF` (??), `TDataset.Append` (??), `TDataset.BeforeEdit` (??), `TDataset.AfterEdit` (??)

### 10.20.24 TDataSet.EnableControls

Synopsis: Enable event propagation of controls

Declaration: `procedure EnableControls`

Visibility: `public`

Description: `EnableControls` tells the dataset to resume sending data-related events to the controls. This must be used after a call to `TDataSet.DisableControls` (??) to re-enable updating of controls.

Note that for each call to `DisableControls`, a matching call to `EnableControls` must be made: an internal count is kept and only when the count reaches zero, the controls are again notified of changes to the dataset. It is therefore essential that the call to `EnableControls` is put in a `Finally` block:

```
MyDataset.DisableControls;
Try
    // Do some intensive stuff
Finally
    MyDataset.EnableControls
end;
```

Errors: Failure to call `enablecontrols` will prevent the controls from receiving updates. The state can be checked with `TDataSet.ControlsDisabled` (??).

See also: `TDataSet.DisableControls` (??), `TDataSet.ControlsDisabled` (??)

### 10.20.25 TDataSet.FieldName

Synopsis: Search a field by name

Declaration: `function FieldByName(const FieldName: String) : TField`

Visibility: `public`

Description: `FieldByName` is a shortcut for `Fields.FieldByName` (??): it searches for the field with `fieldname` equalling `FieldName`. The case is performed case-insensitive. The matching field instance is returned.

Errors: If the field is not found, an `EDatabaseError` (233) exception will be raised.

See also: `TFields.FieldByName` (??), `TDataSet.FindField` (??)

### 10.20.26 TDataSet.FindField

Synopsis: Find a field by name

Declaration: `function FindField(const FieldName: String) : TField`

Visibility: `public`

Description: `FindField` is a shortcut for `Fields.FindField` (??): it searches for the field with `fieldname` equalling `FieldName`. The case is performed case-insensitive. The matching field instance is returned, and if no match is found, `Nil` is returned.

See also: `TDataSet.FieldName` (??), `TFields.FindField` (??)

### 10.20.27 TDataSet.FindFirst

Synopsis: Find the first active record (deprecated)

Declaration: `function FindFirst : Boolean`

Visibility: `public`

Description: `FindFirst` positions the cursor on the first record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataSet`: The implementation in `TDataSet` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataSet.First (??)` instead.

See also: `TDataSet.First (??)`, `TDataSet.FindLast (??)`, `TDataSet.FindNext (??)`, `TDataSet.FindPrior (??)`

### 10.20.28 TDataSet.FindLast

Synopsis: Find the last active record (deprecated)

Declaration: `function FindLast : Boolean`

Visibility: `public`

Description: `FindLast` positions the cursor on the last record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataSet`: The implementation in `TDataSet` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataSet.Last (??)` instead.

See also: `TDataSet.Last (??)`, `TDataSet.FindFirst (??)`, `TDataSet.FindNext (??)`, `TDataSet.FindPrior (??)`

### 10.20.29 TDataSet.FindNext

Synopsis: Find the next active record (deprecated)

Declaration: `function FindNext : Boolean`

Visibility: `public`

Description: `FindNext` positions the cursor on the next record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataSet`: The implementation in `TDataSet` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataSet.Next (??)` instead.

See also: `TDataSet.Next (??)`, `TDataSet.FindFirst (??)`, `TDataSet.FindLast (??)`, `TDataSet.FindPrior (??)`

### 10.20.30 TDataSet.FindPrior

Synopsis: Find the previous active record (deprecated)

Declaration: `function FindPrior : Boolean`

Visibility: `public`

**Description:** `FindPrior` positions the cursor on the previous record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataset`: The implementation in `TDataset` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataset.Prior (??)` instead.

See also: `TDataset.Prior (??)`, `TDataset.FindFirst (??)`, `TDataset.FindLast (??)`, `TDataset.FindPrior (??)`

### 10.20.31 TDataSet.First

**Synopsis:** Position the dataset on the first record.

**Declaration:** `procedure First`

**Visibility:** `public`

**Description:** `First` positions the dataset on the first record. This action will trigger the `TDataset.BeforeScroll (??)` and `TDataset.AfterScroll (??)` events. After the action is completed, the `TDataset.BOF (??)` property will be `True`.

**Errors:** If the dataset is unidirectional or is closed, an `EDatabaseError (233)` exception will be raised.

See also: `TDataset.Prior (??)`, `TDataset.Last (??)`, `TDataset.Next (??)`, `TDataset.BOF (??)`, `TDataset.BeforeScroll (??)`, `TDataset.AfterScroll (??)`

### 10.20.32 TDataSet.FreeBookmark

**Synopsis:** Free a bookmark obtained with `GetBookmark` (deprecated)

**Declaration:** `procedure FreeBookmark (ABookmark: TBookmark); Virtual`

**Visibility:** `public`

**Description:** `FreeBookmark` must be used to free a bookmark obtained by `TDataset.GetBookmark (??)`. It should not be used on bookmarks obtained with the `TDataset.Bookmark (??)` property. Both `GetBookmark` and `FreeBookmark` are deprecated. Use the `Bookmark` property instead: it uses a string type, which is automatically disposed of when the string variable goes out of scope.

See also: `TDataset.GetBookmark (??)`, `TDataset.Bookmark (??)`

### 10.20.33 TDataSet.GetBookmark

**Synopsis:** Get a bookmark pointer (deprecated)

**Declaration:** `function GetBookmark : TBookmark; Virtual`

**Visibility:** `public`

**Description:** `GetBookmark` gets a bookmark pointer to the current cursor location. The `TDataset.SetBookmark (??)` call can be used to return to the current record in the dataset. After use, the bookmark must be disposed of with the `TDataset.FreeBookmark (??)` call. The bookmark will be `Nil` if the dataset is empty or not active.

This call is deprecated. Use the `TDataset.Bookmark (??)` property instead to get a bookmark.

See also: `TDataset.SetBookmark (??)`, `TDataset.FreeBookmark (??)`, `TDataset.Bookmark (??)`



**10.20.34 TDataSet.GetCurrentRecord**

Synopsis: Copy the data for the current record in a memory buffer

Declaration: `function GetCurrentRecord(Buffer: PChar) : Boolean; Virtual`

Visibility: `public`

Description: `GetCurrentRecord` can be overridden by `TDataSet` descendants to copy the data for the current record to `Buffer`. `Buffer` must point to a memory area, large enough to contain the data for the record. If the data is copied successfully to the buffer, the function returns `True`. The `TDataSet` implementation is empty, and returns `False`.

See also: `TDataSet.ActiveBuffer` (??)

**10.20.35 TDataSet.GetFieldList**

Synopsis: Return field instances in a list

Declaration: `procedure GetFieldList(List: TList; const FieldNames: String)`

Visibility: `public`

Description: `GetfieldList` parses `FieldNames` for names of fields, and returns the field instances that match the names in `list`. `FieldNames` must be a list of field names, separated by semicolons. The list is cleared prior to filling with the requested field instances.

Errors: If `FieldNames` contains a name of a field that does not exist in the dataset, then an `EDatabaseError` (233) exception will be raised.

See also: `TDataSet.GetFieldNames` (??), `TDataSet.FieldByName` (??), `TDataSet.FindField` (??)

**10.20.36 TDataSet.GetFieldNames**

Synopsis: Return a list of all available field names

Declaration: `procedure GetFieldNames(List: TStrings)`

Visibility: `public`

Description: `GetFieldNames` returns in `List` the names of all available fields, one field per item in the list. The dataset must be open for this function to work correctly.

See also: `TDataSet.GetFieldNameList` (??), `TDataSet.FieldByName` (??), `TDataSet.FindField` (??)

**10.20.37 TDataSet.GotoBookmark**

Synopsis: Jump to bookmark

Declaration: `procedure GotoBookmark(ABookmark: TBookmark)`

Visibility: `public`

Description: `GotoBookmark` positions the dataset to the bookmark position indicated by `ABookmark`. `ABookmark` is a bookmark obtained by the `TDataSet.GetBookmark` (??) function.

This function is deprecated, use the `TDataSet.Bookmark` (??) property instead.

Errors: if `ABookmark` does not contain a valid bookmark, then an exception may be raised.

See also: `TDataSet.Bookmark` (??), `TDataSet.GetBookmark` (??), `TDataSet.FreeBookmark` (??)

**10.20.38 TDataSet.Insert**

Synopsis: Insert a new record at the current position.

Declaration: `procedure Insert`

Visibility: `public`

Description: `Insert` will insert a new record at the current position. When this function is called, any pending modifications (when the dataset already is in insert or edit mode) will be posted. After that, the `BeforeInsert (??)`, `BeforeScroll (??)`, `OnNewRecord (??)`, `AfterInsert (??)` and `AfterScroll (??)` events are triggered in the order indicated here. The dataset is in the `dsInsert` state after this method is called, and the contents of the various fields can be set. To write the new record to the underlying database `TDataSet.Post (??)` must be called.

Errors: If the dataset is read-only, calling `Insert` will result in an `EDatabaseError (233)`.

See also: `BeforeInsert (??)`, `BeforeScroll (??)`, `OnNewRecord (??)`, `AfterInsert (??)`, `AfterScroll (??)`, `TDataSet.Post (??)`, `TDataSet.Append (??)`

**10.20.39 TDataSet.InsertRecord**

Synopsis: Insert a new record with given values.

Declaration: `procedure InsertRecord(const Values: Array of const)`

Visibility: `public`

Description: `InsertRecord` is not yet implemented in Free Pascal. It does nothing.

See also: `TDataSet.Insert (??)`, `TDataSet.SetFieldValues (??)`

**10.20.40 TDataSet.IsEmpty**

Synopsis: Check if the dataset contains no data

Declaration: `function IsEmpty : Boolean`

Visibility: `public`

Description: `IsEmpty` returns `True` if the dataset is empty, i.e. if `EOF (??)` and `TDataSet.BOF (??)` are both `True`, and the dataset is not in insert mode.

See also: `TDataSet.EOF (??)`, `TDataSet.BOF (??)`, `TDataSet.State (??)`

**10.20.41 TDataSet.IsLinkedTo**

Synopsis: Check whether a datasource is linked to the dataset

Declaration: `function IsLinkedTo (ADatasource: TDataSource) : Boolean`

Visibility: `public`

Description: `IsLinkedTo` returns `True` if `ADatasource` is linked to this dataset, either directly (the `ADatasource.Dataset" (??)` points to the current dataset instance, or indirectly.

See also: `TDataSource.Dataset (??)`

### 10.20.42 TDataSet.IsSequenced

Synopsis: Is the data sequenced

Declaration: `function IsSequenced : Boolean; Virtual`

Visibility: `public`

Description: `IsSequenced` indicates whether it is safe to use the `TDataSet.RecNo (??)` property to navigate in the records of the data. By default, this property is set to `True`, but `TDataSet` descendents may set this property to `False` (for instance, unidirectional datasets), in which case `RecNo` should not be used to navigate through the data.

See also: `TDataSet.RecNo (??)`

### 10.20.43 TDataSet.Last

Synopsis: Navigate forward to the last record

Declaration: `procedure Last`

Visibility: `public`

Description: `Last` puts the cursor at the last record in the dataset, fetching more records from the underlying database if needed. After a call to `Last`, the `TDataSet.EOF (??)` property will be `True`. Calling this method will trigger the `TDataSet.BeforeScroll (??)` and `TDataSet.AfterScroll (??)` events.

See also: `TDataSet.First (??)`, `TDataSet.Next (??)`, `TDataSet.EOF (??)`, `TDataSet.BeforeScroll (??)`, `TDataSet.AfterScroll (??)`

### 10.20.44 TDataSet.Locate

Synopsis: Locate a record based on some key values

Declaration: `function Locate(const keyfields: String;const keyvalues: Variant;  
options: TLocateOptions) : Boolean; Virtual`

Visibility: `public`

Description: `Locate` attempts to locate a record in the dataset. There are 2 possible cases when using `Locate`.

1. `Keyvalues` is a single value. In that case, `KeyFields` is the name of the field whose value must be matched to the value in `KeyValues`
2. `Keyvalues` is a variant array. In that case, `KeyFields` must contain a list of names of fields (separated by semicolons) whose values must be matched to the values in the `KeyValues` array

The matching always happens according to the `Options` parameter. For a description of the possible values, see `TLocateOption` ([227](#)).

If a record is found that matches the criteria, then the `locate` operation positions the cursor on this record, and returns `True`. If no record is found to match the criteria, `False` is returned, and the position of the cursor is unchanged.

The implementation in `TDataSet` always returns `False`. It is up to `TDataSet` descendents to implement this method and return an appropriate value.

See also: `TDataSet.Find (??)`, `TDataSet.Lookup (??)`, `TLocateOption` ([227](#))

**10.20.45 TDataSet.Lookup**

Synopsis: Search for a record and return matching values.

Declaration: `function Lookup(const KeyFields: String; const KeyValues: Variant;  
const ResultFields: String) : Variant; Virtual`

Visibility: public

Description: `Lookup` always returns `False` in `TDataSet`. Descendents of `TDataSet` can override this method to call `TDataSet.Locate (??)` to locate the record with fields `KeyFields` matching `KeyValues` and then to return the values of the fields in `ResultFields`. If `ResultFields` contains more than one fieldname (separated by semicolons), then the function returns an array. If there is only 1 fieldname, the value is returned directly.

Errors: If the dataset is unidirectional, then a `EDatabaseError (233)` exception will be raised.

See also: `TDataSet.Locate (??)`

**10.20.46 TDataSet.MoveBy**

Synopsis: Move the cursor position

Declaration: `function MoveBy(Distance: LongInt) : LongInt`

Visibility: public

Description: `MoveBy` moves the current record pointer with `Distance` positions. `Distance` may be a positive number, in which case the cursor is moved forward, or a negative number, in which case the cursor is moved backward. The move operation will stop as soon as the beginning or end of the data is reached. The `TDataSet.BeforeScroll (??)` and `TDataSet.AfterScroll (??)` events are triggered (once) when this method is called. The function returns the distance which was actually moved by the cursor.

Errors: A negative distance will result in an `EDatabaseError (233)` exception on unidirectional datasets.

See also: `TDataSet.RecNo (??)`, `TDataSet.BeforeScroll (??)`, `TDataSet.AfterScroll (??)`

**10.20.47 TDataSet.Next**

Synopsis: Go to the next record in the dataset.

Declaration: `procedure Next`

Visibility: public

Description: `Next` positions the cursor on the next record in the dataset. It is equivalent to a `MoveBy (1)` operation. Calling this method triggers the `TDataSet.BeforeScroll (??)` and `TDataSet.AfterScroll (??)` events. If the dataset is located on the last known record (`EOF (??)` is true), then no action is performed, and the events are not triggered.

Errors: Calling this method on a closed dataset will result in an `EDatabaseError (233)` exception.

See also: `TDataSet.MoveBy (??)`, `TDataSet.Prior (??)`, `TDataSet.Last (??)`, `TDataSet.BeforeScroll (??)`, `TDataSet.AfterScroll (??)`, `TDataSet.EOF (??)`

**10.20.48 TDataSet.Open**

Synopsis: Activate the dataset: Fetch data into memory.

Declaration: `procedure Open`

Visibility: `public`

Description: `Open` must be used to make the `TDataSet` Active. It does nothing if the dataset is already active. `Open` initialises the `TDataSet` and brings the dataset in a browsable state:

Effectively the following happens:

1. The `BeforeOpen` event is triggered.
2. The descendents `InternalOpen` method is called to actually fetch data and initialize field-  
defs and field instances.
3. `BOF (??)` is set to `True`
4. Internal buffers are allocated and filled with data
5. If the dataset is empty, `EOF (??)` is set to `true`
6. `State (??)` is set to `dsBrowse`
7. The `AfterOpen (??)` event is triggered

Errors: If the descendent class cannot fetch the data, or the data does not match the field definitions present in the dataset, then an exception will be raised.

See also: `TDataSet.Active (??)`, `TDataSet.State (??)`, `TDataSet.BOF (??)`, `TDataSet.EOF (??)`, `TDataSet.BeforeOpen (??)`, `TDataSet.AfterOpen (??)`

**10.20.49 TDataSet.Post**

Synopsis: Post pending edits to the database.

Declaration: `procedure Post; Virtual`

Visibility: `public`

Description: `Post` attempts to save pending edits when the dataset is in one of the edit modes: that is, after a `Insert (??)`, `Append (??)` or `TDataSet.Edit (??)` operation. The changes will be committed to memory - and usually immediatly to the underlying database as well. Prior to saving the data to memory, it will check some constraints: in `TDataSet`, the presence of a value for all required fields is checked. if for a required field no value is present, an exception will be raised. A call to `Post` results in the triggering of the `BeforePost (??)`, `AfterPost (??)` events. After the call to `Post`, the `State (??)` of the dataset is again `dsBrowse`, i.e. the dataset is again in browse mode.

Errors: Invoking the `post` method when the dataset is not in one of the editing modes (`dsEditModes (218)`) will result in an `EdatabaseError (233)` exception. If an exception occurs during the save operation, the `OnPostError (??)` event is triggered to handle the error.

See also: `Insert (??)`, `Append (??)`, `Edit (??)`, `OnPostError (??)`, `BeforePost (??)`, `AfterPost (??)`, `State (??)`

**10.20.50 TDataSet.Prior**

Synopsis: Go to the previous record

Declaration: `procedure Prior`

Visibility: `public`

Description: `Prior` moves the cursor to the previous record. It is equivalent to a `MoveBy(-1)` operation. Calling this method triggers the `TDataSet.BeforeScroll` (??) and `TDataSet.AfterScroll` (??) events. If the dataset is located on the first record, (`BOF` (??) is true) then no action is performed, and the events are not triggered.

Errors: Calling this method on a closed dataset will result in an `EDatabaseError` (233) exception.

See also: `TDataSet.MoveBy` (??), `TDataSet.Next` (??), `TDataSet.First` (??), `TDataSet.BeforeScroll` (??), `TDataSet.AfterScroll` (??), `TDataSet.BOF` (??)

**10.20.51 TDataSet.Refresh**

Synopsis: Refresh the records in the dataset

Declaration: `procedure Refresh`

Visibility: `public`

Description: `Refresh` posts any pending edits, and refetches the data in the dataset from the underlying database, and attempts to reposition the cursor on the same record as it was. This operation is not supported by all datasets, and should be used with care. The repositioning may not always succeed, in which case the cursor will be positioned on the first record in the dataset. This is in particular true for unidirectional datasets. Calling `Refresh` results in the triggering of the `BeforeRefresh` (??) and `AfterRefresh` (??) events.

Errors: Refreshing may fail if the underlying dataset descendent does not support it.

See also: `TDataSet.Close` (??), `TDataSet.Open` (??), `BeforeRefresh` (??), `AfterRefresh` (??)

**10.20.52 TDataSet.Resync**

Synopsis: Resynchronize the data buffer

Declaration: `procedure Resync (Mode: TResyncMode); Virtual`

Visibility: `public`

Description: `Resync` refetches the records around the cursor position. It should not be used by application code, instead `TDataSet.Refresh` (??) should be used. The `Resync` parameter indicates how the buffers should be refreshed.

See also: `TDataSet.Refresh` (??)

**10.20.53 TDataSet.SetFields**

Synopsis: Set a number of field values at once

Declaration: `procedure SetFields (const Values: Array of const)`

Visibility: `public`

**Description:** `SetFields` sets the values of the fields with the corresponding values in the array. It starts with the first field in the `TDataset.Fields` (??) property, and works it's way down the array.

**Errors:** If the dataset is not in edit mode, then an `EDatabaseError` (233) exception will be raised. If there are more values than fields, an `EListError` exception will be raised.

See also: `TDataset.Fields` (??)

#### 10.20.54 `TDataset.Translate`

**Synopsis:** Transliterate a buffer

**Declaration:** `function Translate(Src: PChar; Dest: PChar; ToOem: Boolean) : Integer; Virtual`

**Visibility:** public

**Description:** `Translate` is called for all string fields for which the `TStringField.Transliterate` (??) property is set to `True`. The `toOEM` parameter is set to `True` if the transliteration must happen from the used codepage to the codepage used for storage, and if it is set to `False` then the transliteration must happen from the native codepage to the storage codepage. This call must be overridden by descendents of `TDataset` to provide the necessary transliteration: `TDataset` just copies the contents of the `Src` buffer to the `Dest` buffer. The result must be the number of bytes copied to the destination buffer.

**Errors:** No checks are performed on the buffers.

See also: `TStringField.Transliterate` (??)

#### 10.20.55 `TDataset.UpdateCursorPos`

**Synopsis:** Update cursor position

**Declaration:** `procedure UpdateCursorPos`

**Visibility:** public

**Description:** `UpdateCursorPos` should not be used in application code. It is used to ensure that the logical cursor position is the correct (physical) position.

See also: `TDataset.Refresh` (??)

#### 10.20.56 `TDataset.UpdateRecord`

**Synopsis:** Indicate that the record contents have changed

**Declaration:** `procedure UpdateRecord`

**Visibility:** public

**Description:** `UpdateRecord` notifies controls that the contents of the current record have changed. It triggers the event. This should never be called by application code, and is intended only for descendents of `TDataset`.

See also: `OnUpdateRecord` (??)

**10.20.57 TDataSet.UpdateStatus**

Synopsis: Get the update status for the current record

Declaration: `function UpdateStatus : TUpdateStatus; Virtual`

Visibility: `public`

Description: `UpdateStatus` always returns `usUnModified` in the `TDataSet` implementation. Descendent classes should override this method to indicate the status for the current record in case they support cached updates: the function should return the status of the current record: has the record been locally inserted, modified or deleted, or none of these. `UpdateStatus` is not used in `TDataSet` itself, but is provided so applications have a unique API to work with datasets that have support for cached updates.

**10.20.58 TDataSet.BlockReadSize**

Declaration: `Property BlockReadSize : Integer`

Visibility: `public`

Access: `Read,Write`

**10.20.59 TDataSet.BOF**

Synopsis: Is the cursor at the beginning of the data (on the first record)

Declaration: `Property BOF : Boolean`

Visibility: `public`

Access: `Read`

Description: `BOF` returns `True` if the first record is the first record in the dataset, `False` otherwise. It will always be `True` if the dataset is just opened, or after a call to `TDataSet.First (??)`. As soon as `TDataSet.Next (??)` is called, `BOF` will no longer be true.

See also: `TDataSet.EOF (??)`, `TDataSet.Next (??)`, `TDataSet.First (??)`

**10.20.60 TDataSet.Bookmark**

Synopsis: Get or set the current cursor position

Declaration: `Property Bookmark : TBookmarkStr`

Visibility: `public`

Access: `Read,Write`

Description: `Bookmark` can be read to obtain a bookmark to the current position in the dataset. The obtained value can be used to return to current position at a later stage. Writing the `Bookmark` property with a value previously obtained like this, will reposition the dataset on the same position as it was when the property was read.

This is often used when scanning all records, like this:



```

Var
  B : TBookmarkStr;

begin
  With MyDataset do
    begin
      B:=Bookmark;
      DisableControls;
    try
      First;
      While Not EOF do
        begin
          DoSomething;
        Next;
      end;
    finally
      EnableControls;
      Bookmark:=B;
    end;
  end;
end;

```

At the end of this code, the dataset will be positioned on the same record as when the code was started. The `TDataset.DisableControls` (??) and `TDataset.EnableControls` (??) calls prevent the controls from receiving update notifications as the dataset scrolls through the records, thus reducing flicker on the screen.

Note that bookmarks become invalid as soon as the dataset closes. A call to refresh may also destroy the bookmarks.

See also: `TDataset.DisableControls` (??), `TDataset.EnableControls` (??)

### 10.20.61 TDataSet.CanModify

Synopsis: Can the data in the dataset be modified

Declaration: `Property CanModify : Boolean`

Visibility: public

Access: Read

Description: `CanModify` indicates whether the dataset allows editing. Unidirectional datasets do not allow editing. Descendent datasets can impose additional conditions under which the data can not be modified (read-only datasets, for instance). If the `CanModify` property is `False`, then the edit, append or insert methods will fail.

See also: `TDataset.Insert` (??), `TDataset.Append` (??), `TDataset.Delete` (??), `Tdataset.Edit` (??)

### 10.20.62 TDataSet.DataSource

Synopsis: Datasource this dataset is connected to.

Declaration: `Property DataSource : TDataSource`

Visibility: public

Access: Read

**Description:** `Datasource` is the datasource this dataset is connected to, and from which it can get values for parameters. In `TDataset`, the `Datasource` property is not used, and is always `Nil`. It is up to descendent classes that actually support a datasource to implement getter and setter routines for the `Datasource` property.

See also: `TDatasource` (303)

### 10.20.63 `TDataset.DefaultFields`

**Synopsis:** Is the dataset using persistent fields or not.

**Declaration:** Property `DefaultFields` : Boolean

**Visibility:** public

**Access:** Read

**Description:** `DefaultFields` is `True` if the fields were generated dynamically when the dataset was opened. If it is `False` then the field instances are persistent, i.e. they were created at design time with the fields editor. If `DefaultFields` is `True`, then for each item in the `TDataset.FieldDefs` (??) property, a field instance is created. These field instances are freed again when the dataset is closed.

If `DefaultFields` is `False`, then there may be less field instances than there are items in the `FieldDefs` property. This can be the case for instance when opening a DBF file at runtime which has more fields than the file used at design time.

See also: `TDataset.FieldDefs` (??), `TDataset.Fields` (??), `TField` (315)

### 10.20.64 `TDataset.EOF`

**Synopsis:** Indicates whether the last record has been reached.

**Declaration:** Property `EOF` : Boolean

**Visibility:** public

**Access:** Read

**Description:** `EOF` is `True` if the cursor is on the last record in the dataset, and no more records are available. It is also `True` for an empty dataset. The `EOF` property will be set to `True` in the following cases:

1. The `TDataset.Last` (??) method is called.
2. The record is on the last record, and the `TDataset.Next` (??) method is called.
3. The dataset is empty when opened

In all other cases, `EOF` is `False`. Note that when the cursor is on the last-but-one record, and `Next` is called, `EOF` will not yet be `True`. It is only when the cursor is on the last record and `Next` is called, that `EOF` will become `True`. This means that the following loop will stop after the last record was visited:

```
With MyDataset do
  While not EOF do
    begin
      DoSomething;
      Next;
    end;
```

See also: `TDataset.BOF` (??), `TDataset.Next` (??), `TDataset.Last` (??), `TDataset.IsEmpty` (??)

**10.20.65 TDataSet.FieldCount**

Synopsis: Number of fields

Declaration: `Property FieldCount : LongInt`

Visibility: `public`

Access: `Read`

Description: `FieldCount` is the same as `Fields.Count` (??), i.e. the number of fields. For a dataset with persistent fields (when `DefaultFields` (??) is `False`) then this number will be always the same every time the dataset is opened. For a dataset with dynamically created fields, the number of fields may be different each time the dataset is opened.

See also: `TFields` ([345](#))

**10.20.66 TDataSet.FieldDefs**

Synopsis: Definitions of available fields in the underlying database

Declaration: `Property FieldDefs : TFieldDefs`

Visibility: `public`

Access: `Read,Write`

Description: `FieldDefs` is filled by the `TDataset` descendent when the dataset is opened. It represents the fields as they are returned by the particular database when the data is initially fetched from the engine. If the dataset uses dynamically created fields (when `DefaultFields` (??) is `True`), then for each item in this list, a field instance will be created with default properties available in the field definition. If the dataset uses persistent fields, then the fields in the field list will be checked against the items in the `FieldDefs` property. If no matching item is found for a persistent field, then an exception will be raised. Items that exist in the `fielddefs` property but for which there is no matching field instance, are ignored.

See also: `TDataset.Open` (??), `TDataset.DefaultFields` (??), `TDataset.Fields` (??)

**10.20.67 TDataSet.Found**

Synopsis: Check success of one of the `Find` methods

Declaration: `Property Found : Boolean`

Visibility: `public`

Access: `Read`

Description: `Found` is `True` if the last of one of the `TDataset.FindFirst` (??), `TDataset.FindLast` (??), `TDataset.FindNext` (??) or `TDataset.FindPrior` (??) operations was succesful.

See also: `TDataset.FindFirst` (??), `TDataset.FindLast` (??), `TDataset.FindNext` (??), `TDataset.FindPrior` (??)

**10.20.68 TDataSet.Modified**

Synopsis: Was the current record modified ?

Declaration: `Property Modified : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: `Modified` is `True` if the current record was modified after a call to `Tdataset.Edit (??)` or `Tdataset.Insert (??)`. It becomes `True` if a value was written to one of the fields of the dataset.

See also: `Tdataset.Edit (??)`, `TDataSet.Insert (??)`, `TDataSet.Append (??)`, `TDataSet.Cancel (??)`, `TDataSet.Post (??)`

**10.20.69 TDataSet.IsUniDirectional**

Synopsis: Is the dataset unidirectional (i.e. forward scrolling only)

Declaration: `Property IsUniDirectional : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsUniDirectional` is `True` if the dataset is unidirectional. By default it is `False`, i.e. scrolling backwards is allowed. If the dataset is unidirectional, then any attempt to scroll backwards (using one of `TDataSet.Prior (??)` or `TDataSet.Next (??)`), random positioning of the cursor, editing or filtering will result in an `EDatabaseError (233)`. Unidirectional datasets are also not suitable for display in a grid, as they have only 1 record in memory at any given time: they are only useful for performing an action on all records:

```
With MyDataset do
  While not EOF do
    begin
      DoSomething;
      Next;
    end;
```

See also: `TDataSet.Prior (??)`, `TDataSet.Next (??)`

**10.20.70 TDataSet.RecordCount**

Synopsis: Number of records in the dataset

Declaration: `Property RecordCount : LongInt`

Visibility: `public`

Access: `Read`

Description: `RecordCount` is the number of records in the dataset. This number is not necessarily equal to the number of records returned by a query. For optimization purposes, a `TDataSet` descendent may choose not to fetch all records from the database when the dataset is opened. If this is the case, then the `RecordCount` will only reflect the number of records that have actually been fetched at the current time, and therefor the value will change as more records are fetched from the database.

Only when `Last` has been called (and the dataset has been forced to fetch all records returned by the database), will the value of `RecordCount` be equal to the number of records returned by the query.

In general, datasets based on in-memory data or flat files, will return the correct number of records in `RecordCount`.

See also: `TDataset.RecNo` (??)

### 10.20.71 `TDataset.RecNo`

Synopsis: Current record number

Declaration: Property `RecNo` : `LongInt`

Visibility: public

Access: Read,Write

Description: `RecNo` returns the current position in the dataset. It can be written to set the cursor to the indicated position. This property must be implemented by `TDataset` descendents, for `TDataset` the property always returns -1.

This property should not be used if exact positioning is required. it is inherently unreliable.

See also: `TDataset.RecordCount` (??)

### 10.20.72 `TDataset.RecordSize`

Synopsis: Size of the record in memory

Declaration: Property `RecordSize` : `Word`

Visibility: public

Access: Read

Description: `RecordSize` is the total size of the memory buffer used for the records. This property returns always 0 in the `TDataset` implementation. Descendent classes should implement this property. Note that this property does not necessarily reflect the actual data size for the records. that may be more or less, depending on how the `TDataset` descendent manages it's data.

See also: `TField.Datasize` (??), `TDataset.RecordCount` (??), `TDataset.RecNo` (??)

### 10.20.73 `TDataset.State`

Synopsis: Current operational state of the dataset

Declaration: Property `State` : `TDatasetState`

Visibility: public

Access: Read

Description: `State` determines the current operational state of the dataset. During it's lifetime, the dataset is in one of many states, depending on which operation is currently in progress:

- If a dataset is closed, the `State` is `dsInactive`.
- As soon as it is opened, it is in `dsBrowse` mode, and remains in this state while changing the cursor position.

- If the `Edit` or `Insert` or `Append` methods is called, the `State` changes to `dsEdit` or `dsInsert`, respectively.
- As soon as edits have been posted or cancelled, the state is again `dsBrowse`.
- Closing the dataset sets the state again to `dsInactive`.

There are some other states, mainly connected to internal operations, but which can become visible in some of the dataset's events.

See also: `TDataset.Active` (??), `TDataset.Edit` (??), `TDataset.Insert` (??), `TDataset.Append` (??), `TDataset.Post` (??), `TDataset.Cancel` (??)

#### 10.20.74 TDataSet.Fields

Synopsis: Indexed access to the fields of the dataset.

Declaration: `Property Fields : Tfields`

Visibility: `public`

Access: `Read`

Description: `Fields` provides access to the fields of the dataset. It is of type `TFields` (345) and therefore gives indexed access to the fields, but also allows other operations such as searching for fields based on their names or getting a list of fieldnames.

See also: `TFieldDefs` (343), `TField` (315)

#### 10.20.75 TDataSet.FieldValues

Synopsis: Acces to field values based on the field names.

Declaration: `Property FieldValues[fieldname: String]: Variant; default`

Visibility: `public`

Access: `Read,Write`

Description: `FieldValues` provides array-like access to the values of the fields, based on the names of the fields. The value is read or written as a variant type. It is equivalent to the following:

```
FieldByName(FieldName).AsVariant
```

It can be read as well as written.

See also: `TFields.FieldByName` (??)

#### 10.20.76 TDataSet.Filter

Synopsis: Filter to apply to the data in memory.

Declaration: `Property Filter : String`

Visibility: `public`

Access: `Read,Write`

**Description:** `Filter` is not implemented by `TDataset`. It is up to descendent classes to implement actual filtering: the filtering happens on in-memory data, and is not applied on the database level. (in particular: setting the filter property will in no way influence the `WHERE` clause of an SQL-based dataset).

In general, the `filter` property accepts a SQL-like syntax usually encountered in the `WHERE` clause of an SQL `SELECT` statement.

The filter is only applied if the `Filtered` property is set to `True`. If the `Filtered` property is `False`, the `Filter` property is ignored.

See also: `TDataset.Filtered` (??), `TDataset.FilterOptions` (??)

### 10.20.77 `TDataset.Filtered`

**Synopsis:** Is the filter active or not.

**Declaration:** `Property Filtered : Boolean`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Filtered` determines whether the filter condition in `TDataset.Filter` (??) is applied or not. The filter is only applied if the `Filtered` property is set to `True`. If the `Filtered` property is `False`, the `Filter` property is ignored.

See also: `TDataset.Filter` (??), `TDataset.FilterOptions` (??)

### 10.20.78 `TDataset.FilterOptions`

**Synopsis:** Options to apply when filtering

**Declaration:** `Property FilterOptions : TFilterOptions`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `FilterOptions` determines what options should be taken into account when applying the filter in `TDataset.Filter` (??), such as case-sensitivity or whether to treat an asterisk as a wildcard: By default, an asterisk (\*) at the end of a literal string in the filter expression is treated as a wildcard. When `FilterOptions` does not include `foNoPartialCompare`, strings that have an asterisk at the end, indicate a partial string match. In that case, the asterisk matches any number of characters. If `foNoPartialCompare` is included in the options, the asterisk is regarded as a regular character.

See also: `TDataset.Filter` (??), `TDataset.FilterOptions` (??)

### 10.20.79 `TDataset.Active`

**Synopsis:** Is the dataset open or closed.

**Declaration:** `Property Active : Boolean`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Active` is `True` if the dataset is open, and `False` if it is closed (`TDataset.State` (??) is then `dsInactive`). Setting the `Active` property to `True` is equivalent to calling `TDataset.Open` (??), setting it to `False` is equivalent to calling `TDataset.Close` (??)

See also: `TDataset.State` (??), `TDataset.Open` (??), `TDataset.Close` (??)

### 10.20.80 `TDataset.AutoCalcFields`

**Synopsis:** How often should the value of calculated fields be calculated

**Declaration:** `Property AutoCalcFields : Boolean`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `AutoCalcFields` is by default `true`, meaning that the values of calculated fields will be computed in the following cases:

- When the dataset is opened
- When the dataset is put in edit mode
- When a data field changed

When `AutoCalcFields` is `False`, then the calculated fields are called whenever

- The dataset is opened
- The dataset is put in edit mode

Both proper calculated fields and lookup fields are computed. Calculated fields are computed through the `TDataset.OnCalcFields` (??) event.

See also: `TField.FieldKind` (??), `TDataset.OnCalcFields` (??)

### 10.20.81 `TDataset.BeforeOpen`

**Synopsis:** Event triggered before the dataset is opened.

**Declaration:** `Property BeforeOpen : TDataSetNotifyEvent`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `BeforeOpen` is triggered before the dataset is opened. No actions have been performed yet when this event is called, and the dataset is still in `dsInactive` state. It can be used to set parameters and options that influence the opening process. If an exception is raised during the event handler, the dataset remains closed.

See also: `TDataset.AfterOpen` (??), `TDataset.State` (??)



### 10.20.82 TDataSet.AfterOpen

Synopsis: Event triggered after the dataset is opened.

Declaration: Property AfterOpen : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: AfterOpen is triggered after the dataset is opened. The dataset has fetched its data and is in `dsBrowse` state when this event is triggered. If the dataset is not empty, then a `TDataSet.AfterScroll` (??) event will be triggered immediately after the AfterOpen event. If an exception is raised during the event handler, the dataset remains open, but the AfterScroll event will not be triggered.

See also: `TDataSet.AfterOpen` (??), `TDataSet.State` (??), `TDataSet.AfterScroll` (??)

### 10.20.83 TDataSet.BeforeClose

Synopsis: Event triggered before the dataset is closed.

Declaration: Property BeforeClose : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: BeforeClose is triggered before the dataset is closed. No actions have been performed yet when this event is called, and the dataset is still in `dsBrowse` state or one of the editing states. It can be used to prevent closing of the dataset, for instance if there are pending changes not yet committed to the database. If an exception is raised during the event handler, the dataset remains opened.

See also: `TDataSet.AfterClose` (??), `TDataSet.State` (??)

### 10.20.84 TDataSet.AfterClose

Synopsis: Event triggered after the dataset is closed

Declaration: Property AfterClose : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: AfterOpen is triggered after the dataset is opened. The dataset has discarded its data and has cleaned up its internal memory structures. It is in `dsInactive` state when this event is triggered.

See also: `TDataSet.BeforeClose` (??), `TDataSet.State` (??)

### 10.20.85 TDataSet.BeforeInsert

Synopsis: Event triggered before the dataset is put in insert mode.

Declaration: Property BeforeInsert : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

**Description:** `BeforeInsert` is triggered at the start of the `TDataset.Append (??)` or `TDataset.Insert (??)` methods. The dataset is still in `dsBrowse` state when this event is triggered. If an exception is raised in the `BeforeInsert` event handler, then the dataset will remain in `dsBrowse` state, and the append or insert operation is cancelled.

See also: `TDataset.AfterInsert (??)`, `TDataset.Append (??)`, `TDataset.Insert (??)`

### 10.20.86 TDataSet.AfterInsert

**Synopsis:** Event triggered after the dataset is put in insert mode.

**Declaration:** `Property AfterInsert : TDataSetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `AfterInsert` is triggered after the dataset has finished putting the dataset in `dsInsert` state and it has initialized the new record buffer. This event can be used e.g. to set initial field values. After the `Afterinsert` event, the `TDataset.AfterScroll (??)` event is still triggered. Raising an exception in the `AfterInsert` event, will prevent the `AfterScroll` event from being triggered, but does not undo the insert or append operation.

See also: `TDataset.BeforeInsert (??)`, `TDataset.AfterScroll (??)`, `TDataset.Append (??)`, `TDataset.Insert (??)`

### 10.20.87 TDataSet.BeforeEdit

**Synopsis:** Event triggered before the dataset is put in edit mode.

**Declaration:** `Property BeforeEdit : TDataSetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `BeforeEdit` is triggered at the start of the `TDataset.Edit (??)` method. The dataset is still in `dsBrowse` state when this event is triggered. If an exception is raised in the `BeforeEdit` event handler, then the dataset will remain in `dsBrowse` state, and the edit operation is cancelled.

See also: `TDataset.AfterEdit (??)`, `TDataset.Edit (??)`, `TDataset.State (??)`

### 10.20.88 TDataSet.AfterEdit

**Synopsis:** Event triggered after the dataset is put in edit mode.

**Declaration:** `Property AfterEdit : TDataSetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `AfterEdit` is triggered after the dataset has finished putting the dataset in `dsEdit` state and it has initialized the edit buffer for the record. Raising an exception in the `AfterEdit` event does not undo the edit operation.

See also: `TDataset.BeforeEdit (??)`, `TDataset.Edit (??)`, `TDataset.State (??)`

### 10.20.89 TDataSet.BeforePost

Synopsis: Event called before changes are posted to the underlying database

Declaration: `Property BeforePost : TDataSetNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `BeforePost` is triggered at the start of the `TDataSet.Post` (??) method, when the dataset is still in one of the edit states (`dsEdit,dsInsert`). If the dataset was not in an edit state when `Post` is called, the `BeforePost` event is not triggered. This event can be used to supply values for required fields that have no value yet (the `Post` operation performs the check on required fields only after this event), or it can be used to abort the post operation: if an exception is raised during the `BeforePost` operation, the posting operation is cancelled, and the dataset remains in the editing state it was in before the post operation.

See also: `TDataSet.post` (??), `TDataSet.AfterPost` (??), `TDataSet.State` (??)

### 10.20.90 TDataSet.AfterPost

Synopsis: Event called after changes have been posted to the underlying database

Declaration: `Property AfterPost : TDataSetNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `AfterPost` is triggered when the `TDataSet.Post` (??) operation was successfully completed, and the dataset is again in `dsBrowse` state. If an error occurred during the post operation, then the `AfterPost` event is not called, but the `TDataSet.OnPostError` (??) event is triggered instead.

See also: `TDataSet.BeforePost` (??), `TDataSet.Post` (??), `TDataSet.State` (??), `TDataSet.OnPostError` (??)

### 10.20.91 TDataSet.BeforeCancel

Synopsis: Event triggered before a Cancel operation.

Declaration: `Property BeforeCancel : TDataSetNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `BeforeCancel` is triggered at the start of the `TDataSet.Cancel` (??) operation, when the state is still one of the editing states (`dsEdit,dsInsert`). The event handler can be used to abort the cancel operation: if an exception is raised during the event handler, then the cancel operation stops. If the dataset was not in one of the editing states when the `Cancel` method was called, then the event is not triggered.

See also: `TDataSet.AfterCancel` (??), `TDataSet.Cancel` (??), `TDataSet.State` (??)

### 10.20.92 TDataSet.AfterCancel

Synopsis: Event triggered after a Cancel operation.

Declaration: Property AfterCancel : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: AfterCancel is triggered when the TDataSet.Cancel (??) operation was successfully completed, and the dataset is again in dsBrowse state.

See also: TDataSet.BeforeCancel (??), TDataSet.Cancel (??), TDataSet.State (??)

### 10.20.93 TDataSet.BeforeDelete

Synopsis: Event triggered before a Delete operation.

Declaration: Property BeforeDelete : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: BeforeDelete is triggered at the start of the TDataSet.Delete (??) operation, when the dataset is still in dsBrowse state. The event handler can be used to abort the delete operation: if an exception is raised during the event handler, then the delete operation stops. The event is followed by a TDataSet.BeforeScroll (??) event. If the dataset was in insert mode when the Delete method was called, then the event will not be called, as TDataSet.Cancel (??) is called instead.

See also: TDataSet.AfterDelete (??), TDataSet.Delete (??), TDataSet.BeforeScroll (??), TDataSet.Cancel (??), TDataSet.State (??)

### 10.20.94 TDataSet.AfterDelete

Synopsis:

Declaration: Property AfterDelete : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: AfterDelete is triggered after the successful completion of the TDataSet.Delete (??) operation, when the dataset is again in dsBrowse state. The event is followed by a TDataSet.AfterScroll (??) event.

See also: TDataSet.BeforeDelete (??), TDataSet.Delete (??), TDataSet.AfterScroll (??), TDataSet.State (??)

### 10.20.95 TDataSet.BeforeScroll

Synopsis: Event triggered before the cursor changes position.

Declaration: Property BeforeScroll : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

**Description:** `BeforeScroll` is triggered before the cursor changes position. This can happen with one of the navigation methods: `TDataset.Next` (??), `TDataset.Prior` (??), `TDataset.First` (??), `TDataset.Last` (??), but also with two of the editing operations: `TDataset.Insert` (??) and `TDataset.Delete` (??). Raising an exception in this event handler aborts the operation in progress.

See also: `TDataset.AfterScroll` (??), `TDataset.Next` (??), `TDataset.Prior` (??), `TDataset.First` (??), `TDataset.Last` (??), `TDataset.Insert` (??), `TDataset.Delete` (??)

### 10.20.96 TDataSet.AfterScroll

**Synopsis:** Event triggered after the cursor has changed position.

**Declaration:** Property `AfterScroll` : `TDataSetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `AfterScroll` is triggered after the cursor has changed position. This can happen with one of the navigation methods: `TDataset.Next` (??), `TDataset.Prior` (??), `TDataset.First` (??), `TDataset.Last` (??), but also with two of the editing operations: `TDataset.Insert` (??) and `TDataset.Delete` (??) and after the dataset was opened. It is suitable for displaying status information or showing a value that needs to be calculated for each record.

See also: `TDataset.AfterScroll` (??), `TDataset.Next` (??), `TDataset.Prior` (??), `TDataset.First` (??), `TDataset.Last` (??), `TDataset.Insert` (??), `TDataset.Delete` (??), `TDataset.Open` (??)

### 10.20.97 TDataSet.BeforeRefresh

**Synopsis:** Event triggered before the data is refreshed.

**Declaration:** Property `BeforeRefresh` : `TDataSetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `BeforeRefresh` is triggered at the start of the `TDataset.Refresh` (??) method, after the dataset has been put in browse mode. If the dataset cannot be put in browse mode, the `BeforeRefresh` method will not be triggered. If an exception is raised during the `BeforeRefresh` method, then the refresh method is cancelled and the dataset remains in the `dsBrowse` state.

See also: `TDataset.Refresh` (??), `TDataset.AfterRefresh` (??), `TDataset.State` (??)

### 10.20.98 TDataSet.AfterRefresh

**Synopsis:** Event triggered after the data has been refreshed.

**Declaration:** Property `AfterRefresh` : `TDataSetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `AfterRefresh` is triggered at the end of the `TDataset.Refresh` (??) method, after the dataset has refreshed its data and is again in `dsBrowse` state. This event can be used to react on changes in data in the current record

See also: `TDataset.Refresh` (??), `TDataset.State` (??), `TDataset.BeforeRefresh` (??)

**10.20.99 TDataSet.OnCalcFields**

Synopsis: Event triggered when values for calculated fields must be computed.

Declaration: `Property OnCalcFields : TDataSetNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnCalcFields` is triggered whenever the dataset needs to (re)compute the values of any calculated fields in the dataset. It is called very often, so this event should return as quickly as possible. Only the values of the calculated fields should be set, no methods of the dataset that change the data or cursor position may be called during the execution of this event handler. The frequency with which this event is called can be controlled through the `TDataSet.AutoCalcFields` (??) property. Note that the value of lookup fields does not need to be calculated in this event, their value is computed automatically before this event is triggered.

See also: `TDataSet.AutoCalcFields` (??), `TField.Kind` (??)

**10.20.100 TDataSet.OnDeleteError**

Synopsis: Event triggered when a delete operation fails.

Declaration: `Property OnDeleteError : TDataSetErrorEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnDeleteError` is triggered when the `TDataSet.Delete` (??) method fails to delete the record in the underlying database. The event handler can be used to indicate what the response to the failed delete should be. To this end, it gets the exception object passed to it (parameter `E`), and it can examine this object to return an appropriate action in the `DataAction` parameter. The following responses are supported:

**daFail**The operation should fail (an exception will be raised)

**daAbort**The operation should be aborted (edits are undone, and an `EAbort` exception is raised)

**daRetry**Retry the operation.

For more information, see also the description of the `TDataSetErrorEvent` (221) event handler type.

See also: `TDataSetErrorEvent` (221), `TDataSet.Delete` (??), `TDataSet.OnEditError` (??), `TDataSet.OnPostError` (??)

**10.20.101 TDataSet.OnEditError**

Synopsis: Event triggered when an edit operation fails.

Declaration: `Property OnEditError : TDataSetErrorEvent`

Visibility: `public`

Access: `Read,Write`

**Description:** `OnEditError` is triggered when the `TDataset.Edit (??)` method fails to put the dataset in edit mode because the underlying database engine reported an error. The event handler can be used to indicate what the response to the failed edit operation should be. To this end, it gets the exception object passed to it (parameter `E`), and it can examine this object to return an appropriate action in the `DataAction` parameter. The following responses are supported:

**daFail**The operation should fail (an exception will be raised)

**daAbort**The operation should be aborted (edits are undone, and an `EAbort` exception is raised)

**daRetry**Retry the operation.

For more information, see also the description of the `TDatasetErrorEvent (221)` event handler type.

See also: `TDatasetErrorEvent (221)`, `TDataset.Edit (??)`, `TDataset.OnDeleteError (??)`, `TDataset.OnPostError (??)`

### 10.20.102 TDataSet.OnFilterRecord

**Synopsis:** Event triggered to filter records.

**Declaration:** `Property OnFilterRecord : TFilterRecordEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `OnFilterRecord` can be used to provide event-based filtering for datasets that support it. This event is only triggered when the `Tdataset.Filtered (??)` property is set to `True`. The event handler should set the `Accept` parameter to `True` if the current record should be accepted, or to `False` if it should be rejected. No methods that change the state of the dataset may be used during this event, and calculated fields or lookup field values are not yet available.

See also: `TDataset.Filter (??)`, `TDataset.Filtered (??)`, `TDataset.state (??)`

### 10.20.103 TDataSet.OnNewRecord

**Synopsis:** Event triggered when a new record is created.

**Declaration:** `Property OnNewRecord : TDataSetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `OnNewRecord` is triggered by the `TDataset.Append (??)` or `TDataset.Insert (??)` methods when the buffer for the new record's data has been allocated. This event can be used to set default value for some of the fields in the dataset. If an exception is raised during this event handler, the operation is cancelled and the dataset is put again in browse mode (`TDataset.State (??)` is again `dsBrowse`).

See also: `TDataset.Append (??)`, `TDataset.Insert (??)`, `TDataset.State (??)`

### 10.20.104 TDataSet.OnPostError

Synopsis: Event triggered when a post operation fails.

Declaration: Property OnPostError : TDataSetErrorEvent

Visibility: public

Access: Read,Write

Description: OnPostError is triggered when the TDataSet.Post (??) method fails to post the changes in the dataset buffer to the underlying database, because the database engine reported an error. The event handler can be used to indicate what the response to the failed post operation should be. To this end, it gets the exception object passed to it (parameter E), and it can examine this object to return an appropriate action in the DataAction parameter. The following responses are supported:

**daFail**The operation should fail (an exception will be raised)

**daAbort**The operation should be aborted (edits are undone, and an EAbort exception is raised)

**daRetry**Retry the operation.

For more information, see also the description of the TDataSetErrorEvent (221) event handler type.

See also: TDataSetErrorEvent (221), TDataSet.Post (??), TDataSet.OnDeleteError (??), TDataSet.OnEditError (??)

## 10.21 TDataSource

### 10.21.1 Description

TDataSource is a mediating component: it handles communication between any DB-Aware component (often edit controls on a form) and a TDataSet (267) instance. Any database aware component should never communicate with a dataset directly. Instead, it should communicate with a TDataSource (303) instance. The TDataSet instance will communicate with the TDataSource instance, which will notify every component attached to it. Vice versa, any component that wishes to make changes to the dataset, will notify the TDataSource instance, which will then (if needed) notify the TDataSet instance. The datasource can be disabled, in which case all communication between the dataset and the DB-Aware components is suspended until the datasource is again enabled.

See also: TDataSet (267), TDataSource (303)

### 10.21.2 Method overview

Page	Property	Description
<a href="#">304</a>	Create	Create a new instance of TDataSource
<a href="#">304</a>	Destroy	Remove a TDataSource instance from memory
<a href="#">304</a>	Edit	Put the dataset in edit mode, if needed
<a href="#">305</a>	IsLinkedTo	Check if a dataset is linked to a certain dataset



### 10.21.3 Property overview

Page	Property	Access	Description
<a href="#">305</a>	AutoEdit	rw	Should the dataset be put in edit mode automatically
<a href="#">305</a>	DataSet	rw	Dataset this datasource is connected to
<a href="#">306</a>	Enabled	rw	Enable or disable sending of events
<a href="#">306</a>	OnDataChange	rw	Called whenever data changes in the current record
<a href="#">306</a>	OnStateChange	rw	Called whenever the state of the dataset changes
<a href="#">307</a>	OnUpdateData	rw	Called whenever the data in the dataset must be updated
<a href="#">305</a>	State	r	State of the dataset

### 10.21.4 TDataSource.Create

Synopsis: Create a new instance of TDataSource

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of `TDataSource`. It simply allocates some resources and then calls the inherited constructor.

See also: `TDataSource.Destroy` (??)

### 10.21.5 TDataSource.Destroy

Synopsis: Remove a TDataSource instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` notifies all `TDataLink` ([262](#)) instances connected to it that the dataset is no longer available, and then removes itself from the `TDataLink` instance. It then cleans up all resources and calls the inherited constructor.

See also: `TDataSource.Create` (??), `TDataLink` ([262](#))

### 10.21.6 TDataSource.Edit

Synopsis: Put the dataset in edit mode, if needed

Declaration: `procedure Edit`

Visibility: `public`

Description: `Edit` will check `AutoEdit` (??): if it is `True`, then it puts the `Dataset` (??) it is connected to in edit mode, if it was in browse mode. If `AutoEdit` is `False`, then nothing happens. Application or component code that deals with GUI development should always attempt to set a dataset in edit mode through this method instead of calling `TDataset.Edit` (??) directly.

Errors: An `EDatabaseError` ([233](#)) exception can occur if the dataset is read-only or fails to set itself in edit mode. (e.g. unidirectional datasets).

See also: `TDataSource.AutoEdit` (??), `TDataset.Edit` (??), `TDataset.State` (??)

### 10.21.7 TDataSource.IsLinkedTo

Synopsis: Check if a dataset is linked to a certain dataset

Declaration: `function IsLinkedTo (ADataset: TDataSet) : Boolean`

Visibility: public

Description: `IsLinkedTo` checks if it is somehow linked to `ADataset`: it checks the `Dataset` (??) property, and returns `True` if it is the same. If not, it continues by checking any detail dataset fields that the dataset possesses (recursively). This function can be used to detect circular links in e.g. master-detail relationships.

See also: `TDataSource.Dataset` (??)

### 10.21.8 TDataSource.State

Synopsis: State of the dataset

Declaration: `Property State : TDataSetState`

Visibility: public

Access: Read

Description: `State` contains the `State` (??) of the dataset it is connected to, or `dsInactive` if the dataset property is not set or the datasource is not enabled. Components connected to a dataset through a datasource property should always check `TDataSource.State` instead of checking `TDataSet.State` (??) directly, to take into account the effect of the `Enabled` (??) property.

See also: `TDataSet.State` (??), `TDataSource.Enabled` (??)

### 10.21.9 TDataSource.AutoEdit

Synopsis: Should the dataset be put in edit mode automatically

Declaration: `Property AutoEdit : Boolean`

Visibility: published

Access: Read,Write

Description: `AutoEdit` can be set to `True` to prevent visual controls from putting the dataset in edit mode. Visual controls use the `TDataSource.Edit` (??) method to attempt to put the dataset in edit mode as soon as the user changes something. If `AutoEdit` is set to `False` then the `Edit` method does nothing. The effect is that the user must explicitly set the dataset in edit mode (by clicking some button or some other action) before the fields can be edited.

See also: `TDataSource.Edit` (??), `TDataSet.Edit` (??)

### 10.21.10 TDataSource.DataSet

Synopsis: Dataset this datasource is connected to

Declaration: `Property DataSet : TDataSet`

Visibility: published

Access: Read,Write

**Description:** `Dataset` must be set by the application programmer to the `TDataset` (267) instance for which this datasource is handling events. Setting it to `Nil` will disable all controls that are connected to this datasource instance. Once it is set and the datasource is enabled, the datasource will start sending data events to the controls or components connected to it.

See also: `TDataset` (267), `TDatasource.Enabled` (??)

### 10.21.11 `TDatasource.Enabled`

**Synopsis:** Enable or disable sending of events

**Declaration:** `Property Enabled : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `Enabled` is by default set to `True`: the datasource instance communicates events from the dataset to components connected to the datasource, and vice versa: components can interact with the dataset. If the `Enabled` property is set to `False` then no events are communicated to connected components: it is as if the dataset property was set to `Nil`. Reversely, the components cannot interact with the dataset if the `Enabled` property is set to `False`.

See also: `TDataset` (267), `TDatasource.Dataset` (??), `TDatasource.AutoEdit` (??)

### 10.21.12 `TDatasource.OnStateChange`

**Synopsis:** Called whenever the state of the dataset changes

**Declaration:** `Property OnStateChange : TNotifyEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnStateChange` is called whenever the `TDataset.State` (??) property changes, and the datasource is enabled. It can be used in application code to react to state changes: enabling or disabling non-DB-Aware controls, setting empty values etc.

See also: `TDatasource.OnUpdateData` (??), `TDatasource.OnStateChange` (??), `TDataset.State` (??), `TDatasource.Enabled` (??)

### 10.21.13 `TDatasource.OnDataChange`

**Synopsis:** Called whenever data changes in the current record

**Declaration:** `Property OnDataChange : TDataChangeEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnDataChange` is called whenever a field value changes: if the `Field` parameter is set, a single field value changed. If the `Field` parameter is `Nil`, then the whole record changed: when the dataset is opened, when the user scrolls to a new record. This event handler can be set to react to data changes: to update the contents of non-DB-aware controls for instance. The event is not called when the datasource is not enabled.

See also: `TDatasource.OnUpdateData` (??), `TDatasource.OnStateChange` (??), `TDataset.AfterScroll` (??), `TField.OnChange` (??), `TDatasource.Enabled` (??)

### 10.21.14 TDataSource.OnUpdateData

Synopsis: Called whenever the data in the dataset must be updated

Declaration: Property OnUpdateData : TNotifyEvent

Visibility: published

Access: Read,Write

Description: OnUpdateData is called whenever the dataset needs the latest data from the controls: usually just before a TDataSet.Post (??) operation. It can be used to copy data from non-db-aware controls to the dataset just before the dataset is posting the changes to the underlying database.

See also: TDataSource.OnDataChange (??), TDataSource.OnStateChange (??), TDataSet.Post (??)

## 10.22 TDateField

### 10.22.1 Description

TDateField is the class used when a dataset must manage data of type date. (TField.DataType (??) equals ftDate). It initializes some of the properties of the TField (315) class to be able to work with date fields.

It should never be necessary to create an instance of TDateField manually, a field of this class will be instantiated automatically for each date field when a dataset is opened.

See also: TDataSet (267), TField (315), TDateTimeField (307), TTimeField (396)

### 10.22.2 Method overview

Page	Property	Description
<a href="#">307</a>	Create	Create a new instance of a TDateField class.

### 10.22.3 TDateField.Create

Synopsis: Create a new instance of a TDateField class.

Declaration: constructor Create(AOwner: TComponent); Override

Visibility: public

Description: Create initializes a new instance of the TDateField class. It calls the inherited destructor, and then sets some TField (315) properties to configure the instance for working with date values.

See also: TField (315)

## 10.23 TDateTimeField

### 10.23.1 Description

TDateTimeField is the class used when a dataset must manage data of type datetime. (TField.DataType (??) equals ftDateTime). It also serves as base class for the TDateField (307) or TTimeField (396) classes. It overrides some of the properties and methods of the TField (315) class to be able to work with date/time fields.

It should never be necessary to create an instance of `TDateTimeField` manually, a field of this class will be instantiated automatically for each datetime field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TDateField` (307), `TTimeField` (396)

### 10.23.2 Method overview

Page	Property	Description
<a href="#">308</a>	Create	Create a new instance of a <code>TDateTimeField</code> class.

### 10.23.3 Property overview

Page	Property	Access	Description
<a href="#">308</a>	DisplayFormat	rw	Formatting string for textual representation of the field
<a href="#">309</a>	EditMask		Specify an edit mask for an edit control
<a href="#">308</a>	Value	rw	Contents of the field as a <code>TDateTime</code> value

### 10.23.4 TDateTimeField.Create

Synopsis: Create a new instance of a `TDateTimeField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of the `TDateTimeField` class. It calls the inherited destructor, and then sets some `TField` (315) properties to configure the instance for working with date/time values.

See also: `TField` (315)

### 10.23.5 TDateTimeField.Value

Synopsis: Contents of the field as a `TDateTime` value

Declaration: `Property Value : TDateTime`

Visibility: public

Access: Read,Write

Description: `Value` is redefined from `TField.Value` (??) by `TDateTimeField` as a `TDateTime` value. It returns the same value as the `TField.AsDateTime` (??) property.

See also: `TField.AsDateTime` (??), `TField.Value` (??)

### 10.23.6 TDateTimeField.DisplayFormat

Synopsis: Formatting string for textual representation of the field

Declaration: `Property DisplayFormat : String`

Visibility: published

Access: Read,Write

**Description:** `DisplayFormat` can be set to a formatting string that will then be used by the `TField.DisplayText` (??) property to format the value with the `DateTimeToString` (??) function.

See also: `DateTimeToString` (??), `FormatDateTime` (??), `TField.DisplayText` (??)

### 10.23.7 TDateTimeField.EditMask

**Synopsis:** Specify an edit mask for an edit control

**Declaration:** `Property EditMask :`

**Visibility:** published

**Access:**

**Description:** `EditMask` can be used to specify an edit mask for controls that allow to edit this field. It has no effect on the field value, and serves only to ensure that the user can enter only correct data for this field.

`TDateTimeField` just changes the visibility of the `EditMask` property, it is introduced in `TField`.

For more information on valid edit masks, see the documentation of the GUI controls.

See also: `TField.EditMask` (??)

## 10.24 TDBDataset

### 10.24.1 Description

`TDBDataset` is a `TDataset` descendent which introduces the concept of a database: a central component (`TDatabase` (257)) which represents a connection to a database. This central component is exposed in the `TDBDataset.Database` (??) property. When the database is no longer connected, or is no longer in memory, all `TDBDataset` instances connected to it are disabled.

`TDBDataset` also introduces the notion of a transaction, exposed in the `Transaction` (??) property.

`TDBDataset` is an abstract class, it should never be used directly.

Dataset component writers should descend their component from `TDBDataset` if they wish to introduce a central database connection component. The database connection logic will be handled automatically by `TDBDataset`.

See also: `TDatabase` (257), `TDBTransaction` (310)

### 10.24.2 Method overview

Page	Property	Description
<a href="#">310</a>	<code>destroy</code>	Remove the <code>TDBDataset</code> instance from memory.

### 10.24.3 Property overview

Page	Property	Access	Description
<a href="#">310</a>	<code>DataBase</code>	rw	Database this dataset is connected to
<a href="#">310</a>	<code>Transaction</code>	rw	Transaction in which this dataset is running.

#### 10.24.4 TDBDataset.destroy

Synopsis: Remove the `TDBDataset` instance from memory.

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` will disconnect the `TDBDataset` from its Database (??) and Transaction (??). After this it calls the inherited destructor.

See also: `TDBDataset.Database` (??), `TDatabase` (257)

#### 10.24.5 TDBDataset.DataBase

Synopsis: Database this dataset is connected to

Declaration: `Property DataBase : TDataBase`

Visibility: `public`

Access: `Read,Write`

Description: `Database` should be set to the `TDatabase` (257) instance this dataset is connected to. It can only be set when the dataset is closed.

Descendent classes should check in the property setter whether the database instance is of the correct class.

Errors: If the property is set when the dataset is active, an `EDatabaseError` (233) exception will be raised.

See also: `TDatabase` (257), `TDBDataset.Transaction` (??)

#### 10.24.6 TDBDataset.Transaction

Synopsis: Transaction in which this dataset is running.

Declaration: `Property Transaction : TDBTransaction`

Visibility: `public`

Access: `Read,Write`

Description: `Transaction` points to a `TDBTransaction` (310) component that represents the transaction this dataset is active in. This property should only be used for databases that support transactions.

The property can only be set when the dataset is disabled.

See also: `TDBTransaction` (310), `TDBDataset.Database` (??)

### 10.25 TDBTransaction

#### 10.25.1 Description

`TDBTransaction` encapsulates a SQL transaction. It is an abstract class, and should be used by component creators that wish to encapsulate transactions in a class. The `TDBTransaction` class offers functionality to refer to a `TDatabase` (257) instance, and to keep track of `TDataset` instances which are connected to the transaction.

See also: `TDatabase` (257), `TDataset` (267)

### 10.25.2 Method overview

Page	Property	Description
<a href="#">311</a>	CloseDataSets	Close all connected datasets
<a href="#">311</a>	Create	Transaction property
<a href="#">311</a>	destroy	Remove a <code>TDBTransaction</code> instance from memory.

### 10.25.3 Property overview

Page	Property	Access	Description
<a href="#">312</a>	Active	rw	Is the transaction active or not
<a href="#">312</a>	DataBase	rw	Database this transaction is connected to

### 10.25.4 TDBTransaction.Create

Synopsis: Transaction property

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new `TDBTransaction` instance. It sets up the necessary resources, after having called the inherited constructor.

See also: `TDBTransaction.Destroy` (??)

### 10.25.5 TDBTransaction.destroy

Synopsis: Remove a `TDBTransaction` instance from memory.

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` first disconnects all connected `TDBDataset` ([309](#)) instances and then cleans up the resources allocated in the `Create` (??) constructor. After that it calls the inherited destructor.

See also: `TDBTransaction.Create` (??)

### 10.25.6 TDBTransaction.CloseDataSets

Synopsis: Close all connected datasets

Declaration: `procedure CloseDataSets`

Visibility: `public`

Description: `CloseDatasets` closes all connected datasets (All `TDBDataset` ([309](#)) instances whose `Transaction` (??) property points to this `TDBTransaction` instance).

See also: `TDBDataset` ([309](#)), `TDBDataset.Transaction` (??)



### 10.25.7 TDBTransaction.DataBase

Synopsis: Database this transaction is connected to

Declaration: Property DataBase : TDataBase

Visibility: public

Access: Read,Write

Description: Database points to the database that this transaction is part of. This property can be set only when the transaction is not active.

Errors: Setting this property to a new value when the transaction is active will result in an EDatabaseError (233) exception.

See also: TDBTransaction.Active (??), TDataBase (257)

### 10.25.8 TDBTransaction.Active

Synopsis: Is the transaction active or not

Declaration: Property Active : Boolean

Visibility: published

Access: Read,Write

Description: Active is True if a transaction was started using TDBTransaction.StartTransaction (??). Reversely, setting Active to True will call StartTransaction, setting it to False will call TDBTransaction.EndTransaction (??).

See also: TDBTransaction.StartTransaction (??), TDBTransaction.EndTransaction (??)

## 10.26 TDefCollection

### 10.26.1 Description

TDefCollection is a parent class for the TFieldDefs (343) and TIndexDefs (360) collections: It holds a set of named definitions on behalf of a TDataset (267) component. To this end, it introduces a dataset (??) property, and a mechanism to notify the dataset of any updates in the collection. It is supposed to hold items of class TNamedItem (373), so the TDefCollection.Find (??) method can find items by named.

### 10.26.2 Method overview

Page	Property	Description
<a href="#">313</a>	create	Instantiate a new TDefCollection instance.
<a href="#">313</a>	Find	Find an item by name
<a href="#">313</a>	GetItemNames	Return a list of all names in the collection
<a href="#">313</a>	IndexOf	Find location of item by name

### 10.26.3 Property overview

Page	Property	Access	Description
<a href="#">314</a>	Dataset	r	Dataset this collection manages definitions for.
<a href="#">314</a>	Updated	rw	Has one of the items been changed

### 10.26.4 TDefCollection.create

Synopsis: Instantiate a new `TDefCollection` instance.

Declaration: `constructor create(ADataset: TDataSet; AOwner: TPersistent;  
AClass: TCollectionItemClass)`

Visibility: public

Description: `Create` saves the `ADataset` and `AOwner` components in local variables for later reference, and then calls the inherited `Create` with `AClass` as a parameter. `AClass` should at least be of type `TNamedItem`. `ADataset` is the dataset on whose behalf the collection is managed. `AOwner` is the owner of the collection, normally this is the form or datamodule on which the dataset is dropped.

See also: `TDataset` (267), `TNamedItem` (373)

### 10.26.5 TDefCollection.Find

Synopsis: Find an item by name

Declaration: `function Find(const AName: String) : TNamedItem`

Visibility: public

Description: `Find` searches for an item in the collection with name `AName` and returns the item if it is found. If no item with the requested name is found, `Nil` is returned. The search is performed case-insensitive.

Errors: If no item with matching name is found, `Nil` is returned.

See also: `TNamedItem.Name` (??), `TDefCollection.IndexOf` (??)

### 10.26.6 TDefCollection.GetItemNames

Synopsis: Return a list of all names in the collection

Declaration: `procedure GetItemNames(List: TStrings)`

Visibility: public

Description: `GetItemNames` fills `List` with the names of all items in the collection. It clears the list first.

Errors: If `List` is not a valid `TStrings` instance, an exception will occur.

See also: `TNamedItem.Name` (??)

### 10.26.7 TDefCollection.IndexOf

Synopsis: Find location of item by name

Declaration: `function IndexOf(const AName: String) : LongInt`

Visibility: public

Description: `IndexOf` searches in the collection for an item whose `Name` property matches `AName` and returns the index of the item if it finds one. If no item is found, -1 is returned. The search is performed case-insensitive.

See also: `TDefCollection.Find` (??), `TNamedItem.Name` (??)

### 10.26.8 TDefCollection.Dataset

Synopsis: Dataset this collection manages definitions for.

Declaration: `Property Dataset : TDataSet`

Visibility: public

Access: Read

Description: `Dataset` is the dataset this collection manages definitions for. It must be supplied when the collection is created and cannot change during the lifetime of the collection.

### 10.26.9 TDefCollection.Updated

Synopsis: Has one of the items been changed

Declaration: `Property Updated : Boolean`

Visibility: public

Access: Read,Write

Description: `Changed` indicates whether the collection has changed: an item was added or removed, or one of the properties of the items was changed.

## 10.27 TDetailDataLink

### 10.27.1 Description

`TDetailDataLink` handles the communication between a detail dataset and the master datasource in a master-detail relationship between datasets. It should never be used in an application, and should only be used by component writers that wish to provide master-detail functionality for `TDataSet` descendents.

See also: `TDataSet` ([267](#)), `TDataSource` ([303](#))

### 10.27.2 Property overview

Page	Property	Access	Description
<a href="#">314</a>	<code>DetailDataSet</code>	r	Detail dataset in Master-detail relation

### 10.27.3 TDetailDataLink.DetailDataSet

Synopsis: Detail dataset in Master-detail relation

Declaration: `Property DetailDataSet : TDataSet`

Visibility: public

Access: Read

Description: `DetailDataSet` is the detail dataset in a master-detail relationship between 2 datasets. `DetailDataSet` is always `Nil` in `TDetailDataLink` and is only filled in in descendent classes like `TMasterDataLink` ([369](#)). The master dataset is available through the regular `TDataLink.DataSource` ([??](#)) property.

See also: `TDataSet` ([267](#)), `TMasterDataLink` ([369](#)), `TDataLink.DataSource` ([??](#))

## 10.28 TField

### 10.28.1 Description

`TField` is an abstract class that defines access methods for a field in a record, controlled by a `TDataset` (267) instance. It provides methods and properties to access the contents of the field in the current record. Reading one of the `AsXXX` properties of `TField` will access the field contents and return the contents as the desired type. Writing one of the `AsXXX` properties will write a value to the buffer represented by the `TField` instance.

`TField` is an abstract class, meaning that it should never be created directly. `TDataset` instances always create one of the descendent classes of `TField`, depending on the type of the underlying data.

See also: `TDataset` (267), `TFieldDef` (339), `TFields` (345)

### 10.28.2 Method overview

Page	Property	Description
<a href="#">318</a>	<code>Assign</code>	Copy properties from one <code>TField</code> instance to another
<a href="#">319</a>	<code>AssignValue</code>	Assign value of a variant record to the field.
<a href="#">318</a>	<code>CheckTypeSize</code>	
<a href="#">319</a>	<code>Clear</code>	Clear the field contents.
<a href="#">318</a>	<code>Create</code>	Create a new <code>TField</code> instance
<a href="#">318</a>	<code>Destroy</code>	Destroy the <code>TField</code> instance
<a href="#">319</a>	<code>FocusControl</code>	Set focus to the first control connected to this field.
<a href="#">319</a>	<code>GetData</code>	Get the data from this field
<a href="#">320</a>	<code>IsBlob</code>	Is the field a BLOB field (untyped data of indeterminate size).
<a href="#">320</a>	<code>IsValidChar</code>	Check whether a character is valid input for the field
<a href="#">320</a>	<code>RefreshLookupList</code>	Refresh the lookup list
<a href="#">321</a>	<code>SetData</code>	Save the field data
<a href="#">321</a>	<code>SetFieldType</code>	Set the field data type
<a href="#">321</a>	<code>Validate</code>	Validate the data buffer



### 10.28.3 Property overview

Page	Property	Access	Description
332	Alignment	rw	Alignment for this field
322	AsBCD	rw	Access the field's contents as a BCD (Binary coded Decimal)
322	AsBoolean	rw	Access the field's contents as a Boolean value.
322	AsCurrency	rw	Access the field's contents as a Currency value.
323	AsDateTime	rw	Access the field's contents as a TDateTime value.
323	AsFloat	rw	Access the field's contents as a floating-point (Double) value.
324	AsInteger	rw	Access the field's contents as a 32-bit signed integer (longint) value.
324	AsLargeInt	rw	Access the field's contents as a 64-bit signed integer (longint) value.
323	AsLongint	rw	Access the field's contents as a 32-bit signed integer (longint) value.
324	AsString	rw	Access the field's contents as an AnsiString value.
325	AsVariant	rw	Access the field's contents as a Variant value.
325	AsWideString	rw	Access the field's contents as a WideString value.
325	AttributeSet	rw	Not used: dictionary information
326	Calculated	rw	Is the field a calculated field ?
326	CanModify	r	Can the field's contents be modified.
332	ConstraintErrorMessage	rw	Message to display if the CustomConstraint constraint is violated.
326	CurValue	r	Current value of the field
332	CustomConstraint	rw	Custom constraint for the field's value
326	DataSet	rw	Dataset this field belongs to
327	DataSet	r	Size of the field's data
327	DataType	r	The data type of the field.
333	DefaultExpression	rw	Default value for the field
333	DisplayLabel	rws	Name of the field for display purposes
327	DisplayName	r	User-readable fieldname
327	DisplayText	r	Formatted field value
333	DisplayWidth	rw	Width of the field in characters
328	EditMask	rw	Specify an edit mask for an edit control
328	EditMaskPtr	r	Alias for EditMask
333	FieldKind	rw	The kind of field.
334	FieldName	rw	Name of the field
328	FieldNo	r	Number of the field in the record
334	HasConstraints	r	Does the field have any constraints defined
334	ImportedConstraint	rw	Constraint for the field value on the level of the underlying database
334	Index	rw	Index of the field in the list of fields
329	IsIndexedField	r	Is the field an indexed field ?
329	IsNull	r	Is the field empty
335	KeyFields	rw	Key fields to use when looking up a field value.
329	Lookup	rw	Is the field a lookup field
335	LookupCache	rw	Should lookup values be cached
335	LookupDataSet	rw	Dataset with lookup values
336	LookupKeyFields	rw	Names of fields on which to perform a locate
331	LookupList	r	List of lookup values
336	LookupResultField	rw	Name of field to use as lookup value
329	NewValue	rw	The new value of the field
330	Offset	r	Offset of the field's value in the dataset buffer
331	OldValue	r	Old value of the field
338	OnChange	rw	Event triggered when the field's value has changed
338	OnGetText	rw	Event to format the field's content
338	OnSetText	rw	Event to set the field's content based on a user-formatted string
338	OnValidate	rw	Event to validate the value of a field before it is written to the data buffer

### 10.28.4 TField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(AValue: LongInt); Virtual`

Visibility: `default`

### 10.28.5 TField.Create

Synopsis: Create a new TField instance

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new TField instance and sets up initial values for the fields. TField is a component, and AOwner will be used as the owner of the TField instance. This usually will be the form or datamodule on which the dataset was placed. There should normally be no need for a programmer to create a Tfield instance manually. The TDataset.Open (??) method will create the necessary TField instances, if none had been created in the designer.

See also: TDataset.Open (??)

### 10.28.6 TField.Destroy

Synopsis: Destroy the TField instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up any structures set up by the field instance, and then calls the inherited destructor. There should be no need to call this method under normal circumstances: the dataset instance will free any TField instances it has created when the dataset was opened.

See also: TDataset.Close (??)

### 10.28.7 TField.Assign

Synopsis: Copy properties from one TField instance to another

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` is overridden by TField to copy the field value (not the field properties) from Source if it exists. If Source is Nil then the value of the field is cleared.

Errors: If Source is not a TField instance, then an exception will be raised.

See also: TField.Value (??)

### 10.28.8 TField.AssignValue

Synopsis: Assign value of a variant record to the field.

Declaration: `procedure AssignValue(const AValue: TVarRec)`

Visibility: public

Description: `AssignValue` assigns the value of a "array of const" record `AValue` (of type `TVarRec`) to the field's value. If the record contains a `TPersistent` instance, it will be used as argument for the `Assign` to the field.

The dataset must be in edit mode to execute this method.

Errors: If the `AValue` contains an unsupported value (such as a non-nil pointer) then an exception will be raised. If the dataset is not in one of the edit modes, then executing this method will raise an `EDatabaseError` (233) exception.

See also: `TField.Assign` (??), `TField.Value` (??)

### 10.28.9 TField.Clear

Synopsis: Clear the field contents.

Declaration: `procedure Clear; Virtual`

Visibility: public

Description: `Clear` clears the contents of the field. After calling this method the value of the field is `Null` and `IsNull` (??) returns `True`.

The dataset must be in edit mode to execute this method.

Errors: If the dataset is not in one of the edit modes, then executing this method will raise an `EDatabaseError` (233) exception.

See also: `TField.IsNull` (??), `TField.Value` (??)

### 10.28.10 TField.FocusControl

Synopsis: Set focus to the first control connected to this field.

Declaration: `procedure FocusControl`

Visibility: public

Description: `FocusControl` will set focus to the first control that is connected to this field.

Errors: If the control cannot receive focus, then this method will raise an exception.

See also: `TDataset.EnableControls` (??), `TDataset.DisableControls` (??)

### 10.28.11 TField.GetData

Synopsis: Get the data from this field

Declaration: `function GetData(Buffer: Pointer) : Boolean; Overload`  
`function GetData(Buffer: Pointer; NativeFormat: Boolean) : Boolean`  
`; Overload`



Visibility: public

**Description:** `GetData` is used internally by `TField` to fetch the value of the data of this field into the data buffer pointed to by `Buffer`. If it returns `False` if the field has no value (i.e. is `Null`). If the `NativeFormat` parameter is true, then date/time formats should use the `TDateTime` format. It should not be necessary to use this method, instead use the various '`AsXXX`' methods to access the data.

**Errors:** No validity checks are performed on `Buffer`: it should point to a valid memory area, and should be large enough to contain the value of the field. Failure to provide a buffer that matches these criteria will result in an exception.

See also: `TField.IsNull` (??), `TField.SetData` (??), `TField.Value` (??)

### 10.28.12 TField.IsBlob

**Synopsis:** Is the field a BLOB field (untyped data of indeterminate size).

**Declaration:** `class function IsBlob; Virtual`

Visibility: default

**Description:** `IsBlob` returns `True` if the field is one of the blob field types. The `TField` implementation returns false. Only one of the blob-type field classes override this function and let it return `True`.

**Errors:** None.

See also: `TBlobField.IsBlob` (??)

### 10.28.13 TField.IsValidChar

**Synopsis:** Check whether a character is valid input for the field

**Declaration:** `function IsValidChar(InputChar: Char) : Boolean; Virtual`

Visibility: public

**Description:** `IsValidChar` checks whether `InputChar` is a valid characters for the current field. It does this by checking whether `InputChar` is in the set of characters specified by the `TField.ValidChars` (??) property. The `ValidChars` property will be initialized to a correct set of characters by descendent classes. For instance, a numerical field will only accept numerical characters and the sign and decimal separator characters.

Descendent classes can override this method to provide custom checks. The `ValidChars` property can be set to restrict the list of valid characters to a subset of what would normally be available.

See also: `TField.ValidChars` (??)

### 10.28.14 TField.RefreshLookupList

**Synopsis:** Refresh the lookup list

**Declaration:** `procedure RefreshLookupList`

Visibility: public

**Description:** `RefreshLookupList` fills the lookup list for a lookup fields with all key, value pairs found in the lookup dataset. It will open the lookup dataset if needed. The lookup list is only used if the `TField.LookupCache` (??) property is set to `True`.

**Errors:** If the values of the various lookup properties is not correct or the lookup dataset cannot be opened, then an exception will be raised.

See also: `LookupDataset` (??), `LookupKeyFields` (??), `LookupResultField` (??)

### 10.28.15 TField.SetData

**Synopsis:** Save the field data

**Declaration:** `procedure SetData(Buffer: Pointer); Overload`  
`procedure SetData(Buffer: Pointer; NativeFormat: Boolean); Overload`

**Visibility:** public

**Description:** `SetData` saves the value of the field data in `Buffer` to the dataset internal buffer. The `Buffer` pointer should point to a memory buffer containing the data for the field in the correct format. If the `NativeFormat` parameter is true, then date/time formats should use the `TDateTime` format.

There should normally not be any need to call `SetData` directly: it is called by the various setter methods of the `AsXXX` properties of `TField`.

**Errors:** No validity checks are performed on `Buffer`: it should point to a valid memory area, and should be large enough to contain the value of the field. Failure to provide a buffer that matches these criteria will result in an exception.

See also: `TField.GetData` (??), `TField.Value` (??)

### 10.28.16 TField.SetFieldType

**Synopsis:** Set the field data type

**Declaration:** `procedure SetFieldType(AValue: TFieldType); Virtual`

**Visibility:** public

**Description:** `SetFieldType` does nothing, but it can be overridden by descendent classes to provide special handling when the field type is set.

See also: `TField.DataType` (??)

### 10.28.17 TField.Validate

**Synopsis:** Validate the data buffer

**Declaration:** `procedure Validate(Buffer: Pointer)`

**Visibility:** public

**Description:** `Validate` is called by `SetData` prior to writing the data from `Buffer` to the dataset buffer. It will call the `TField.OnValidate` (??) event handler, if one is set, to allow the application programmer to program additional checks.

See also: `TField.SetData` (??), `TField.OnValidate` (??)

### 10.28.18 TField.AsBCD

Synopsis: Access the field's contents as a BCD (Binary coded Decimal)

Declaration: `Property AsBCD : TBCD`

Visibility: `public`

Access: `Read,Write`

Description: `AsBCD` can be used to read or write the contents of the field as a BCD value (Binary Coded Decimal).

If the native type of the field is not BCD, then an attempt will be made to convert the field value from the native format to a BCD value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a BCD value, an exception may be raised.

See also: `TField.AsCurrency` (??), `TField.Value` (??)

### 10.28.19 TField.AsBoolean

Synopsis: Access the field's contents as a Boolean value.

Declaration: `Property AsBoolean : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `AsBoolean` can be used to read or write the contents of the field as a boolean value. If the native

type of the field is not Boolean, then an attempt will be made to convert the field value from the native format to a boolean value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a Boolean value (for instance a string value), an exception may be raised.

See also: `TField.Value` (??), `TField.AsInteger` (??)

### 10.28.20 TField.AsCurrency

Synopsis: Access the field's contents as a Currency value.

Declaration: `Property AsCurrency : Currency`

Visibility: `public`

Access: `Read,Write`

Description: `AsBoolean` can be used to read or write the contents of the field as a currency value. If the native

type of the field is not Boolean, then an attempt will be made to convert the field value from the native format to a currency value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a currency-compatible value (dates or string values), an exception may be raised.

See also: `TField.Value` (??), `TField.AsFloat` (??)

**10.28.21 TField.AsDateTime**

Synopsis: Access the field's contents as a TDateTime value.

Declaration: `Property AsDateTime : TDateTime`

Visibility: `public`

Access: Read,Write

Description: `AsDateTime` can be used to read or write the contents of the field as a TDateTime value (for both date and time values). If the native type of the field is not a date or time value, then an attempt will be made to convert the field value from the native format to a TDateTime value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a TDateTime-compatible value (dates or string values), an exception may be raised.

See also: `TField.Value (??)`, `TField.AsString (??)`

**10.28.22 TField.AsFloat**

Synopsis: Access the field's contents as a floating-point (Double) value.

Declaration: `Property AsFloat : Double`

Visibility: `public`

Access: Read,Write

Description: `AsFloat` can be used to read or write the contents of the field as a floating-point value (of type double, i.e. with double precision). If the native type of the field is not a floating-point value, then an attempt will be made to convert the field value from the native format to a floating-point value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a floating-point-compatible value (string values for instance), an exception may be raised.

See also: `TField.Value (??)`, `TField.AsString (??)`, `TField.AsCurrency (??)`

**10.28.23 TField.AsLongint**

Synopsis: Access the field's contents as a 32-bit signed integer (longint) value.

Declaration: `Property AsLongint : LongInt`

Visibility: `public`

Access: Read,Write

Description: `AsLongint` can be used to read or write the contents of the field as a 32-bit signed integer value (of type longint). If the native type of the field is not a longint value, then an attempt will be made to convert the field value from the native format to a longint value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a 32-bit signed integer-compatible value (string values for instance), an exception may be raised.

This is an alias for the `TField.AsInteger (??)`.

See also: `TField.Value (??)`, `TField.AsString (??)`, `TField.AsInteger (??)`

**10.28.24 TField.AsLargeInt**

Synopsis: Access the field's contents as a 64-bit signed integer (longint) value.

Declaration: `Property AsLargeInt : LargeInt`

Visibility: public

Access: Read,Write

Description: `AsLargeInt` can be used to read or write the contents of the field as a 64-bit signed integer value (of type `Int64`). If the native type of the field is not an `Int64` value, then an attempt will be made to convert the field value from the native format to an `Int64` value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a 64-bit signed integer-compatible value (string values for instance), an exception may be raised.

See also: `TField.Value` (??), `TField.AsString` (??), `TField.AsInteger` (??)

**10.28.25 TField.AsInteger**

Synopsis: Access the field's contents as a 32-bit signed integer (longint) value.

Declaration: `Property AsInteger : Integer`

Visibility: public

Access: Read,Write

Description: `AsInteger` can be used to read or write the contents of the field as a 32-bit signed integer value (of type `Integer`). If the native type of the field is not an integer value, then an attempt will be made to convert the field value from the native format to a integer value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a 32-bit signed integer-compatible value (string values for instance), an exception may be raised.

See also: `TField.Value` (??), `TField.AsString` (??), `TField.AsLongint` (??), `TField.AsInt64` (??)

**10.28.26 TField.AsString**

Synopsis: Access the field's contents as an `AnsiString` value.

Declaration: `Property AsString : String`

Visibility: public

Access: Read,Write

Description: `AsString` can be used to read or write the contents of the field as an `AnsiString` value. If the native type of the field is not an `ansistring` value, then an attempt will be made to convert the field value from the native format to a `ansistring` value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not an `ansistring`-compatible value, an exception may be raised.

See also: `TField.Value` (??), `TField.AsWideString` (??)

### 10.28.27 TField.AsWideString

Synopsis: Access the field's contents as a WideString value.

Declaration: `Property AsWideString : WideString`

Visibility: `public`

Access: Read,Write

Description: `AsWideString` can be used to read or write the contents of the field as a WideString value. If the native type of the field is not a widestring value, then an attempt will be made to convert the field value from the native format to a widestring value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a widestring-compatible value, an exception may be raised.

See also: `TField.Value (??)`, `TField.AString (??)`

### 10.28.28 TField.AsVariant

Synopsis: Access the field's contents as a Variant value.

Declaration: `Property AsVariant : variant`

Visibility: `public`

Access: Read,Write

Description: `AsVariant` can be used to read or write the contents of the field as a Variant value. If the native type of the field is not a Variant value, then an attempt will be made to convert the field value from the native format to a variant value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a variant-compatible value, an exception may be raised.

See also: `TField.Value (??)`, `TField.AString (??)`

### 10.28.29 TField.AttributeSet

Synopsis: Not used: dictionary information

Declaration: `Property AttributeSet : String`

Visibility: `public`

Access: Read,Write

Description: `AttributeSet` was used in older Delphi versions to store data dictionary information for use in data-aware controls at design time. Not used in FreePascal (or newer Delphi versions); kept for Delphi compatibility.

**10.28.30 TField.Calculated**

Synopsis: Is the field a calculated field ?

Declaration: `Property Calculated : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Calculated` is `True` if the `FieldKind` (??) is `fkCalculated`. Setting the property will result in `FieldKind` being set to `fkCalculated` (for a value of `True`) or `fkData`. This property should be considered read-only.

See also: `TField.FieldKind` (??)

**10.28.31 TField.CanModify**

Synopsis: Can the field's contents be modified.

Declaration: `Property CanModify : Boolean`

Visibility: `public`

Access: `Read`

Description: `CanModify` is `True` if the field is not read-only and the dataset allows modification.

See also: `TField.ReadOnly` (??), `TDataset.CanModify` (??)

**10.28.32 TField.CurValue**

Synopsis: Current value of the field

Declaration: `Property CurValue : Variant`

Visibility: `public`

Access: `Read`

Description: `CurValue` returns the current value of the field as a variant.

See also: `TField.Value` (??)

**10.28.33 TField.DataSet**

Synopsis: Dataset this field belongs to

Declaration: `Property DataSet : TDataset`

Visibility: `public`

Access: `Read,Write`

Description: `DataSet` contains the dataset this field belongs to. Writing this property will add the field to the list of fields of a dataset, after removing it from the list of fields of the dataset the field was previously assigned to. It should under normal circumstances never be necessary to set this property, the `TDataset` code will take care of this.

See also: `TDataset` (267), `TDataset.Fields` (??)

### 10.28.34 TField.DataSize

Synopsis: Size of the field's data

Declaration: `Property DataSize : Integer`

Visibility: `public`

Access: `Read`

Description: `DataSource` is the memory size needed to store the field's contents. This is different from the `Size` (??) property which declares a logical size for datatypes that have a variable size (such as string fields). For BLOB fields, use the `TBlobField.BlobSize` (??) property to get the size of the field's contents for the current record..

See also: `TField.Size` (??), `TBlobField.BlobSize` (??)

### 10.28.35 TField.DataType

Synopsis: The data type of the field.

Declaration: `Property DataType : TFieldType`

Visibility: `public`

Access: `Read`

Description: `DataType` indicates the type of data the field has. This property is initialized when the dataset is opened or when persistent fields are created for the dataset. Instead of checking the class type of the field, it is better to check the `DataType`, since the actual class of the `TField` instance may differ depending on the dataset.

See also: `TField.FieldKind` (??)

### 10.28.36 TField.DisplayName

Synopsis: User-readable fieldname

Declaration: `Property DisplayName : String`

Visibility: `public`

Access: `Read`

Description: `DisplayName` is the name of the field as it will be displayed to the user e.g. in grid column headers. By default it equals the `FieldName` (??) property, unless assigned another value.

The use of this property is deprecated. Use `DisplayLabel` (??) instead.

See also: `TField.FieldName` (??)

### 10.28.37 TField.DisplayText

Synopsis: Formatted field value

Declaration: `Property DisplayText : String`

Visibility: `public`

Access: `Read`



**Description:** `DisplayText` returns the field's value as it should be displayed to the user, with all necessary formatting applied. Controls that should display the value of the field should use `DisplayText` instead of the `TField.AsString (??)` property, which does not take into account any formatting.

See also: `TField.AsString (??)`

### 10.28.38 TField.EditMask

**Synopsis:** Specify an edit mask for an edit control

**Declaration:** `Property EditMask : TEditMask`

**Visibility:** public

**Access:** Read,Write

**Description:** `EditMask` can be used to specify an edit mask for controls that allow to edit this field. It has no effect on the field value, and serves only to ensure that the user can enter only correct data for this field.

For more information on valid edit masks, see the documentation of the GUI controls.

See also: `TDateTimeField.EditMask (??)`, `TStringField.EditMask (??)`

### 10.28.39 TField.EditMaskPtr

**Synopsis:** Alias for `EditMask`

**Declaration:** `Property EditMaskPtr : TEditMask`

**Visibility:** public

**Access:** Read

**Description:** `EditMaskPtr` is a read-only alias for the `EditMask (??)` property. It is not used.

See also: `TField.EditMask (??)`

### 10.28.40 TField.FieldNo

**Synopsis:** Number of the field in the record

**Declaration:** `Property FieldNo : LongInt`

**Visibility:** public

**Access:** Read

**Description:** `FieldNo` is the position of the field in the record. It is a 1-based index and is initialized when the dataset is opened or when persistent fields are created for the dataset.

See also: `TField.Index (??)`

#### 10.28.41 TField.IsIndexField

Synopsis: Is the field an indexed field ?

Declaration: `Property IsIndexField : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsIndexField` is `true` if the field is an indexed field. By default this property is `False`, descendants of `TDataset` (267) can change this to `True`.

See also: `TField.Calculated` (??)

#### 10.28.42 TField.IsNull

Synopsis: Is the field empty

Declaration: `Property IsNull : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsNull` is `True` if the field does not have a value. If the underlying data contained a value, or a value is written to it, `IsNull` will return `False`. After `TDataset.Insert` (??) is called or `Clear` (??) is called then `IsNull` will return `True`.

See also: `TField.Clear` (??), `TDataset.Insert` (??)

#### 10.28.43 TField.Lookup

Synopsis: Is the field a lookup field

Declaration: `Property Lookup : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Lookup` is `True` if the `FieldKind` (??) equals `fkLookup`, `False` otherwise. Setting the `Lookup` property will switch the `FieldKind` between the `fkLookup` and `fkData`.

See also: `TField.FieldKind` (??)

#### 10.28.44 TField.NewValue

Synopsis: The new value of the field

Declaration: `Property NewValue : Variant`

Visibility: `public`

Access: `Read,Write`

Description: `NewValue` returns the new value of the field. The FPC implementation of `TDataset` (267) does not yet support this.

See also: `TField.Value` (??), `TField.CurValue` (??)

#### 10.28.45 TField.Offset

Synopsis: Offset of the field's value in the dataset buffer

Declaration: `Property Offset : Word`

Visibility: public

Access: Read

Description: `Offset` is the location of the field's contents in the dataset memory buffer. It is read-only and initialized by the dataset when it is opened.

See also: `TField.FieldNo (??)`, `TField.Index (??)`, `TField.Datasize (??)`

#### 10.28.46 TField.Size

Synopsis: Logical size of the field

Declaration: `Property Size : Integer`

Visibility: public

Access: Read,Write

Description: `Size` is the declared size of the field for datatypes that can have variable size, such as string types, BCD types or array types. To get the size of the storage needed to store the field's content, the `DataSetSize (??)` should be used. For blob fields, the current size of the

#### 10.28.47 TField.Text

Synopsis: Text representation of the field

Declaration: `Property Text : String`

Visibility: public

Access: Read,Write

Description: `Text` can be used to retrieve or set the value of the value as a string value for editing purposes. It will trigger the `TField.OnGetText (??)` event handler if a handler was specified. For display purposes, the `TField.DisplayText (??)` property should be used. Controls that should display the value in a textual format should use `Text` whenever they must display the text for editing purposes. Inversely, when a control should save the value entered by the user, it should write the contents to the `Text` property, not the `AsString (??)` property, this will invoke the `TField.OnSetText (??)` event handler, if one is set.

See also: `TField.AsString (??)`, `TField.DisplayText (??)`, `TField.Value (??)`

#### 10.28.48 TField.ValidChars

Synopsis: Characters that are valid input for the field's content

Declaration: `Property ValidChars : TFieldChars`

Visibility: public

Access: Read

**Description:** `ValidChars` is a property that is initialized by descendent classes to contain the set of characters that can be entered in an edit control which is used to edit the field. Numerical fields will set this to a set of numerical characters, string fields will set this to all possible characters. It is possible to restrict the possible input by setting this property to a subset of all possible characters (for example, set it to all uppercase letters to allow the user to enter only uppercase characters. `TField` itself does not enforce the validity of the data when the content of the field is set, an edit control should check the validity of the user input by means of the `IsValidChar (??)` function.

See also: `TField.IsValidChar (??)`

### 10.28.49 TField.Value

**Synopsis:** Value of the field as a variant value

**Declaration:** `Property Value : variant`

**Visibility:** public

**Access:** Read, Write

**Description:** `Value` can be used to read or write the value of the field as a Variant value. When setting the value, the value will be converted to the actual type of the field as defined in the underlying data. Likewise, when reading the value property, the actual field value will be converted to a variant value. If the field does not contain a value (when `IsNull (??)` returns `True`), then `Value` will contain `Null`.

It is not recommended to use the `Value` property: it should only be used when the type of the field is unknown. If the type of the field is known, it is better to use one of the `AsXXX` properties, which will not only result in faster code, but will also avoid strange type conversions.

See also: `TField.IsNull (??)`, `TField.Text (??)`, `TField.DisplayText (??)`

### 10.28.50 TField.OldValue

**Synopsis:** Old value of the field

**Declaration:** `Property OldValue : variant`

**Visibility:** public

**Access:** Read

**Description:** `OldValue` returns the value of the field prior to an edit operation. This feature is currently not supported in FPC.

See also: `TField.Value (??)`, `TField.CurValue (??)`, `TField.NewValue (??)`

### 10.28.51 TField.LookupList

**Synopsis:** List of lookup values

**Declaration:** `Property LookupList : TLookupList`

**Visibility:** public

**Access:** Read

**Description:** `LookupList` contains the list of key, value pairs used when caching the possible lookup values for a lookup field. The list is only valid when the `LookupCache (??)` property is set to `True`. It can be refreshed using the `RefreshLookupList (??)` method.

See also: `TField.RefreshLookupList (??)`, `TField.LookupCache (??)`

**10.28.52 TField.Alignment**

Synopsis: Alignment for this field

Declaration: `Property Alignment : TAlignment`

Visibility: published

Access: Read,Write

Description: `Alignment` contains the alignment that UI controls should observe when displaying the contents of the field. Setting the property at the field level will make sure that all DB-Aware controls will display the contents of the field with the same alignment.

See also: `TField.DisplayText` (??)

**10.28.53 TField.CustomConstraint**

Synopsis: Custom constraint for the field's value

Declaration: `Property CustomConstraint : String`

Visibility: published

Access: Read,Write

Description: `CustomConstraint` may contain a constraint that will be enforced when the dataset posts it's data. It should be a SQL-like expression that results in a `True` or `False` value. Examples of valid constraints are:

```
Salary < 10000
YearsEducation < Age
```

If the constraint is not satisfied when the record is posted, then an exception will be raised with the value of `ConstraintErrorMessage` (??) as a message.

This feature is not yet implemented in FPC.

See also: `TField.ConstraintErrorMessage` (??), `TField.ImportedConstraint` (??)

**10.28.54 TField.ConstraintErrorMessage**

Synopsis: Message to display if the `CustomConstraint` constraint is violated.

Declaration: `Property ConstraintErrorMessage : String`

Visibility: published

Access: Read,Write

Description: `ConstraintErrorMessage` is the message that should be displayed when the dataset checks the constraints and the constraint in `TField.CustomConstraint` (??) is violated.

This feature is not yet implemented in FPC.

See also: `TField.CustomConstraint` (??)

### 10.28.55 TField.DefaultExpression

Synopsis: Default value for the field

Declaration: `Property DefaultExpression : String`

Visibility: published

Access: Read,Write

Description: `DefaultValue` can be set to a value that should be entered in the field whenever the `TDataset.Append (??)` or `TDataset.Insert (??)` methods are executed. It should contain a valid SQL expression that results in the correct type for the field.

This feature is not yet implemented in FPC.

See also: `TDataset.Insert (??)`, `TDataset.Append (??)`, `TDataset.CustomConstraint (??)`

### 10.28.56 TField.DisplayLabel

Synopsis: Name of the field for display purposes

Declaration: `Property DisplayLabel : String`

Visibility: published

Access: Read,Write

Description: `DisplayLabel` is the name of the field as it will be displayed to the user e.g. in grid column headers. By default it equals the `FieldName (??)` property, unless assigned another value.

See also: `TField.FieldName (??)`

### 10.28.57 TField.DisplayWidth

Synopsis: Width of the field in characters

Declaration: `Property DisplayWidth : LongInt`

Visibility: published

Access: Read,Write

Description: `DisplayWidth` is the width (in characters) that should be used by controls that display the contents of the field (such as in grids or lookup lists). It is initialized to a default value for most fields (e.g. it equals `Size (??)` for string fields) but can be modified to obtain a more appropriate value for the field's expected content.

See also: `TField.Alignment (??)`, `TField.DisplayText (??)`

### 10.28.58 TField.FieldKind

Synopsis: The kind of field.

Declaration: `Property FieldKind : TFieldKind`

Visibility: published

Access: Read,Write

Description: `FieldKind` indicates the type of the `TField` instance. Besides `TField` instances that represent fields present in the underlying data records, there can also be calculated or lookup fields. This property determines what kind of field the `TField` instance is.

**10.28.59 TField.FieldName**

Synopsis: Name of the field

Declaration: `Property FieldName : String`

Visibility: published

Access: Read,Write

Description: `FieldName` is the name of the field as it is defined in the underlying data structures (for instance the name of the field in a SQL table, DBase file, or the alias of the field if it was aliased in a SQL SELECT statement. It does not always equal the `Name` property, which is the name of the `TField` component instance. The `Name` property will generally equal the name of the dataset appended with the value of the `FieldName` property.

See also: `TFieldDef.Name` (??), `TField.Size` (??), `TField.DataType` (??)

**10.28.60 TField.HasConstraints**

Synopsis: Does the field have any constraints defined

Declaration: `Property HasConstraints : Boolean`

Visibility: published

Access: Read

Description: `HasConstraints` will contain `True` if one of the `CustomConstraint` (??) or `ImportedConstraint` (??) properties is set to a non-empty value.

See also: `CustomConstraint` (??), `ImportedConstraint` (??)

**10.28.61 TField.Index**

Synopsis: Index of the field in the list of fields

Declaration: `Property Index : LongInt`

Visibility: published

Access: Read,Write

Description: `Index` is the name of the field in the list of fields of a dataset. It is, in general, the (0-based) position of the field in the underlying data structures, but this need not always be so. The `TField.FieldNo` (??) property should be used for that.

See also: `TField.FieldNo` (??)

**10.28.62 TField.ImportedConstraint**

Synopsis: Constraint for the field value on the level of the underlying database

Declaration: `Property ImportedConstraint : String`

Visibility: published

Access: Read,Write

**Description:** `ImportedConstraint` contains any constraints that the underlying data engine imposes on the values of a field (usually in an SQL CONSTRAINT) clause. Whether this field is filled with appropriate data depends on the implementation of the `TDataset` (267) descendent.

See also: `TField.CustomConstraint` (??), `TDataset` (267), `TField.ConstraintErrorMessage` (??)

### 10.28.63 TField.KeyFields

**Synopsis:** Key fields to use when looking up a field value.

**Declaration:** `Property KeyFields : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `KeyFields` should contain a semi-colon separated list of field names from the lookupfield's dataset which will be matched to the fields enumerated in `LookupKeyFields` (??) in the dataset pointed to by the `LookupDataset` (??) property.

See also: `LookupKeyFields` (??), `LookupDataset` (??)

### 10.28.64 TField.LookupCache

**Synopsis:** Should lookup values be cached

**Declaration:** `Property LookupCache : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `LookupCache` is by default `False`. If it is set to `True` then a list of key, value pairs will be created from the `LookupKeyFields` (??) in the dataset pointed to by the `LookupDataset` (??) property. The list of key, value pairs is available through the `TField.LookupList` (??) property.

See also: `LookupKeyFields` (??), `LookupDataset` (??), `TField.LookupList` (??)

### 10.28.65 TField.LookupDataSet

**Synopsis:** Dataset with lookup values

**Declaration:** `Property LookupDataSet : TDataset`

**Visibility:** published

**Access:** Read,Write

**Description:** `LookupDataset` is used by lookup fields to fetch the field's value. The `LookupKeyFields` (??) property is used as a list of fields to locate a record in this dataset, and the value of the `LookupResultField` (??) field is then used as the value of the lookup field.

See also: `KeyFields` (??), `LookupKeyFields` (??), `LookupResultField` (??), `LookupCache` (??)



### 10.28.66 TField.LookupKeyFields

Synopsis: Names of fields on which to perform a locate

Declaration: `Property LookupKeyFields : String`

Visibility: published

Access: Read,Write

Description: `LookupKeyFields` should contain a semi-colon separated list of field names from the dataset pointed to by the `LookupDataset` (??) property. These fields will be used when locating a record corresponding to the values in the `TField.KeyFields` (??) property.

See also: `KeyFields` (??), `LookupDataset` (??), `LookupResultField` (??), `LookupCache` (??)

### 10.28.67 TField.LookupResultField

Synopsis: Name of field to use as lookup value

Declaration: `Property LookupResultField : String`

Visibility: published

Access: Read,Write

Description: `LookupResultField` contains the field name from a field in the dataset pointed to by the `LookupDataset` (??) property. The value of this field will be used as the lookup's field value when a record is found in the lookup dataset as result for the lookup field value.

See also: `KeyFields` (??), `LookupDataset` (??), `LookupKeyFields` (??), `LookupCache` (??)

### 10.28.68 TField.Origin

Synopsis: Original fieldname of the field.

Declaration: `Property Origin : String`

Visibility: published

Access: Read,Write

Description: `Origin` contains the origin of the field in the form `TableName.fieldName`. This property is filled only if the `TDataset` (267) descendent or the database engine support retrieval of this property. It can be used to automatically create update statements, together with the `TField.ProviderFlags` (??) property.

See also: `TDataset` (267), `TField.ProviderFlags` (??)

### 10.28.69 TField.ProviderFlags

Synopsis: Flags for provider or update support

Declaration: `Property ProviderFlags : TProviderFlags`

Visibility: published

Access: Read,Write

**Description:** `ProviderFlags` contains a set of flags that can be used by engines that automatically generate update SQL statements or update data packets. The various items in the set tell the engine whether the key is a key field, should be used in the where clause of an update statement or whether - in fact - it should be updated at all.

These properties should be set by the programmer so engines such as SQLDB can create correct update SQL statements whenever they need to post changes to the database. Note that to be able to set these properties in a designer, persistent fields must be created.

See also: `TField.Origin` (??)

### 10.28.70 TField.ReadOnly

**Synopsis:** Is the field read-only

**Declaration:** `Property ReadOnly : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `ReadOnly` can be set to `True` to prevent controls of writing data to the field, effectively making it a read-only field. Setting this property to `True` does not prevent the field from getting a value through code: it is just an indication for GUI controls that the field's value is considered read-only.

See also: `TFieldDef.Attributes` (??)

### 10.28.71 TField.Required

**Synopsis:** Does the field require a value

**Declaration:** `Property Required : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `Required` determines whether the field needs a value when posting the data: when a dataset posts the changed made to a record (new or existing), it will check whether all fields with the `Required` property have a value assigned to them. If not, an exception will be raised. Descendents of `TDataset` (267) will set the property to `True` when opening the dataset, depending on whether the field is required in the underlying data engine. For fields that are not required by the database engine, the programmer can still set the property to `True` if the business logic requires a field.

See also: `TDataset.Open` (??), `ReadOnly` (??), `Visible` (??)

### 10.28.72 TField.Visible

**Synopsis:** Should the field be shown in grids

**Declaration:** `Property Visible : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `Visible` can be used to hide fields from a grid when displaying data to the user. Invisible fields will by default not be shown in the grid.

See also: `TField.ReadOnly` (??), `TField.Required` (??)

**10.28.73 TField.OnChange**

Synopsis: Event triggered when the field's value has changed

Declaration: `Property OnChange : TFieldNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnChange` is triggered whenever the field's value has been changed. It is triggered only after the new contents have been written to the dataset buffer, so it can be used to react to changes in the field's content. To prevent the writing of changes to the buffer, use the `TField.OnValidate (??)` event. It is not allowed to change the state of the dataset or the contents of the field during the execution of this event handler: doing so may lead to infinite loops and other unexpected results.

See also: `TField.OnChange (??)`

**10.28.74 TField.OnGetText**

Synopsis: Event to format the field's content

Declaration: `Property OnGetText : TFieldGetTextEvent`

Visibility: published

Access: Read,Write

Description: `OnGetText` is triggered whenever the `TField.Text (??)` or `TField.DisplayText (??)` properties are read. It can be used to return a custom formatted string in the `AText` parameter which will then typically be used by a control to display the field's contents to the user. It is not allowed to change the state of the dataset or the contents of the field during the execution of this event handler.

See also: `TField.Text (??)`, `TField.DisplayText (??)`, `TField.OnSetText (??)`, `TFieldGetTextEvent (223)`

**10.28.75 TField.OnSetText**

Synopsis: Event to set the field's content based on a user-formatted string

Declaration: `Property OnSetText : TFieldSetTextEvent`

Visibility: published

Access: Read,Write

Description: `OnSetText` is called whenever the `TField.Text (??)` property is written. It can be used to set the actual value of the field based on the passed `AText` parameter. Typically, this event handler will perform the inverse operation of the `TField.OnGetText (??)` handler, if it exists.

See also: `TField.Text (??)`, `TField.OnGetText (??)`, `TFieldGetTextEvent (223)`

**10.28.76 TField.OnValidate**

Synopsis: Event to validate the value of a field before it is written to the data buffer

Declaration: `Property OnValidate : TFieldNotifyEvent`

Visibility: published

Access: Read,Write

**Description:** `OnValidate` is called prior to writing a new field value to the dataset's data buffer. It can be used to prevent writing the new value to the buffer by raising an exception in the event handler. Note that this event handler is always called, irrespective of the way the value of the field is set.

See also: `TField.Text` (??), `TField.OnGetText` (??), `TField.OnSetText` (??), `TField.OnChange` (??)

## 10.29 TFieldDef

### 10.29.1 Description

`TFieldDef` is used to describe the fields that are present in the data underlying the dataset. For each field in the underlying field, an `TFieldDef` instance is created when the dataset is opened. This class offers almost no methods, it is mainly a storage class, to store all relevant properties of fields in a record (name, data type, size, required or not, etc.)

See also: `TDataset.FieldDefs` (??), `TFieldDefs` (343)

### 10.29.2 Method overview

Page	Property	Description
<a href="#">340</a>	Assign	Assign the contents of one <code>TFieldDef</code> instance to another.
<a href="#">339</a>	Create	Constructor for <code>TFieldDef</code> .
<a href="#">340</a>	CreateField	Create <code>TField</code> instance based on definitions in current <code>TFieldDef</code> instance.
<a href="#">340</a>	Destroy	Free the <code>TFieldDef</code> instance

### 10.29.3 Property overview

Page	Property	Access	Description
<a href="#">342</a>	Attributes	rw	Additional attributes of the field.
<a href="#">342</a>	DataType	rw	Data type for the field
<a href="#">341</a>	FieldClass	r	<code>TField</code> class used for this fielddef
<a href="#">341</a>	FieldNo	r	Field number
<a href="#">341</a>	InternalCalcField	rw	Is this a definition of an internally calculated field ?
<a href="#">342</a>	Precision	rw	Precision used in BCD (Binary Coded Decimal) fields
<a href="#">341</a>	Required	rw	Is the field required ?
<a href="#">342</a>	Size	rw	Size of the buffer needed to store the data of the field

### 10.29.4 TFieldDef.Create

**Synopsis:** Constructor for `TFieldDef`.

**Declaration:** `constructor create(ACollection: TCollection);` Override  
`constructor Create(AOwner: TFieldDefs;const AName: String;`  
`ADataType: TFieldType;ASize: Integer;`  
`ARequired: Boolean;AFieldNo: LongInt);` Overload

**Visibility:** public

**Description:** `Create` is the constructor for the `TFieldDef` class.

If a simple call is used, with a single argument `ACollection`, the inherited `Create` is called and the `Field` number is set to the incremented current index.

If the more complicated call is used, with multiple arguments, then after the inherited `Create` call, the `Name` (??), `datatype` (??), `size` (??), `precision` (??), `FieldNo` (??) and the `Required` (??) property are all set according to the passed arguments.

Errors: If a duplicate name is passed, then an exception will occur.

See also: `Name` (??), `datatype` (??), `size` (??), `precision` (??), `FieldNo` (??), `Required` (??)

### 10.29.5 TFieldDef.Destroy

Synopsis: Free the `TFieldDef` instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the `TFieldDef` instance. It simply calls the inherited destructor.

See also: `TFieldDef.Create` (??)

### 10.29.6 TFieldDef.Assign

Synopsis: Assign the contents of one `TFieldDef` instance to another.

Declaration: `procedure Assign(APersistent: TPersistent); Override`

Visibility: `public`

Description: `Assign` assigns all published properties of `APersistent` to the current instance, if `APersistent` is an instance of class `TFieldDef`.

Errors: If `APersistent` is not of class `TFieldDef` (339), then an exception will be raised.

### 10.29.7 TFieldDef.CreateField

Synopsis: Create `TField` instance based on definitions in current `TFieldDef` instance.

Declaration: `function CreateField(AOwner: TComponent) : TField`

Visibility: `public`

Description: `CreateField` determines, based on the `DataType` (??) what `TField` (315) descendent it should create, and then returns a newly created instance of this class. It sets the appropriate defaults for the `Size` (??), `FieldName` (??), `FieldNo` (??), `Precision` (??), `ReadOnly` (??) and `Required` (??) properties of the newly created instance. It should nver be necessary to use this call in an end-user program, only `TDataset` descendent classes should use this call.

The newly created field is owned by the component instance passed in the `AOwner` parameter.

The `DefaultFieldClasses` (217) array is used to determine which `TField` Descendent class should be used when creating the `TField` instance, but descendents of `TDataset` may override the values in that array.

See also: `DefaultFieldClasses` (217), `TField` (315)

**10.29.8 TFieldDef.FieldClass**

Synopsis: TField class used for this fielddef

Declaration: `Property FieldClass : TFieldClass`

Visibility: public

Access: Read

Description: `FieldClass` is the class of the `TField` instance that is created by the `CreateField (??)` class. The return value is retrieved from the `TDataset` instance the `TFieldDef` instance is associated with. If there is no `TDataset` instance available, the return value is `Nil`.

See also: `TDataset` (267), `CreateField (??)`, `TField` (315)

**10.29.9 TFieldDef.FieldNo**

Synopsis: Field number

Declaration: `Property FieldNo : LongInt`

Visibility: public

Access: Read

Description: `FieldNo` is the number of the field in the data structure where the dataset contents comes from, for instance in a DBase file. If the underlying data layer does not support the concept of field number, a sequential number is assigned.

**10.29.10 TFieldDef.InternalCalcField**

Synopsis: Is this a definition of an internally calculated field ?

Declaration: `Property InternalCalcField : Boolean`

Visibility: public

Access: Read,Write

Description: `InternalCalc` is `True` if the `fielddef` instance represents an internally calculated field: for internally calculated fields, storage must be provided by the underlying data mechanism.

**10.29.11 TFieldDef.Required**

Synopsis: Is the field required ?

Declaration: `Property Required : Boolean`

Visibility: public

Access: Read,Write

Description: `Required` is set to `True` if the field requires a value when posting data to the dataset. If no value was entered, the dataset will raise an exception when the record is posted. The `Required` property is usually initialized based on the definition of the field in the underlying database. For SQL-based databases, a field declared as `NOT NULL` will result in a `Required` property of `True`.

### 10.29.12 TFieldDef.Attributes

Synopsis: Additional attributes of the field.

Declaration: `Property Attributes : TFieldAttributes`

Visibility: published

Access: Read,Write

Description: `Attributes` contain additional attributes of the field. It shares the `faRequired` attribute with the `Required` property.

See also: `TFieldDef.Required` (??)

### 10.29.13 TFieldDef.DataType

Synopsis: Data type for the field

Declaration: `Property DataType : TFieldType`

Visibility: published

Access: Read,Write

Description: `DataType` contains the data type of the field's contents. Based on this property, the `FieldClass` property determines what kind of field class must be used to represent this field.

See also: `TFieldDef.FieldClass` (??), `TFieldDef.CreateField` (??)

### 10.29.14 TFieldDef.Precision

Synopsis: Precision used in BCD (Binary Coded Decimal) fields

Declaration: `Property Precision : LongInt`

Visibility: published

Access: Read,Write

Description: `Precision` is the number of digits used in a BCD (Binary Coded Decimal) field. It is not the number of digits after the decimal separator, but the total number of digits.

See also: `TFieldDef.Size` (??)

### 10.29.15 TFieldDef.Size

Synopsis: Size of the buffer needed to store the data of the field

Declaration: `Property Size : Integer`

Visibility: published

Access: Read,Write

Description: `Size` indicates the size of the buffer needed to hold data for the field. For types with a fixed size (such as integer, word or data/time) the size can be zero: the buffer mechanism reserves automatically enough heap memory. For types which can have various sizes (blobs, string types, BCD types), the `Size` property tells the buffer mechanism how many bytes are needed to hold the data for the field.

See also: `TFieldDef.Precision` (??), `TFieldDef.DataType` (??)

## 10.30 TFieldDefs

### 10.30.1 Description

TFieldDefs is used by each TDataSet instance to keep a description of the data that it manages; for each field in a record that makes up the underlying data, the TFieldDefs instance keeps an instance of TFieldDef that describes the field's contents. For any internally calculated fields of the dataset, a TFieldDef instance is kept as well. This collection is filled by descendent classes of TDataSet as soon as the dataset is opened; it is cleared when the dataset closes. After the collection was populated, the dataset creates TField instances based on all the definitions in the collections. If persistent fields were used, the contents of the fielddefs collection is compared to the field components that are present in the dataset. If the collection contains more field definitions than Field components, these extra fields will not be available in the dataset.

See also: TFieldDef ([339](#)), TDataSet ([267](#))

### 10.30.2 Method overview

Page	Property	Description
<a href="#">343</a>	Add	Add a new field definition to the collection.
<a href="#">344</a>	AddFieldDef	Add new TFieldDef
<a href="#">344</a>	Assign	Copy all items from one dataset to another
<a href="#">343</a>	Create	Create a new instance of TFieldDefs
<a href="#">344</a>	Find	Find item by name
<a href="#">345</a>	MakeNameUnique	Create a unique field name starting from a base name
<a href="#">344</a>	Update	Force update of definitions

### 10.30.3 Property overview

Page	Property	Access	Description
<a href="#">345</a>	HiddenFields	rw	Should field instances be created for hidden fields
<a href="#">345</a>	Items	rw	Indexed access to the fielddef instances

### 10.30.4 TFieldDefs.Create

Synopsis: Create a new instance of TFieldDefs

Declaration: constructor Create (ADataset: TDataSet)

Visibility: public

Description: Create is used to create a new instance of TFieldDefs. The ADataset argument contains the dataset instance for which the collection contains the field definitions.

See also: TFieldDef ([339](#)), TDataSet ([267](#))

### 10.30.5 TFieldDefs.Add

Synopsis: Add a new field definition to the collection.

Declaration: procedure Add(const AName: String; ADataType: TFieldType; ASize: Word; ARequired: Boolean); Overload  
 procedure Add(const AName: String; ADataType: TFieldType; ASize: Word); Overload  
 procedure Add(const AName: String; ADataType: TFieldType); Overload



Visibility: public

Description: Add adds a new item to the collection and fills in the Name, DataType, Size and Required properties of the newly added item with the provided parameters.

Errors: If an item with name AName already exists in the collection, then an exception will be raised.

See also: TFieldDefs.AddFieldDef (??)

### 10.30.6 TFieldDefs.AddFieldDef

Synopsis: Add new TFieldDef

Declaration: function AddFieldDef : TFieldDef

Visibility: public

Description: AddFieldDef creates a new TFieldDef item and returns the instance.

See also: TFieldDefs.Add (??)

### 10.30.7 TFieldDefs.Assign

Synopsis: Copy all items from one dataset to another

Declaration: procedure Assign(FieldDefs: TFieldDefs); Overload

Visibility: public

Description: Assign simply calls inherited Assign with the FieldDefs argument.

See also: TFieldDef.Assign (??)

### 10.30.8 TFieldDefs.Find

Synopsis: Find item by name

Declaration: function Find(const AName: String) : TFieldDef

Visibility: public

Description: Find simply calls the inherited TDefCollection.Find (??) to find an item with name AName and typecasts the result to TFieldDef.

See also: TDefCollection.Find (??), TNamedItem.Name (??)

### 10.30.9 TFieldDefs.Update

Synopsis: Force update of definitions

Declaration: procedure Update; Overload

Visibility: public

Description: Update notifies the dataset that the field definitions are updated, if it was not yet notified.

See also: TDefCollection.Updated (??)

### 10.30.10 TFieldDefs.MakeNameUnique

Synopsis: Create a unique field name starting from a base name

Declaration: `function MakeNameUnique(const AName: String) : String; Virtual`

Visibility: public

Description: `MakeNameUnique` uses `AName` to construct a name of a field that is not yet in the collection. If `AName` is not yet in the collection, then `AName` is returned. If a field definition with field name equal to `AName` already exists, then a new name is constructed by appending a sequence number to `AName` till the resulting name does not appear in the list of field definitions.

See also: `TFieldDefs.Find` (??), `TFieldDef.Name` (??)

### 10.30.11 TFieldDefs.HiddenFields

Synopsis: Should field instances be created for hidden fields

Declaration: `Property HiddenFields : Boolean`

Visibility: public

Access: Read,Write

Description: `HiddenFields` determines whether a field is created for fielddefs that have the `faHiddenCol` attribute set. If set to `False` (the default) then no `TField` instances will be created for hidden fields. If it is set to `True`, then a `TField` instance will be created for hidden fields.

See also: `TFieldDef.Attributes` (??)

### 10.30.12 TFieldDefs.Items

Synopsis: Indexed access to the fielddef instances

Declaration: `Property Items[Index: LongInt]: TFieldDef; default`

Visibility: public

Access: Read,Write

Description: `Items` provides zero-based indexed access to all `TFieldDef` instances in the collection. The index must vary between 0 and `Count-1`, or an exception will be raised.

See also: `TFieldDef` (339)

## 10.31 Tfields

### 10.31.1 Description

`TFields` mimics a `TCollection` class for the `Fields` (??) property of `TDataset` (267) instance. Since `TField` (315) is a descendent of `TComponent`, it cannot be an item of a collection, and must be managed by another class.

See also: `TField` (315), `TDataset` (267), `TDataset.Fields` (??)

### 10.31.2 Method overview

Page	Property	Description
<a href="#">346</a>	Add	Add a new field to the list
<a href="#">347</a>	CheckFieldName	Check field name for duplicate entries
<a href="#">347</a>	CheckFieldNames	Check a list of field names for duplicate entries
<a href="#">347</a>	Clear	Clear the list of fields
<a href="#">346</a>	Create	Create a new instance of TFields
<a href="#">346</a>	Destroy	Free the TFields instance
<a href="#">348</a>	FieldByName	Find a field based on its name
<a href="#">348</a>	FieldByNumber	Search field based on its fieldnumber
<a href="#">348</a>	FindField	Find a field based on its name
<a href="#">348</a>	GetEnumerator	Return an enumerator for the <code>for..in</code> construct
<a href="#">349</a>	GetFieldNames	Get the list of fieldnames
<a href="#">349</a>	IndexOf	Return the index of a field instance
<a href="#">349</a>	Remove	Remove an instance from the list

### 10.31.3 Property overview

Page	Property	Access	Description
<a href="#">349</a>	Count	r	Number of fields in the list
<a href="#">350</a>	Dataset	r	Dataset the fields belong to
<a href="#">350</a>	Fields	rw	Indexed access to the fields in the list

### 10.31.4 Tfields.Create

Synopsis: Create a new instance of TFields

Declaration: `constructor Create (ADataset: TDataSet)`

Visibility: `public`

Description: `Create` initializes a new instance of `TFields`. It stores the `ADataset` parameter, so it can be retrieved at any time in the `TFields.Dataset (??)` property, and initializes an internal list object to store the list of fields.

See also: `TDataSet (267)`, `TFields.Dataset (??)`, `TField (315)`

### 10.31.5 Tfields.Destroy

Synopsis: Free the TFields instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the field instances that it manages on behalf of the `Dataset (??)`. After that it cleans up the internal structures and then calls the inherited destructor.

See also: `TDataSet (267)`, `TField (315)`, `TFields.Clear (??)`

### 10.31.6 Tfields.Add

Synopsis: Add a new field to the list

Declaration: `procedure Add (Field: TField)`

Visibility: public

Description: Add must be used to add a new TField (315) instance to the list of fields. After a TField instance is added to the list, the TFields instance will free the field instance if it is cleared.

See also: TField (315), TFields.Clear (??)

### 10.31.7 Tfields.CheckFieldName

Synopsis: Check field name for duplicate entries

Declaration: `procedure CheckFieldName(const Value: String)`

Visibility: public

Description: CheckFieldName checks whether a field with name equal to Value (case insensitive) already appears in the list of fields (using TFields.Find (??)). If it does, then an EDatabaseError (233) exception is raised.

See also: TField.FieldName (??), TFields.Find (??)

### 10.31.8 Tfields.CheckFieldNames

Synopsis: Check a list of field names for duplicate entries

Declaration: `procedure CheckFieldNames(const Value: String)`

Visibility: public

Description: CheckFieldNames splits Value in a list of fieldnames, using semicolon as a separator. For each of the fieldnames obtained in this way, it calls CheckFieldName (??).

Errors: Spaces are not discarded, so leaving a space after or before a fieldname will not find the fieldname, and will yield a false negative result.

See also: TField.FieldName (??), TFields.CheckFieldName (??), TFields.Find (??)

### 10.31.9 Tfields.Clear

Synopsis: Clear the list of fields

Declaration: `procedure Clear`

Visibility: public

Description: Clear removes all TField (315) var instances from the list. All field instances are freed after they have been removed from the list.

See also: TField (315)

**10.31.10 Tfields.FindField**

Synopsis: Find a field based on its name

Declaration: `function FindField(const Value: String) : TField`

Visibility: public

Description: `FindField` searches the list of fields and returns the field instance whose `FieldName` (??) property matches `Value`. The search is performed case-insensitively. If no field instance is found, then `Nil` is returned.

See also: `TFields.FieldName` (??)

**10.31.11 Tfields.FieldByName**

Synopsis: Find a field based on its name

Declaration: `function FieldByName(const Value: String) : TField`

Visibility: public

Description: `Fieldbyname` searches the list of fields and returns the field instance whose `FieldName` (??) property matches `Value`. The search is performed case-insensitively.

Errors: If no field instance is found, then an exception is raised. If this behaviour is undesired, use `TField.FindField` (??), where `Nil` is returned if no match is found.

See also: `TFields.FindField` (??), `TFields.FieldName` (??), `TFields.FieldByNumber` (??), `TFields.IndexOf` (??)

**10.31.12 Tfields.FieldByNumber**

Synopsis: Search field based on its fieldnumber

Declaration: `function FieldByNumber(FieldNo: Integer) : TField`

Visibility: public

Description: `FieldByNumber` searches for the field whose `TField.FieldNo` (??) property matches the `FieldNo` parameter. If no such field is found, `Nil` is returned.

See also: `TFields.FieldByName` (??), `TFields.FindField` (??), `TFields.IndexOf` (??)

**10.31.13 Tfields.GetEnumerator**

Synopsis: Return an enumerator for the `for..in` construct

Declaration: `function GetEnumerator : TFieldsEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of `IEnumerable` and returns an instance of `TFieldsEnumerator` (350)

See also: `TFieldsEnumerator` (350), `#rtl.system.IEnumerable` (??)

#### 10.31.14 Tfields.GetFieldNames

Synopsis: Get the list of fieldnames

Declaration: `procedure GetFieldNames(Values: TStrings)`

Visibility: public

Description: `GetFieldNames` fills `Values` with the fieldnames of all the fields in the list, each item in the list contains 1 fieldname. The list is cleared prior to filling it.

See also: `TField.FieldName` (??)

#### 10.31.15 Tfields.IndexOf

Synopsis: Return the index of a field instance

Declaration: `function IndexOf(Field: TField) : LongInt`

Visibility: public

Description: `IndexOf` scans the list of fields and returns the index of the field instance in the list (it compares actual field instances, not field names). If the field does not appear in the list, -1 is returned.

See also: `TFields.FieldName` (??), `TFields.FieldByNumber` (??), `TFields.FindField` (??)

#### 10.31.16 Tfields.Remove

Synopsis: Remove an instance from the list

Declaration: `procedure Remove(Value: TField)`

Visibility: public

Description: `Remove` removes the field `Value` from the list. It does not free the field after it was removed. If the field is not in the list, then nothing happens.

See also: `TFields.Clear` (??)

#### 10.31.17 Tfields.Count

Synopsis: Number of fields in the list

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` is the number of fields in the fieldlist. The items in the `Fields` (??) property are numbered from 0 to `Count-1`.

See also: `TFields.fields` (??)

### 10.31.18 Tfields.Dataset

Synopsis: Dataset the fields belong to

Declaration: `Property Dataset : TDataSet`

Visibility: `public`

Access: `Read`

Description: `Dataset` is the dataset instance that owns the fieldlist. It is set when the `TFields` (345) instance is created. This property is purely for informational purposes. When adding fields to the list, no check is performed whether the field's `Dataset` property matches this dataset.

See also: `TFields.Create` (??), `TField.Dataset` (??), `TDataSet` (267)

### 10.31.19 Tfields.Fields

Synopsis: Indexed access to the fields in the list

Declaration: `Property Fields[Index: Integer]: TField; default`

Visibility: `public`

Access: `Read,Write`

Description: `Fields` is the default property of the `TFields` class. It provides indexed access to the fields in the list: the index runs from 0 to `Count-1`.

Errors: Providing an index outside the allowed range will result in an `EListError` exception.

See also: `TFields.FieldName` (??)

## 10.32 TFieldsEnumerator

### 10.32.1 Description

`TFieldsEnumerator` implements all the methods of `IEnumerator` so a `TFields` (345) instance can be used in a `for..in` construct. `TFieldsEnumerator` returns all the fields in the `TFields` collection. Therefor the following construct is possible:

```
Var
  F : TField;

begin
  // ...
  For F in MyDataset.Fields do
    begin
      // F is of type TField.
    end;
  // ...
```

Do not create an instance of `TFieldsEnumerator` manually. The compiler will do all that is needed when it encounters the `for..in` construct.

See also: `TField` (315), `TFields` (345), `#rtl.system.IEnumerator` (??)

**10.32.2 Method overview**

Page	Property	Description
<a href="#">351</a>	Create	Create a new instance of <code>TFieldsEnumerator</code> .
<a href="#">351</a>	MoveNext	Move the current field to the next field in the collection.

**10.32.3 Property overview**

Page	Property	Access	Description
<a href="#">351</a>	Current	r	Return the current field

**10.32.4 TFieldsEnumerator.Create**

Synopsis: Create a new instance of `TFieldsEnumerator`.

Declaration: `constructor Create(AFields: TFields)`

Visibility: `public`

Description: `Create` instantiates a new instance of `TFieldsEnumerator`. It stores the `AFields` reference, pointing to the `TFields` ([345](#)) instance that created the enumerator. It initializes the enumerator position.

**10.32.5 TFieldsEnumerator.MoveNext**

Synopsis: Move the current field to the next field in the collection.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` moves the internal pointer to the next field in the fields collection, and returns `True` if the operation was a success. If no more fields are available, then `False` is returned.

See also: `TFieldsEnumerator.Current` ([??](#))

**10.32.6 TFieldsEnumerator.Current**

Synopsis: Return the current field

Declaration: `Property Current : TField`

Visibility: `public`

Access: `Read`

Description: `Current` returns the current field. It will return a non-nil value only after `MoveNext` returned `True`.

See also: `TFieldsEnumerator.MoveNext` ([??](#))



## 10.33 TFloatField

### 10.33.1 Description

TFloatField is the class created when a dataset must manage floating point values of double precision. It exposes a few new properties such as Currency (??), MaxValue (??), MinValue (??) and overrides some TField (315) methods to work with floating point data.

It should never be necessary to create an instance of TFloatField manually, a field of this class will be instantiated automatically for each floating-point field when a dataset is opened.

See also: Currency (??), MaxValue (??), MinValue (??)

### 10.33.2 Method overview

Page	Property	Description
<a href="#">352</a>	CheckRange	Check whether a value is in the allowed range of values for the field
<a href="#">352</a>	Create	Create a new instance of the TFloatField

### 10.33.3 Property overview

Page	Property	Access	Description
<a href="#">353</a>	Currency	rw	Is the field a currency field.
<a href="#">353</a>	MaxValue	rw	Maximum value for the field
<a href="#">354</a>	MinValue	rw	Minimum value for the field
<a href="#">354</a>	Precision	rw	Precision (number of digits) of the field in text representations
<a href="#">353</a>	Value	rw	Value of the field as a double type

### 10.33.4 TFloatField.Create

Synopsis: Create a new instance of the TFloatField

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: Create initializes a new instance of TFloatField. It calls the inherited constructor and then initializes some properties.

### 10.33.5 TFloatField.CheckRange

Synopsis: Check whether a value is in the allowed range of values for the field

Declaration: `function CheckRange(AValue: Double) : Boolean`

Visibility: public

Description: CheckRange returns True if AValue lies within the range defined by the MinValue (??) and MaxValue (??) properties. If the value lies outside of the allowed range, then False is returned.

See also: MaxValue (??), MinValue (??)

### 10.33.6 TFloatField.Value

Synopsis: Value of the field as a double type

Declaration: `Property Value : Double`

Visibility: `public`

Access: `Read,Write`

Description: `Value` is redefined by `TFloatField` to return a value of type `Double`. It returns the same value as `TField.AsFloat (??)`

See also: `TField.AsFloat (??)`, `TField.Value (??)`

### 10.33.7 TFloatField.Currency

Synopsis: Is the field a currency field.

Declaration: `Property Currency : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `Currency` can be set to `True` to indicate that the field contains data representing an amount of currency. This affects the way the `TField.DisplayText (??)` and `TField.Text (??)` properties format the value of the field: if the `Currency` property is `True`, then these properties will format the value as a currency value (generally appending the currency sign) and if the `Currency` property is `False`, then they will format it as a normal floating-point value.

See also: `TField.DisplayText (??)`, `TField.Text (??)`, `TNumericField.DisplayFormat (??)`, `TNumericField.EditFormat (??)`

### 10.33.8 TFloatField.MaxValue

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : Double`

Visibility: `published`

Access: `Read,Write`

Description: `MaxValue` can be set to a value different from zero, it is then the maximum value for the field if set to any value different from zero. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals 0, i.e. any floating-point value is allowed.

If `MaxValue` is set, `MinValue (??)` should also be set, because it will also be checked.

See also: `TFloatField.MinValue (??)`

### 10.33.9 TFloatField.MinValue

Synopsis: Minimum value for the field

Declaration: `Property MinValue : Double`

Visibility: published

Access: Read,Write

Description: `MinValue` can be set to a value different from zero, then it is the minimum value for the field.

When setting the field's value, the value may not be less than `MinValue`. Any attempt to write a smaller value as the field's content will result in an exception. By default `MinValue` equals 0, i.e. any floating-point value is allowed.

If `MinValue` is set, `MaxValue` (??) should also be set, because it will also be checked.

See also: `TFloatField.MaxValue` (??), `TFloatField.CheckRange` (??)

### 10.33.10 TFloatField.Precision

Synopsis: Precision (number of digits) of the field in text representations

Declaration: `Property Precision : LongInt`

Visibility: published

Access: Read,Write

Description: `Precision` is the maximum number of digits that should be used when the field is converted to a textual representation in `TField.Displaytext` (??) or `TField.Text` (??), it is used in the arguments to `FormatFloat` (??).

See also: `TField.Displaytext` (??), `TField.Text` (??), `FormatFloat` (??)

## 10.34 TFMTBCDField

### 10.34.1 Method overview

Page	Property	Description
<a href="#">355</a>	<code>CheckRange</code>	
<a href="#">355</a>	<code>CheckTypeSize</code>	
<a href="#">355</a>	<code>Create</code>	

### 10.34.2 Property overview

Page	Property	Access	Description
<a href="#">355</a>	<code>Currency</code>	rw	
<a href="#">355</a>	<code>MaxValue</code>	rw	
<a href="#">355</a>	<code>MinValue</code>	rw	
<a href="#">355</a>	<code>Precision</code>	rw	
<a href="#">356</a>	<code>Size</code>		
<a href="#">355</a>	<code>Value</code>	rw	

### 10.34.3 TFMTBCDField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(AValue: LongInt);` Override

Visibility: default

### 10.34.4 TFMTBCDField.Create

Declaration: `constructor Create(AOwner: TComponent);` Override

Visibility: public

### 10.34.5 TFMTBCDField.CheckRange

Declaration: `function CheckRange(AValue: TBCD) : Boolean`

Visibility: public

### 10.34.6 TFMTBCDField.Value

Declaration: `Property Value : TBCD`

Visibility: public

Access: Read,Write

### 10.34.7 TFMTBCDField.Precision

Declaration: `Property Precision : LongInt`

Visibility: published

Access: Read,Write

### 10.34.8 TFMTBCDField.Currency

Declaration: `Property Currency : Boolean`

Visibility: published

Access: Read,Write

### 10.34.9 TFMTBCDField.MaxValue

Declaration: `Property MaxValue : String`

Visibility: published

Access: Read,Write

### 10.34.10 TFMTBCDField.MinValue

Declaration: `Property MinValue : String`

Visibility: published

Access: Read,Write

### 10.34.11 TFMTBCDField.Size

Declaration: `Property Size :`

Visibility: `published`

Access:

## 10.35 TGraphicField

### 10.35.1 Description

`TGraphicField` is the class used when a dataset must manage graphical BLOB data. (`TField.DataType` (??) equals `ftGraphic`). It initializes some of the properties of the `TField` (315) class. All methods to be able to work with graphical BLOB data have been implemented in the `TBlobField` (243) parent class.

It should never be necessary to create an instance of `TGraphicsField` manually, a field of this class will be instantiated automatically for each graphical BLOB field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TBLOBField` (243), `TMemoField` (372), `TWideMemoField` (398)

### 10.35.2 Method overview

Page	Property	Description
<a href="#">356</a>	<code>Create</code>	Create a new instance of the <code>TGraphicField</code> class

### 10.35.3 TGraphicField.Create

Synopsis: Create a new instance of the `TGraphicField` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TGraphicField` class. It calls the inherited destructor, and then sets some `TField` (315) properties to configure the instance for working with graphical BLOB values.

See also: `TField` (315)

## 10.36 TGUIDField

### 10.36.1 Description

`TGUIDField` is the class used when a dataset must manage native variant-typed data. (`TField.DataType` (??) equals `ftGUID`). It initializes some of the properties of the `TField` (315) class and overrides some of its methods to be able to work with variant data. It also adds a method to retrieve the field value as a native `TGUID` type.

It should never be necessary to create an instance of `TGUIDField` manually, a field of this class will be instantiated automatically for each GUID field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TGUIDField.AsGuid` (??)

### 10.36.2 Method overview

Page	Property	Description
<a href="#">357</a>	CheckTypeSize	
<a href="#">357</a>	Create	Create a new instance of the TGUIDField class

### 10.36.3 Property overview

Page	Property	Access	Description
<a href="#">357</a>	AsGuid	rw	Field content as a GUID value

### 10.36.4 TGUIDField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(AValue: LongInt); Override`

Visibility: default

### 10.36.5 TGUIDField.Create

Synopsis: Create a new instance of the TGUIDField class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: Create initializes a new instance of the TGUIDField class. It calls the inherited destructor, and then sets some TField ([315](#)) properties to configure the instance for working with GUID values.

See also: TField ([315](#))

### 10.36.6 TGUIDField.AsGuid

Synopsis: Field content as a GUID value

Declaration: `Property AsGuid : TGUID`

Visibility: public

Access: Read,Write

Description: AsGUID can be used to get or set the field's content as a value of type TGUID.

See also: TField.AsString (??)

## 10.37 TIndexDef

### 10.37.1 Description

TIndexDef describes one index in a set of indexes of a TDataset ([267](#)) instance. The collection of indexes is descibed by the TIndexDefs ([360](#)) class. It just has the necessary properties to describe an index, but does not implement any functionality to maintain an index.

See also: TIndexDefs ([360](#))

### 10.37.2 Method overview

Page	Property	Description
<a href="#">358</a>	Create	Create a new index definition
<a href="#">358</a>	Destroy	Remove the index from memory

### 10.37.3 Property overview

Page	Property	Access	Description
<a href="#">359</a>	CaseInsFields	rw	Fields in field list that are ordered case-insensitively
<a href="#">359</a>	DescFields	rw	Fields in field list that are ordered descending
<a href="#">358</a>	Expression	rw	Expression that makes up the index values
<a href="#">359</a>	Fields	rw	Fields making up the index
<a href="#">360</a>	Options	rw	Index options
<a href="#">360</a>	Source	rw	Source of the index

### 10.37.4 TIndexDef.Create

Synopsis: Create a new index definition

Declaration: `constructor Create(Owner: TIndexDefs; const AName: String;  
const TheFields: String; TheOptions: TIndexOptions)  
; Overload`

Visibility: public

Description: `Create` initializes a new `TIndexDef` ([357](#)) instance with the `AName` value as the index name, `AField` as the fields making up the index, and `TheOptions` as the options. `Owner` should be the `TIndexDefs` ([360](#)) instance to which the new `TIndexDef` can be added.

Errors: If an index with name `AName` already exists in the collection, an exception will be raised.

See also: `TIndexDefs` ([360](#)), `TIndexDef.Options` ([??](#)), `TIndexDef.Fields` ([??](#))

### 10.37.5 TIndexDef.Destroy

Synopsis: Remove the index from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` calls the inherited destructor, and removes the item from memory.

See also: `TIndexDef.Create` ([??](#))

### 10.37.6 TIndexDef.Expression

Synopsis: Expression that makes up the index values

Declaration: `Property Expression : String`

Visibility: public

Access: Read, Write

**Description:** `Expression` is an SQL expression based on which the index values are computed. It is only used when `ixExpression` is in `TIndexDef.Options` (??)

See also: `TIndexDef.Options` (??), `TindexDef.Fields` (??)

### 10.37.7 TIndexDef.Fields

**Synopsis:** Fields making up the index

**Declaration:** `Property Fields : String`

**Visibility:** public

**Access:** Read,Write

**Description:** `Fields` is a list of fieldnames, separated by semicolons: the fields that make up the index, in case the index is not based on an expression. The list contains the names of all fields, regardless of whether the sort order for a particular field is ascending or descending. The fields should be in the right order, i.e. the first field is sorted on first, and so on.

The `TIndexDef.DescFields` (??) property can be used to determine the fields in the list that have a descending sort order. The `TIndexDef.CaseInsFields` (??) property determines which fields are sorted in a case-insensitive manner.

See also: `TIndexDef.DescFields` (??), `TIndexDef.CaseInsFields` (??), `TIndexDef.Expression` (??)

### 10.37.8 TIndexDef.CaseInsFields

**Synopsis:** Fields in field list that are ordered case-insensitively

**Declaration:** `Property CaseInsFields : String`

**Visibility:** public

**Access:** Read,Write

**Description:** `CaseInsFields` is a list of fieldnames, separated by semicolons. It contains the names of the fields in the `Fields` (??) property which are ordered in a case-insensitive manner. `CaseInsFields` may not contain fieldnames that do not appear in `Fields`.

See also: `TIndexDef.Fields` (??), `TIndexDef.Expression` (??), `TIndexDef.DescFields` (??)

### 10.37.9 TIndexDef.DescFields

**Synopsis:** Fields in field list that are ordered descending

**Declaration:** `Property DescFields : String`

**Visibility:** public

**Access:** Read,Write

**Description:** `DescFields` is a list of fieldnames, separated by semicolons. It contains the names of the fields in the `Fields` (??) property which are ordered in a descending manner. `DescFields` may not contain fieldnames that do not appear in `Fields`.

See also: `TIndexDef.Fields` (??), `TIndexDef.Expression` (??), `TIndexDef.DescFields` (??)



### 10.37.10 TIndexDef.Options

Synopsis: Index options

Declaration: `Property Options : TIndexOptions`

Visibility: public

Access: Read,Write

Description: `Options` describes the various properties of the index. This is usually filled by the dataset that provides the index definitions. For datasets that provide In-memory indexes, this should be set prior to creating the index: it cannot be changed once the index is created.

See the description of `TIndexOption` ([227](#)) for more information on the various available options.

See also: `TIndexOptions` ([227](#))

### 10.37.11 TIndexDef.Source

Synopsis: Source of the index

Declaration: `Property Source : String`

Visibility: public

Access: Read,Write

Description: `Source` describes where the index comes from. This is a property for the convenience of the various datasets that provide indexes: they can use it to describe the source of the index.

## 10.38 TIndexDefs

### 10.38.1 Description

`TIndexDefs` is used to keep a collection of index (sort order) definitions. It can be used by classes that provide in-memory or on-disk indexes to provide a list of available indexes.

See also: `TIndexDef` ([357](#)), `TIndexDefs.Items` (??)

### 10.38.2 Method overview

Page	Property	Description
<a href="#">361</a>	<code>Add</code>	Add a new index definition with given name and options
<a href="#">361</a>	<code>AddIndexDef</code>	Add a new, empty, index definition
<a href="#">361</a>	<code>Create</code>	Create a new <code>TIndexDefs</code> instance
<a href="#">361</a>	<code>Destroy</code>	Remove the indexdefs from memory.
<a href="#">362</a>	<code>Find</code>	Find an index by name
<a href="#">362</a>	<code>FindIndexForFields</code>	Find index definition based on field names
<a href="#">362</a>	<code>GetIndexForFields</code>	Get index definition based on field names
<a href="#">362</a>	<code>Update</code>	Called whenever one of the items changes

### 10.38.3 Property overview

Page	Property	Access	Description
<a href="#">363</a>	<code>Items</code>	rw	Indexed access to the index definitions

### 10.38.4 TIndexDefs.Create

Synopsis: Create a new TIndexDefs instance

Declaration: `constructor Create(ADataset: TDataSet); Virtual; Overload`

Visibility: public

Description: `Create` initializes a new instance of the TIndexDefs class. It simply calls the inherited destructor with the appropriate item class, TIndexDef (357).

See also: TIndexDef (357), TIndexDefs.Destroy (??)

### 10.38.5 TIndexDefs.Destroy

Synopsis: Remove the indexdefs from memory.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` removes the indexdefs from memory. If the TIndexDefs instance is created by a TDataSet (267) instance, the dataset instance will also destroy it.

See also: TIndexDefs.Create (??)

### 10.38.6 TIndexDefs.Add

Synopsis: Add a new index definition with given name and options

Declaration: `procedure Add(const Name: String; const Fields: String;  
Options: TIndexOptions)`

Visibility: public

Description: `Add` adds a new TIndexDef (357) instance to the list of indexes. It initializes the index definition properties `Name`, `Fields` and `Options` with the values given in the parameters with the same names.

Errors: If an index with the same `Name` already exists in the list of indexes, an exception will be raised.

See also: TIndexDef (357), TNamedItem.Name (??), TIndexDef.Fields (??), TIndexDef.Options (??), TIndexDefs.AddIndexDef (??)

### 10.38.7 TIndexDefs.AddIndexDef

Synopsis: Add a new, empty, index definition

Declaration: `function AddIndexDef : TIndexDef`

Visibility: public

Description: `AddIndexDef` adds a new TIndexDef (357) instance to the list of indexes, and returns the newly created instance. It does not initialize any of the properties of the new index definition.

See also: TIndexDefs.Add (??)

### 10.38.8 TIndexDefs.Find

Synopsis: Find an index by name

Declaration: `function Find(const IndexName: String) : TIndexDef`

Visibility: public

Description: `Find` overloads the `TDefCollection.Find` (??) method to search and return a `TIndexDef` (357) instance based on the name. The search is case-insensitive and returns `Nil` if no matching index definition was found.

See also: `TIndexDef` (357), `TDefCollection.Find` (??), `TIndexDefs.FindIndexForFields` (??)

### 10.38.9 TIndexDefs.FindIndexForFields

Synopsis: Find index definition based on field names

Declaration: `function FindIndexForFields(const Fields: String) : TIndexDef`

Visibility: public

Description: `FindIndexForFields` searches in the list of indexes for an index whose `TIndexDef.Fields` (??) property matches the list of fields in `Fields`. If it finds an index definition, then it returns the found instance.

Errors: If no matching definition is found, an exception is raised. This is different from other `Find` functionality, where `Find` usually returns `Nil` if nothing is found.

See also: `TIndexDef` (357), `TIndexDefs.Find` (??), `TIndexDefs.GetIndexForFields` (??)

### 10.38.10 TIndexDefs.GetIndexForFields

Synopsis: Get index definition based on field names

Declaration: `function GetIndexForFields(const Fields: String;  
CaseInsensitive: Boolean) : TIndexDef`

Visibility: public

Description: `GetIndexForFields` searches in the list of indexes for an index whose `TIndexDef.Fields` (??) property matches the list of fields in `Fields`. If `CaseInsensitive` is `True` it only searches for case-sensitive indexes. If it finds an index definition, then it returns the found instance. If it does not find a matching definition, `Nil` is returned.

See also: `TIndexDef` (357), `TIndexDefs.Find` (??), `TIndexDefs.FindIndexForFields` (??)

### 10.38.11 TIndexDefs.Update

Synopsis: Called whenever one of the items changes

Declaration: `procedure Update; Virtual; Overload`

Visibility: public

Description: `Update` can be called to have the dataset update its index definitions.

### 10.38.12 TIndexDefs.Items

Synopsis: Indexed access to the index definitions

Declaration: `Property Items[Index: Integer]: TIndexDef; default`

Visibility: public

Access: Read,Write

Description: `Items` is redefined by `TIndexDefs` using `TIndexDef` as the type for the elements. It is the default property of the `TIndexDefs` class.

See also: `TIndexDef` ([357](#))

## 10.39 TIntegerField

### 10.39.1 Description

`TIntegerField` is an alias for `TLongintField` ([365](#)).

See also: `TLongintField` ([365](#)), `TField` ([315](#))

## 10.40 TLargeintField

### 10.40.1 Description

`TLargeIntField` is instantiated when a dataset must manage a field with 64-bit signed data: the data type `ftLargeInt`. It overrides some methods of `TField` ([315](#)) to handle int64 data, and sets some of the properties to values for int64 data. It also introduces some methods and properties specific to 64-bit integer data such as `MinValue` (??) and `MaxValue` (??).

It should never be necessary to create an instance of `TLargeIntField` manually, a field of this class will be instantiated automatically for each int64 field when a dataset is opened.

See also: `TField` ([315](#)), `MinValue` (??), `MaxValue` (??)

### 10.40.2 Method overview

Page	Property	Description
<a href="#">364</a>	<code>CheckRange</code>	Check whether a values falls within the allowed range
<a href="#">364</a>	<code>Create</code>	Create a new instance of the <code>TLargeintField</code> class

### 10.40.3 Property overview

Page	Property	Access	Description
<a href="#">364</a>	<code>MaxValue</code>	rw	Maximum value for the field
<a href="#">365</a>	<code>MinValue</code>	rw	Minimum value for the field
<a href="#">364</a>	<code>Value</code>	rw	Field contents as a 64-bit integer value

#### 10.40.4 TLargeintField.Create

Synopsis: Create a new instance of the TLargeintField class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of the TLargeIntField class: it calls the inherited constructor and then initializes the various properties of Tfield (315) and MinValue (??) and MaxValue (??).

See also: TField (315), MinValue (??), MaxValue (??)

#### 10.40.5 TLargeintField.CheckRange

Synopsis: Check whether a values falls within the allowed range

Declaration: `function CheckRange(AValue: LargeInt) : Boolean`

Visibility: public

Description: `CheckRange` returns `True` if `AValue` lies within the range defined by the MinValue (??) and MaxValue (??) properties. If the value lies outside of the allowed range, then `False` is returned.

See also: MaxValue (??), MinValue (??)

#### 10.40.6 TLargeintField.Value

Synopsis: Field contents as a 64-bit integer value

Declaration: `Property Value : LargeInt`

Visibility: public

Access: Read,Write

Description: `Value` is redefined by TLargeIntField as a 64-bit integer value. It returns the same value as TField.AsLargeInt (??).

See also: TField.Value (??), TField.AsLargeInt (??)

#### 10.40.7 TLargeintField.MaxValue

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : LargeInt`

Visibility: published

Access: Read,Write

Description: `MaxValue` is the maximum value for the field if set to any value different from zero. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals 0, i.e. any integer value is allowed.

If `MaxValue` is set, `MinValue` (??) should also be set, because it will also be checked.

See also: TLargeIntField.MinValue (??)

### 10.40.8 TLargeintField.MinValue

Synopsis: Minimum value for the field

Declaration: `Property MinValue : LargeInt`

Visibility: published

Access: Read,Write

Description: `MinValue` is the minimum value for the field. When setting the field's value, the value may not be less than `MinValue`. Any attempt to write a smaller value as the field's content will result in an exception. By default `MinValue` equals 0, i.e. any integer value is allowed.

If `MinValue` is set, `MaxValue` (??) should also be set, because it will also be checked.

See also: `TLargeIntField.MaxValue` (??)

## 10.41 TLongintField

### 10.41.1 Description

`TLongintField` is instantiated when a dataset must manage a field with 32-bit signed data: the data type `ftInteger`. It overrides some methods of `TField` (315) to handle integer data, and sets some of the properties to values for integer data. It also introduces some methods and properties specific to integer data such as `MinValue` (??) and `MaxValue` (??).

It should never be necessary to create an instance of `TLongintField` manually, a field of this class will be instantiated automatically for each integer field when a dataset is opened.

See also: `TField` (315), `MaxValue` (??), `MinValue` (??)

### 10.41.2 Method overview

Page	Property	Description
<a href="#">366</a>	<code>CheckRange</code>	Check whether a valid is in the allowed range of values for the field
<a href="#">365</a>	<code>Create</code>	Create a new instance of <code>TLongintField</code>

### 10.41.3 Property overview

Page	Property	Access	Description
<a href="#">366</a>	<code>MaxValue</code>	rw	Maximum value for the field
<a href="#">366</a>	<code>MinValue</code>	rw	Minimum value for the field
<a href="#">366</a>	<code>Value</code>	rw	Value of the field as longint

### 10.41.4 TLongintField.Create

Synopsis: Create a new instance of `TLongintField`

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of `TLongintField`. After calling the inherited constructor, it initializes the `MinValue` (??) and `MaxValue` (??) properties.

See also: `TField` (315), `MaxValue` (??), `MinValue` (??)

### 10.41.5 TLongintField.CheckRange

Synopsis: Check whether a valid is in the allowed range of values for the field

Declaration: `function CheckRange (AValue: LongInt) : Boolean`

Visibility: `public`

Description: `CheckRange` returns `True` if `AValue` lies within the range defined by the `MinValue (??)` and `MaxValue (??)` properties. If the value lies outside of the allowed range, then `False` is returned.

See also: `MaxValue (??)`, `MinValue (??)`

### 10.41.6 TLongintField.Value

Synopsis: Value of the field as `longint`

Declaration: `Property Value : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `Value` is redefined by `TLongintField` as a 32-bit signed integer value. It returns the same value as the `TField.AsInteger (??)` property.

See also: `TField.Value (??)`

### 10.41.7 TLongintField.MaxValue

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : LongInt`

Visibility: `published`

Access: `Read,Write`

Description: `MaxValue` is the maximum value for the field. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals `MaxInt`, i.e. any integer value is allowed.

See also: `MinValue (??)`

### 10.41.8 TLongintField.MinValue

Synopsis: Minimum value for the field

Declaration: `Property MinValue : LongInt`

Visibility: `published`

Access: `Read,Write`

Description: `MinValue` is the minimum value for the field. When setting the field's value, the value may not be less than `MinValue`. Any attempt to write a smaller value as the field's content will result in an exception. By default `MinValue` equals `-MaxInt`, i.e. any integer value is allowed.

See also: `MaxValue (??)`

## 10.42 TLookupList

### 10.42.1 Description

`TLookupList` is a list object used for storing values of lookup operations by lookup fields. There should be no need to create an instance of `TLookupList` manually, the `TField` instance will create an instance of `TLookupList` on demand.

See also: `TField.LookupCache` (??)

### 10.42.2 Method overview

Page	Property	Description
<a href="#">367</a>	<code>Add</code>	Add a key, value pair to the list
<a href="#">368</a>	<code>Clear</code>	Remove all key, value pairs from the list
<a href="#">367</a>	<code>Create</code>	Create a new instance of <code>TLookupList</code> .
<a href="#">367</a>	<code>Destroy</code>	Free a <code>TLookupList</code> instance from memory
<a href="#">368</a>	<code>FirstKeyByValue</code>	Find the first key that matches a value
<a href="#">368</a>	<code>ValueOfKey</code>	Look up value based on a key
<a href="#">368</a>	<code>ValuesToStrings</code>	Convert values to stringlist

### 10.42.3 TLookupList.Create

Synopsis: Create a new instance of `TLookupList`.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` sets up the necessary structures to manage a list of lookup values for a lookup field.

See also: `TLookupList.Destroy` (??)

### 10.42.4 TLookupList.Destroy

Synopsis: Free a `TLookupList` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees all resources (mostly memory) allocated by the lookup list, and calls then the inherited destructor.

See also: `TLookupList.Create` (??)

### 10.42.5 TLookupList.Add

Synopsis: Add a key, value pair to the list

Declaration: `procedure Add(const AKey: Variant;const AValue: Variant)`

Visibility: `public`

Description: `Add` will add the value `AValue` to the list and associate it with key `AKey`. The same key cannot be added twice.

See also: `TLookupList.Clear` (??)



### 10.42.6 TLookupList.Clear

Synopsis: Remove all key, value pairs from the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all keys and associated values from the list.

See also: `TLookupList.Add` (??)

### 10.42.7 TLookupList.FirstKeyByValue

Synopsis: Find the first key that matches a value

Declaration: `function FirstKeyByValue(const AValue: Variant) : Variant`

Visibility: `public`

Description: `FirstKeyByValue` does a reverse lookup: it returns the first key value in the list that matches the `AValue` value. If none is found, `Null` is returned. This mechanism is quite slow, as a linear search is performed.

Errors: If no key is found, `Null` is returned.

See also: `TLookupList.ValueOfKey` (??)

### 10.42.8 TLookupList.ValueOfKey

Synopsis: Look up value based on a key

Declaration: `function ValueOfKey(const AKey: Variant) : Variant`

Visibility: `public`

Description: `ValueOfKey` does a value lookup based on a key: it returns the value in the list that matches the `AKey` key. If none is found, `Null` is returned. This mechanism is quite slow, as a linear search is performed.

See also: `TLookupList.FirstKeyByValue` (??), `TLookupList.Add` (??)

### 10.42.9 TLookupList.ValuesToStrings

Synopsis: Convert values to stringlist

Declaration: `procedure ValuesToStrings(AStrings: TStrings)`

Visibility: `public`

Description: `ValuesToStrings` converts the list of values to a stringlist, so they can be used e.g. in a drop-down list.

See also: `TLookupList.ValueOfKey` (??)

## 10.43 TMasterDataLink

### 10.43.1 Description

`TMasterDataLink` is a `TDataLink` descendent which handles master-detail relations. It can be used in `TDataset` (267) descendents that must have master-detail functionality: the detail dataset creates an instance of `TMasterDataLink` to point to the master dataset, which is subsequently available through the `TDataLink.Dataset` (??) property.

The class also provides functionality for keeping a list of fields that make up the master-detail functionality, in the `TMasterDataLink.FieldName` (??) and `TMasterDataLink.Fields` (??) properties.

This class should never be used in application code.

See also: `TDataset` (267), `TDataLink.DataSource` (??), `TDataLink.DataSet` (??), `TMasterDataLink.FieldName` (??), `TMasterDataLink.Fields` (??)

### 10.43.2 Method overview

Page	Property	Description
<a href="#">369</a>	Create	Create a new instance of <code>TMasterDataLink</code>
<a href="#">369</a>	Destroy	Free the datalink instance from memory

### 10.43.3 Property overview

Page	Property	Access	Description
<a href="#">370</a>	<code>FieldNames</code>	rw	List of fieldnames that make up the master-detail relationship
<a href="#">370</a>	<code>Fields</code>	r	List of fields as specified in <code>FieldNames</code>
<a href="#">370</a>	<code>OnMasterChange</code>	rw	Called whenever the master dataset data changes
<a href="#">370</a>	<code>OnMasterDisable</code>	rw	Called whenever the master dataset is disabled

### 10.43.4 TMasterDataLink.Create

Synopsis: Create a new instance of `TMasterDataLink`

Declaration: `constructor Create(ADataset: TDataset); Virtual`

Visibility: `public`

Description: `Create` initializes a new instance of `TMasterDataLink`. The `ADataset` parameter is the detail dataset in the master-detail relation: it is saved in the `DetailDataset` (??) property. The master dataset must be set through the `DataSource` (??) property, and is usually set by the application programmer.

See also: `TDetailDataLink.DetailDataset` (??), `TDataLink.DataSource` (??)

### 10.43.5 TMasterDataLink.Destroy

Synopsis: Free the datalink instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the resources used by `TMasterDataLink` and then calls the inherited destructor.

See also: `TMasterDataLink.Create` (??)

### 10.43.6 TMasterDataLink.FieldNameNames

Synopsis: List of fieldnames that make up the master-detail relationship

Declaration: `Property FieldNames : String`

Visibility: `public`

Access: `Read,Write`

Description: `FieldNames` is a semicolon-separated list of fieldnames in the master dataset (`TDataLink.Dataset` (??)) on which the master-detail relationship is based. Setting this property will fill the `TMasterDataLink.Fields` (??) property with the field instances of the master dataset.

See also: `TMasterDataLink.Fields` (??), `TDataLink.Dataset` (??), `TDataset.GetFieldList` (??)

### 10.43.7 TMasterDataLink.Fields

Synopsis: List of fields as specified in `FieldNames`

Declaration: `Property Fields : TList`

Visibility: `public`

Access: `Read`

Description: `Fields` is filled with the `TField` (315) instances from the master dataset (`TDataLink.Dataset` (??)) when the `FieldNames` (??) property is set, and when the master dataset opens.

See also: `TField` (315), `TMasterDataLink.FieldNameNames` (??)

### 10.43.8 TMasterDataLink.OnMasterChange

Synopsis: Called whenever the master dataset data changes

Declaration: `Property OnMasterChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnMasterChange` is called whenever the field values in the master dataset changes, i.e. when it becomes active, or when the current record changes. If the `TMasterDataLink.Fields` (??) list is empty, `TMasterDataLink.OnMasterDisable` (??) is called instead.

See also: `TMasterDataLink.OnMasterDisable` (??)

### 10.43.9 TMasterDataLink.OnMasterDisable

Synopsis: Called whenever the master dataset is disabled

Declaration: `Property OnMasterDisable : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

**Description:** `OnMasterDisable` is called whenever the master dataset is disabled, or when it is active and the field list is empty.

See also: `TMasterDataLink.OnMasterChange` (??)

## 10.44 TMasterParamsDataLink

### 10.44.1 Description

`TMasterParamsDataLink` is a `TDataLink` (262) descendent that can be used to establish a master-detail relationship between 2 `TDataset` instances where the detail dataset is parametrized using a `TParams` instance. It takes care of closing and opening the detail dataset and copying the parameter values from the master dataset whenever the data in the master dataset changes.

See also: `TDatalink` (262), `TDataset` (267), `TParams` (388), `TParam` (376)

### 10.44.2 Method overview

Page	Property	Description
<a href="#">372</a>	<code>CopyParamsFromMaster</code>	Copy parameter values from master dataset.
<a href="#">371</a>	<code>Create</code>	Initialize a new <code>TMasterParamsDataLink</code> instance
<a href="#">371</a>	<code>RefreshParamNames</code>	Refresh the list of parameter names

### 10.44.3 Property overview

Page	Property	Access	Description
<a href="#">372</a>	<code>Params</code>	rw	Parameters of detail dataset.

### 10.44.4 TMasterParamsDataLink.Create

**Synopsis:** Initialize a new `TMasterParamsDataLink` instance

**Declaration:** `constructor Create(ADataset: TDataSet); Override`

**Visibility:** `public`

**Description:** `Create` first calls the inherited constructor using `ADataset`, and then looks for a property named `Params` of type `TParams` (388) in the published properties of `ADataset` and assigns it to the `Params` (??) property.

See also: `TDataset` (267), `TParams` (388), `TMasterParamsDataLink.Params` (??)

### 10.44.5 TMasterParamsDataLink.RefreshParamNames

**Synopsis:** Refresh the list of parameter names

**Declaration:** `procedure RefreshParamNames; Virtual`

**Visibility:** `public`

**Description:** `RefreshParamNames` scans the `Params` (??) property and sets the `FieldNames` (??) property to the list of parameter names.

See also: `TMasterParamsDataLink.Params` (??), `TMasterDataLink.FieldNames` (??)

### 10.44.6 TMasterParamsDataLink.CopyParamsFromMaster

Synopsis: Copy parameter values from master dataset.

Declaration: `procedure CopyParamsFromMaster(CopyBound: Boolean); Virtual`

Visibility: public

Description: `CopyParamsFromMaster` calls `TParams.CopyParamValuesFromDataset` (??), passing it the master dataset: it provides the parameters of the detail dataset with their new values. If `CopyBound` is `false`, then only parameters with their `Bound` (??) property set to `False` are copied. If it is `True` then the value is set for all parameters.

Errors: If the master dataset does not have a corresponding field for each parameter, then an exception will be raised.

See also: `TParams.CopyParamValuesFromDataset` (??), `TParam.Bound` (??)

### 10.44.7 TMasterParamsDataLink.Params

Synopsis: Parameters of detail dataset.

Declaration: `Property Params : TParams`

Visibility: public

Access: Read,Write

Description: `Params` is the `TParams` instance of the detail dataset. If the detail dataset contains a property named `Params` of type `TParams`, then it will be set when the `TMasterParamsDataLink` instance was created. If the property is not published, or has another name, then the `Params` property must be set in code.

See also: `Tparams` (388), `TMasterParamsDataLink.Create` (??)

## 10.45 TMemoField

### 10.45.1 Description

`TMemoField` is the class used when a dataset must manage memo (Text BLOB) data. (`TField.DataType` (??) equals `ftMemo`). It initializes some of the properties of the `TField` (315) class. All methods to be able to work with memo fields have been implemented in the `TBlobField` (243) parent class.

It should never be necessary to create an instance of `TMemoField` manually, a field of this class will be instantiated automatically for each memo field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TBLOBField` (243), `TWideMemoField` (398), `TGraphicField` (356)

### 10.45.2 Method overview

Page	Property	Description
373	Create	Create a new instance of the <code>TMemoField</code> class

### 10.45.3 Property overview

Page	Property	Access	Description
373	Transliterate		Should the contents of the field be transliterated

### 10.45.4 TMemoField.Create

Synopsis: Create a new instance of the `TMemoField` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TMemoField` class. It calls the inherited destructor, and then sets some `TField` (315) properties to configure the instance for working with memo values.

See also: `TField` (315)

### 10.45.5 TMemoField.Transliterate

Synopsis: Should the contents of the field be transliterated

Declaration: `Property Transliterate :`

Visibility: `published`

Access:

Description: `Transliterate` is redefined from `TBlobField.Transliterate (??)` with a default value of `true`.

See also: `TBlobField.Transliterate (??)`, `TStringField.Transliterate (??)`, `TDataset.Translate (??)`

## 10.46 TNamedItem

### 10.46.1 Description

`NamedItem` is a `TCollectionItem (??)` descendent which introduces a `Name (??)` property. It automatically returns the value of the `Name` property as the value of the `DisplayName (??)` property.

See also: `DisplayName (??)`, `Name (??)`

### 10.46.2 Property overview

Page	Property	Access	Description
<a href="#">373</a>	<code>DisplayName</code>	<code>rw</code>	Display name
<a href="#">374</a>	<code>Name</code>	<code>rw</code>	Name of the item

### 10.46.3 TNamedItem.DisplayName

Synopsis: Display name

Declaration: `Property DisplayName : String`

Visibility: `public`

Access: `Read,Write`

Description: `DisplayName` is declared in `TCollectionItem (??)`, and is made `public` in `TNamedItem`. The value equals the value of the `Name (??)` property.

See also: `Name (??)`

### 10.46.4 TNamedItem.Name

Synopsis: Name of the item

Declaration: `Property Name : String`

Visibility: published

Access: Read,Write

Description: Name is the name of the item in the collection. This property is also used as the value for the `DisplayName (??)` property. If the `TNamedItem` item is owned by a `TDefCollection (312)` collection, then the name must be unique, i.e. each Name value may appear only once in the collection.

See also: `DisplayName (??)`, `TDefCollection (312)`

## 10.47 TNumericField

### 10.47.1 Description

`TNumericField` is an abstract class which overrides some of the methods of `TField (315)` to handle numerical data. It also introduces or publishes a couple of properties that are only relevant in the case of numerical data, such as `TNumericField.DisplayFormat (??)` and `TNumericField.EditFormat (??)`.

Since `TNumericField` is an abstract class, it must never be instantiated directly. Instead one of the descendent classes should be created.

See also: `TField (315)`, `TNumericField.DisplayFormat (??)`, `TNumericField.EditFormat (??)`, `TField.Alignment (??)`, `TIntegerField (363)`, `TLargeIntField (363)`, `TFloatField (352)`, `TBCDField (239)`

### 10.47.2 Method overview

Page	Property	Description
<a href="#">374</a>	<code>CheckTypeSize</code>	
<a href="#">374</a>	<code>Create</code>	Create a new instance of <code>TNumericField</code>

### 10.47.3 Property overview

Page	Property	Access	Description
<a href="#">375</a>	<code>Alignment</code>		Alignment of the field
<a href="#">375</a>	<code>DisplayFormat</code>	rw	Format string for display of numerical data
<a href="#">375</a>	<code>EditFormat</code>	rw	Format string for editing of numerical data

### 10.47.4 TNumericField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(AValue: LongInt);` Override

Visibility: default

### 10.47.5 TNumericField.Create

Synopsis: Create a new instance of `TNumericField`

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` calls the inherited constructor and then initializes the `TField.Alignment` (??) property with

See also: `TField.Alignment` (??)

### 10.47.6 TNumericField.Alignment

**Synopsis:** Alignment of the field

**Declaration:** `Property Alignment :`

**Visibility:** `published`

**Access:**

**Description:** `Alignment` is published by `TNumericField` with `taRightJustify` as a default value.

See also: `TField.Alignment` (??)

### 10.47.7 TNumericField.DisplayFormat

**Synopsis:** Format string for display of numerical data

**Declaration:** `Property DisplayFormat : String`

**Visibility:** `published`

**Access:** `Read,Write`

**Description:** `DisplayFormat` specifies a format string (such as used by the `Format` (??) and `FormatFloat` (??) functions) for display purposes: the `TField.DisplayText` (??) property will use this property to format the field's value. Which formatting function (and, consequently, which format can be entered) is used depends on the descendent of the `TNumericField` class.

See also: `Format` (??), `FormatFloat` (??), `TField.DisplayText` (??), `TNumericField.EditFormat` (??)

### 10.47.8 TNumericField.EditFormat

**Synopsis:** Format string for editing of numerical data

**Declaration:** `Property EditFormat : String`

**Visibility:** `published`

**Access:** `Read,Write`

**Description:** `EditFormat` specifies a format string (such as used by the `Format` (??) and `FormatFloat` (??) functions) for editing purposes: the `TField.Text` (??) property will use this property to format the field's value. Which formatting function (and, consequently, which format can be entered) is used depends on the descendent of the `TNumericField` class.

See also: `Format` (??), `FormatFloat` (??), `TField.Text` (??), `TNumericField.DisplayFormat` (??)



## 10.48 TParam

### 10.48.1 Description

`TParam` is one item in a `TParams` (388) collection. It describes the name (`TParam.Name` (??)), type (`ParamType` (??)) and value (`TParam.Value` (??)) of a parameter in a parametrized query or stored procedure. Under normal circumstances, it should never be necessary to create a `TParam` instance manually; the `TDataset` (267) descendent that owns the parameters should have created all necessary `TParam` instances.

See also: `TParams` (388)

### 10.48.2 Method overview

Page	Property	Description
<a href="#">377</a>	<code>Assign</code>	Assign one parameter instance to another
<a href="#">378</a>	<code>AssignField</code>	Copy value from field instance
<a href="#">378</a>	<code>AssignFieldValue</code>	Assign field value to the parameter.
<a href="#">379</a>	<code>AssignFromField</code>	Copy field type and value
<a href="#">378</a>	<code>AssignToField</code>	Assign parameter value to field
<a href="#">379</a>	<code>Clear</code>	Clear the parameter value
<a href="#">377</a>	<code>Create</code>	Create a new parameter value
<a href="#">379</a>	<code>GetData</code>	Get the parameter value from a memory buffer
<a href="#">379</a>	<code>GetDataSize</code>	Return the size of the data.
<a href="#">380</a>	<code>LoadFromFile</code>	Load a parameter value from file
<a href="#">380</a>	<code>LoadFromStream</code>	Load a parameter value from stream
<a href="#">380</a>	<code>SetBlobData</code>	Set BLOB data
<a href="#">380</a>	<code>SetData</code>	Set the parameter value from a buffer

### 10.48.3 Property overview

Page	Property	Access	Description
<a href="#">381</a>	AsBlob	rw	Return parameter value as a blob
<a href="#">381</a>	AsBoolean	rw	Get/Set parameter value as a boolean value
<a href="#">381</a>	AsCurrency	rw	Get/Set parameter value as a currency value
<a href="#">382</a>	AsDate	rw	Get/Set parameter value as a date (TDateTime) value
<a href="#">382</a>	AsDateTime	rw	Get/Set parameter value as a date/time (TDateTime) value
<a href="#">382</a>	AsFloat	rw	Get/Set parameter value as a floating-point value
<a href="#">384</a>	AsFMTBCD	rw	
<a href="#">382</a>	AsInteger	rw	Get/Set parameter value as an integer (32-bit) value
<a href="#">383</a>	AsLargeInt	rw	Get/Set parameter value as a 64-bit integer value
<a href="#">383</a>	AsMemo	rw	Get/Set parameter value as a memo (string) value
<a href="#">383</a>	AsSmallInt	rw	Get/Set parameter value as a smallint value
<a href="#">383</a>	AsString	rw	Get/Set parameter value as a string value
<a href="#">384</a>	AsTime	rw	Get/Set parameter value as a time (TDateTime) value
<a href="#">386</a>	AsWideString	rw	Get/Set the value as a widestring
<a href="#">384</a>	AsWord	rw	Get/Set parameter value as a word value
<a href="#">384</a>	Bound	rw	Is the parameter value bound (set to fixed value)
<a href="#">385</a>	Dataset	r	Dataset to which this parameter belongs
<a href="#">386</a>	DataType	rw	Data type of the parameter
<a href="#">385</a>	IsNull	r	Is the parameter empty
<a href="#">386</a>	Name	rw	Name of the parameter
<a href="#">385</a>	NativeStr	rw	No description available
<a href="#">387</a>	NumericScale	rw	Numeric scale
<a href="#">387</a>	ParamType	rw	Type of parameter
<a href="#">387</a>	Precision	rw	Precision of the BCD value
<a href="#">388</a>	Size	rw	Size of the parameter
<a href="#">385</a>	Text	rw	Read or write the value of the parameter as a string
<a href="#">386</a>	Value	rws	Value as a variant

### 10.48.4 TParam.Create

Synopsis: Create a new parameter value

Declaration: `constructor Create(ACollection: TCollection); Override; Overload`  
`constructor Create(AParams: TParams; AParamType: TParamType); Overload`  
`; Reintroduce`

Visibility: public

Description: `Create` first calls the inherited `create`, and then initializes the parameter properties. The first form creates a default parameter, the second form is a convenience function and initializes a parameter of a certain kind (`AParamType`), in which case the owning `TParams` collection must be specified in `AParams`

See also: `TParams` ([388](#))

### 10.48.5 TParam.Assign

Synopsis: Assign one parameter instance to another

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: public

**Description:** Assign copies the Name, ParamType, Bound, Value, SizePrecision and NumericScale properties from ASource if it is of type TParam. If Source is of type TField (315), then it is passed to TParam.AssignField (??). If Source is of type TStrings, then it is assigned to TParams.AsMemo (??).

**Errors:** If Source is not of type TParam, TField or TStrings, an exception will be raised.

**See also:** TField (315), TParam.Name (??), TParam.Bound (??), TParam.NumericScale (??), TParam.ParamType (??), TParam.value (??), TParam.Size (??), TParam.AssignField (??), Tparam.AsMemo (??)

### 10.48.6 TParam.AssignField

**Synopsis:** Copy value from field instance

**Declaration:** procedure AssignField(Field: TField)

**Visibility:** public

**Description:** AssignField copies the Field, FieldName (??) and Value (??) to the parameter instance. The parameter is bound after this operation. If Field is Nil then the parameter name and value are cleared.

**See also:** TParam.assign (??), TParam.AssignToField (??), TParam.AssignFieldValue (??)

### 10.48.7 TParam.AssignToField

**Synopsis:** Assign parameter value to field

**Declaration:** procedure AssignToField(Field: TField)

**Visibility:** public

**Description:** AssignToField copies the parameter value (??) to the field instance. If Field is Nil, nothing happens.

**Errors:** An EDatabaseError (233) exception is raised if the field has an unsupported field type (for types ftCursor, ftArray, ftDataset, ftReference).

**See also:** TParam.Assign (??), TParam.AssignField (??), TParam.AssignFromField (??)

### 10.48.8 TParam.AssignFieldValue

**Synopsis:** Assign field value to the parameter.

**Declaration:** procedure AssignFieldValue(Field: TField; const AValue: Variant)

**Visibility:** public

**Description:** AssignFieldValue copies only the field type from Field and the value from the AValue parameter. It sets the TParam.Bound (??) bound parameter to True. This method is called from TParam.AssignField (??).

**See also:** TField (315), TParam.AssignField (??), TParam.Bound (??)

### 10.48.9 TParam.AssignFromField

Synopsis: Copy field type and value

Declaration: `procedure AssignFromField(Field: TField)`

Visibility: public

Description: `AssignFromField` copies the field value (??) and data type (`TField.DataType` (??)) to the parameter instance. If `Field` is `Nil`, nothing happens. This is the reverse operation of `TParam.AssignToField` (??).

Errors: An `EDatabaseError` (233) exception is raised if the field has an unsupported field type (for types `ftCursor`, `ftArray`, `ftDataset`, `ftReference`).

See also: `TParam.Assign` (??), `TParam.AssignField` (??), `TParam.AssignToField` (??)

### 10.48.10 TParam.Clear

Synopsis: Clear the parameter value

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` clears the parameter value, it is set to `UnAssigned`. The Datatype, parameter type or name are not touched.

See also: `TParam.Value` (??), `TParam.Name` (??), `TParam.ParamType` (??), `TParam.DataType` (??)

### 10.48.11 TParam.GetData

Synopsis: Get the parameter value from a memory buffer

Declaration: `procedure GetData(Buffer: Pointer)`

Visibility: public

Description: `GetData` retrieves the parameter value and stores it in `buffer`. It uses the same data layout as `TField` (315), and can be used to copy the parameter value to a record buffer.

Errors: Only basic field types are supported. Using an unsupported field type will result in an `EDatabaseError` (233) exception.

See also: `TParam.SetData` (??), `TField` (315)

### 10.48.12 TParam.GetDataSize

Synopsis: Return the size of the data.

Declaration: `function GetDataSize : Integer`

Visibility: public

Description: `GetDataSize` returns the size (in bytes) needed to store the current value of the parameter.

Errors: For an unsupported data type, an `EDatabaseError` (233) exception is raised when this function is called.

See also: `TParam.GetData` (??), `TParam.SetData` (??)

**10.48.13 TParam.LoadFromFile**

Synopsis: Load a parameter value from file

Declaration: `procedure LoadFromFile(const FileName: String; BlobType: TBlobType)`

Visibility: public

Description: `LoadFromFile` can be used to load a BLOB-type parameter from a file named `FileName`. The `BlobType` parameter can be used to set the exact data type of the parameter: it must be one of the BLOB data types. This function simply creates a `TFileStream` instance and passes it to `TParam.LoadFromStream` (??).

Errors: If the specified `FileName` is not a valid file, or the file is not readable, an exception will occur.

See also: `TParam.LoadFromStream` (??), `TBlobType` (219), `TParam.SaveToFile` (??)

**10.48.14 TParam.LoadFromStream**

Synopsis: Load a parameter value from stream

Declaration: `procedure LoadFromStream(Stream: TStream; BlobType: TBlobType)`

Visibility: public

Description: `LoadFromStream` can be used to load a BLOB-type parameter from a stream. The `BlobType` parameter can be used to set the exact data type of the parameter: it must be one of the BLOB data types.

Errors: If the stream does not support taking the `Size` of the stream, an exception will be raised.

See also: `TParam.LoadFromFile` (??), `TParam.SaveToStream` (??)

**10.48.15 TParam.SetBlobData**

Synopsis: Set BLOB data

Declaration: `procedure SetBlobData(Buffer: Pointer; ASize: Integer)`

Visibility: public

Description: `SetBlobData` reads the value of a BLOB type parameter from a memory buffer: the data is read from the memory buffer `Buffer` and is assumed to be `Size` bytes long.

Errors: No checking is performed on the validity of the data buffer. If the data buffer is invalid or the size is wrong, an exception may occur.

See also: `TParam.LoadFromStream` (??)

**10.48.16 TParam.SetData**

Synopsis: Set the parameter value from a buffer

Declaration: `procedure SetData(Buffer: Pointer)`

Visibility: public

**Description:** `SetData` performs the reverse operation of `TParam.GetData (??)`: it reads the parameter value from the memory area pointed to by `Buffer`. The size of the data read is determined by `TParam.GetDataSize (??)` and the type of data by `TParam.DataType (??)`: it is the same storage mechanism used by `TField (315)`, and so can be used to copy the value from a `TDataset (267)` record buffer.

**Errors:** Not all field types are supported. If an unsupported field type is encountered, an `EDatabaseError (233)` exception is raised.

**See also:** `TDataset (267)`, `TParam.GetData (??)`, `TParam.DataType (??)`, `TParam.GetDataSize (??)`

### 10.48.17 TParam.AsBlob

**Synopsis:** Return parameter value as a blob

**Declaration:** `Property AsBlob : TBlobData`

**Visibility:** public

**Access:** Read,Write

**Description:** `AsBlob` returns the parameter value as a blob: currently this is a string. It can be set to set the parameter value.

**See also:** `TParam.AsString (??)`

### 10.48.18 TParam.AsBoolean

**Synopsis:** Get/Set parameter value as a boolean value

**Declaration:** `Property AsBoolean : Boolean`

**Visibility:** public

**Access:** Read,Write

**Description:** `AsBoolean` will return the parameter value as a boolean value. If it is written, the value is set to the specified value and the data type is set to `ftBoolean`.

**See also:** `TParam.DataType (??)`, `TParam.Value (??)`

### 10.48.19 TParam.AsCurrency

**Synopsis:** Get/Set parameter value as a currency value

**Declaration:** `Property AsCurrency : Currency`

**Visibility:** public

**Access:** Read,Write

**Description:** `AsCurrency` will return the parameter value as a currency value. If it is written, the value is set to the specified value and the data type is set to `ftCurrency`.

**See also:** `TParam.AsFloat (??)`, `TParam.DataType (??)`, `TParam.Value (??)`

#### 10.48.20 TParam.AsDate

Synopsis: Get/Set parameter value as a date (TDateTime) value

Declaration: `Property AsDate : TDateTime`

Visibility: `public`

Access: `Read,Write`

Description: `AsDate` will return the parameter value as a date value. If it is written, the value is set to the specified value and the data type is set to `ftDate`.

See also: `TParam.AsDateTime` (??), `TParam.AsTime` (??), `TParam.DataType` (??), `TParam.Value` (??)

#### 10.48.21 TParam.AsDateTime

Synopsis: Get/Set parameter value as a date/time (TDateTime) value

Declaration: `Property AsDateTime : TDateTime`

Visibility: `public`

Access: `Read,Write`

Description: `AsDateTime` will return the parameter value as a TDateTime value. If it is written, the value is set to the specified value and the data type is set to `ftDateTime`.

See also: `TParam.AsDate` (??), `TParam.asTime` (??), `TParam.DataType` (??), `TParam.Value` (??)

#### 10.48.22 TParam.AsFloat

Synopsis: Get/Set parameter value as a floating-point value

Declaration: `Property AsFloat : Double`

Visibility: `public`

Access: `Read,Write`

Description: `AsFloat` will return the parameter value as a double floating-point value. If it is written, the value is set to the specified value and the data type is set to `ftFloat`.

See also: `TParam.AsCurrency` (??), `TParam.DataType` (??), `TParam.Value` (??)

#### 10.48.23 TParam.AsInteger

Synopsis: Get/Set parameter value as an integer (32-bit) value

Declaration: `Property AsInteger : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `AsInteger` will return the parameter value as a 32-bit signed integer value. If it is written, the value is set to the specified value and the data type is set to `ftInteger`.

See also: `TParam.AsLargeInt` (??), `TParam.AsSmallInt` (??), `TParam.AsWord` (??), `TParam.DataType` (??), `TParam.Value` (??)

**10.48.24 TParam.AsLargeInt**

Synopsis: Get/Set parameter value as a 64-bit integer value

Declaration: `Property AsLargeInt : LargeInt`

Visibility: public

Access: Read,Write

Description: `AsLargeInt` will return the parameter value as a 64-bit signed integer value. If it is written, the value is set to the specified value and the data type is set to `ftLargeInt`.

See also: `TParam.asInteger (??)`, `TParam.asSmallint (??)`, `TParam.AsWord (??)`, `TParam.DataType (??)`, `TParam.Value (??)`

**10.48.25 TParam.AsMemo**

Synopsis: Get/Set parameter value as a memo (string) value

Declaration: `Property AsMemo : String`

Visibility: public

Access: Read,Write

Description: `AsMemo` will return the parameter value as a memo (string) value. If it is written, the value is set to the specified value and the data type is set to `ftMemo`.

See also: `TParam.asString (??)`, `TParam.LoadFromStream (??)`, `TParam.SaveToStream (??)`, `TParam.DataType (??)`, `TParam.Value (??)`

**10.48.26 TParam.AsSmallInt**

Synopsis: Get/Set parameter value as a smallint value

Declaration: `Property AsSmallInt : LongInt`

Visibility: public

Access: Read,Write

Description: `AsSmallInt` will return the parameter value as a 16-bit signed integer value. If it is written, the value is set to the specified value and the data type is set to `ftSmallInt`.

See also: `TParam.AsInteger (??)`, `TParam.AsLargeInt (??)`, `TParam.AsWord (??)`, `TParam.DataType (??)`, `TParam.Value (??)`

**10.48.27 TParam.AsString**

Synopsis: Get/Set parameter value as a string value

Declaration: `Property AsString : String`

Visibility: public

Access: Read,Write

Description: `AsString` will return the parameter value as a string value. If it is written, the value is set to the specified value and the data type is set to `ftString`.

See also: `TParam.DataType (??)`, `TParam.Value (??)`



#### 10.48.28 TParam.AsTime

Synopsis: Get/Set parameter value as a time (TDateTime) value

Declaration: `Property AsTime : TDateTime`

Visibility: `public`

Access: `Read,Write`

Description: `AsTime` will return the parameter value as a time (TDateTime) value. If it is written, the value is set to the specified value and the data type is set to `ftTime`.

See also: `TParam.AsDate (??)`, `TParam.AsDateTime (??)`, `TParam.DataType (??)`, `TParam.Value (??)`

#### 10.48.29 TParam.AsWord

Synopsis: Get/Set parameter value as a word value

Declaration: `Property AsWord : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `AsWord` will return the parameter value as an integer. If it is written, the value is set to the specified value and the data type is set to `ftWord`.

See also: `TParam.AsInteger (??)`, `TParam.AsLargeInt (??)`, `TParam.AsSmallint (??)`, `TParam.DataType (??)`, `TParam.Value (??)`

#### 10.48.30 TParam.AsFmtBCD

Declaration: `Property AsFmtBCD : TBCD`

Visibility: `public`

Access: `Read,Write`

#### 10.48.31 TParam.Bound

Synopsis: Is the parameter value bound (set to fixed value)

Declaration: `Property Bound : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Bound` indicates whether a parameter has received a fixed value: setting the parameter value will set `Bound` to `True`. When creating master-detail relationships, parameters with their `Bound` property set to `True` will not receive a value from the master dataset: their value will be kept. Only parameters where `Bound` is `False` will receive a new value from the master dataset.

See also: `TParam.DataType (??)`, `TParam.Value (??)`

### 10.48.32 TParam.Dataset

Synopsis: Dataset to which this parameter belongs

Declaration: `Property Dataset : TDataSet`

Visibility: `public`

Access: `Read`

Description: `Dataset` is the dataset that owns the `TParams` (388) instance of which this `TParam` instance is a part. It is `Nil` if the collection is not set, or is not a `TParams` instance.

See also: `TDataSet` (267), `TParams` (388)

### 10.48.33 TParam.IsNull

Synopsis: Is the parameter empty

Declaration: `Property IsNull : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsNull` is `True` if the value is empty or not set (`Null` or `UnAssigned`).

See also: `TParam.Clear` (??), `TParam.Value` (??)

### 10.48.34 TParam.NativeStr

Synopsis: No description available

Declaration: `Property NativeStr : String`

Visibility: `public`

Access: `Read,Write`

Description: No description available

### 10.48.35 TParam.Text

Synopsis: Read or write the value of the parameter as a string

Declaration: `Property Text : String`

Visibility: `public`

Access: `Read,Write`

Description: `AsText` returns the same value as `TParam.AsString` (??), but, when written, does not set the data type: instead, it attempts to convert the value to the type specified in `TParam.DataType` (??).

See also: `TParam.AsString` (??), `TParam.DataType` (??)

### 10.48.36 TParam.Value

Synopsis: Value as a variant

Declaration: `Property Value : Variant`

Visibility: `public`

Access: `Read,Write`

Description: `Value` returns (or sets) the value as a variant value.

See also: `TParam.DataType` (??)

### 10.48.37 TParam.AsWideString

Synopsis: Get/Set the value as a widestring

Declaration: `Property AsWideString : WideString`

Visibility: `public`

Access: `Read,Write`

Description: `AsWideString` returns the parameter value as a widestring value. Setting the property will set the value of the parameter and will also set the `DataType` (??) to `ftWideString`.

See also: `TParam.AsString` (??), `TParam.Value` (??), `TParam.DataType` (??)

### 10.48.38 TParam.DataType

Synopsis: Data type of the parameter

Declaration: `Property DataType : TFieldType`

Visibility: `published`

Access: `Read,Write`

Description: `DataType` is the current data type of the parameter value. It is set automatically when one of the various `AsXYZ` properties is written, or when the value is copied from a field value.

See also: `TParam.IsNull` (??), `TParam.Value` (??), `TParam.AssignField` (??)

### 10.48.39 TParam.Name

Synopsis: Name of the parameter

Declaration: `Property Name : String`

Visibility: `published`

Access: `Read,Write`

Description: `Name` is the name of the parameter. The name is usually determined automatically from the SQL statement the parameter is part of. Each parameter name should appear only once in the collection.

See also: `TParam.DataType` (??), `TParam.Value` (??), `TParams.ParamByName` (??)

#### 10.48.40 TParam.NumericScale

Synopsis: Numeric scale

Declaration: `Property NumericScale : Integer`

Visibility: published

Access: Read,Write

Description: `NumericScale` can be used to store the numerical scale for BCD values. It is currently unused.

See also: `TParam.Precision (??)`, `TParam.Size (??)`

#### 10.48.41 TParam.ParamType

Synopsis: Type of parameter

Declaration: `Property ParamType : TParamType`

Visibility: published

Access: Read,Write

Description: `ParamType` specifies the type of parameter: is the parameter value written to the database engine, or is it received from the database engine, or both ? It can have the following value:

**ptUnknown**Unknown type

**ptInput**Input parameter

**ptOutput**Output paramete, filled on result

**ptInputOutput**Input/output parameter

**ptResult**Result parameter

The `ParamType` property is usually set by the database engine that creates the parameter instances.

See also: `TParam.DataType (??)`, `TParam.DataSize (??)`, `TParam.Name (??)`

#### 10.48.42 TParam.Precision

Synopsis: Precision of the BCD value

Declaration: `Property Precision : Integer`

Visibility: published

Access: Read,Write

Description: `Precision` can be used to store the numerical precision for BCD values. It is currently unused.

See also: `TParam.NumericScale (??)`, `TParam.Size (??)`

### 10.48.43 TParam.Size

Synopsis: Size of the parameter

Declaration: `Property Size : Integer`

Visibility: published

Access: Read, Write

Description: `Size` is the declared size of the parameter. In the current implementation, this parameter is ignored other than copying it from `TField.DataSize (??)` in the `TParam.AssignFieldValue (??)` method. The actual size can be retrieved through the `TParam.Datasize (??)` property.

See also: `TParam.Datasize (??)`, `TField.DataSize (??)`, `TParam.AssignFieldValue (??)`

## 10.49 TParams

### 10.49.1 Description

`TParams` is a collection of `TParam (376)` values. It is used to specify parameter values for parametrized SQL statements, but is also used to specify parameter values for stored procedures. Its default property is an array of `TParam (376)` values. The class also offers a method to scan a SQL statement for parameter names and replace them with placeholders understood by the SQL engine: `TParams.ParseSQL (??)`.

`TDataset (267)` itself does not use `TParams`. The class is provided in the `DB` unit, so all `TDataset` descendants that need some kind of parametrization make use of the same interface. The `TMasterParamsDataLink (371)` class can be used to establish a master-detail relationship between a parameter-aware `TDataset` instance and another dataset; it will automatically refresh parameter values when the fields in the master dataset change. To this end, the `TParams.CopyParamValuesFromDataset (??)` method exists.

See also: `TDataset (267)`, `TMasterParamsDataLink (371)`, `TParam (376)`, `TParams.ParseSQL (??)`, `TParams.CopyParamValuesFromDataset (??)`

### 10.49.2 Method overview

Page	Property	Description
<a href="#">389</a>	<code>AddParam</code>	Add a parameter to the collection
<a href="#">389</a>	<code>AssignValues</code>	Copy values from another collection
<a href="#">392</a>	<code>CopyParamValuesFromDataset</code>	Copy parameter values from a the fields in a dataset.
<a href="#">389</a>	<code>Create</code>	Create a new instance of <code>TParams</code>
<a href="#">389</a>	<code>CreateParam</code>	Create and add a new parameter to the collection
<a href="#">390</a>	<code>FindParam</code>	Find a parameter with given name
<a href="#">390</a>	<code>GetParamList</code>	Fetch a list of <code>TParam</code> instances
<a href="#">390</a>	<code>IsEqual</code>	Is the list of parameters equal
<a href="#">391</a>	<code>ParamByName</code>	Return a parameter by name
<a href="#">391</a>	<code>ParseSQL</code>	Parse SQL statement, replacing parameter names with SQL parameter placeholders
<a href="#">392</a>	<code>RemoveParam</code>	Remove a parameter from the collection

### 10.49.3 Property overview

Page	Property	Access	Description
<a href="#">392</a>	Dataset	r	Dataset that owns the TParams instance
<a href="#">393</a>	Items	rw	Indexed access to TParams instances in the collection
<a href="#">393</a>	ParamValues	rw	Named access to the parameter values.

### 10.49.4 TParams.Create

Synopsis: Create a new instance of TParams

Declaration: `constructor Create(AOwner: TPersistent); Overload`  
`constructor Create; Overload`

Visibility: public

Description: `Create` initializes a new instance of `TParams`. It calls the inherited constructor with `TParam` ([376](#)) as the collection's item class, and sets `AOwner` as the owner of the collection. Usually, `AOwner` will be the dataset that needs parameters.

See also: `#rtl.classes.TCollection.create` ([??](#)), `TParam` ([376](#))

### 10.49.5 TParams.AddParam

Synopsis: Add a parameter to the collection

Declaration: `procedure AddParam(Value: TParam)`

Visibility: public

Description: `AddParam` adds `Value` to the collection.

Errors: No checks are done on the `TParam` instance. If it is `Nil`, an exception will be raised.

See also: `TParam` ([376](#)), `#rtl.classes.tcollection.add` ([??](#))

### 10.49.6 TParams.AssignValues

Synopsis: Copy values from another collection

Declaration: `procedure AssignValues(Value: TParams)`

Visibility: public

Description: `AssignValues` examines all `TParam` ([376](#)) instances in `Value`, and looks in its own items for a `TParam` instance with the same name. If it is found, then the value and type of the parameter are copied (using `TParam.Assign` ([??](#))). If it is not found, nothing is done.

See also: `TParam` ([376](#)), `TParam.Assign` ([??](#))

### 10.49.7 TParams.CreateParam

Synopsis: Create and add a new parameter to the collection

Declaration: `function CreateParam(FldType: TFieldType; const ParamName: String;`  
`ParamType: TParamType) : TParam`

Visibility: public

**Description:** `CreateParam` creates a new `TParam` (376) instance with datatype equal to `fldType`, Name equal to `ParamName` and sets its `ParamType` property to `ParamType`. The parameter is then added to the collection.

See also: `TParam` (376), `TParam.Name` (??), `TParam.Datatype` (??), `TParam.Paramtype` (??)

### 10.49.8 TParams.FindParam

**Synopsis:** Find a parameter with given name

**Declaration:** `function FindParam(const Value: String) : TParam`

Visibility: public

**Description:** `FindParam` searches the collection for the `TParam` (376) instance with property `Name` equal to `Value`. It will return the last instance with the given name, and will only return one instance. If no match is found, `Nil` is returned.

**Remark:** A `TParams` collection can have 2 `TParam` instances with the same name: no checking for duplicates is done.

See also: `TParam.Name` (??), `TParams.ParamByName` (??), `TParams.GetParamList` (??)

### 10.49.9 TParams.GetParamList

**Synopsis:** Fetch a list of `TParam` instances

**Declaration:** `procedure GetParamList(List: TList;const ParamNames: String)`

Visibility: public

**Description:** `GetParamList` examines the parameter names in the semicolon-separated list `ParamNames`. It searches each `TParam` instance from the names in the list and adds it to `List`.

**Errors:** If the `ParamNames` list contains an unknown parameter name, then an exception is raised. Whitespace is not discarded.

See also: `TParam` (376), `TParam.Name` (??), `TParams.ParamByName` (??)

### 10.49.10 TParams.IsEqual

**Synopsis:** Is the list of parameters equal

**Declaration:** `function IsEqual(Value: TParams) : Boolean`

Visibility: public

**Description:** `IsEqual` compares the parameter count of `Value` and if it matches, it compares all `TParam` items of `Value` with the items it owns. If all items are equal (all properties match), then `True` is returned. The items are compared on index, so the order is important.

See also: `TParam` (376)

### 10.49.11 TParams.ParamByName

Synopsis: Return a parameter by name

Declaration: `function ParamByName(const Value: String) : TParam`

Visibility: public

Description: `ParamByName` searches the collection for the `TParam` (376) instance with property `Name` equal to `Value`. It will return the last instance with the given name, and will only return one instance. If no match is found, an exception is raised.

**Remark:** A `TParams` collection can have 2 `TParam` instances with the same name: no checking for duplicates is done.

See also: `TParam.Name` (??), `TParams.FindParam` (??), `TParams.GetParamList` (??)

### 10.49.12 TParams.ParseSQL

Synopsis: Parse SQL statement, replacing parameter names with SQL parameter placeholders

Declaration: `function ParseSQL(SQL: String; DoCreate: Boolean) : String; Overload`  
`function ParseSQL(SQL: String; DoCreate: Boolean; EscapeSlash: Boolean;`  
`EscapeRepeat: Boolean; ParameterStyle: TParamStyle)`  
`: String; Overload`  
`function ParseSQL(SQL: String; DoCreate: Boolean; EscapeSlash: Boolean;`  
`EscapeRepeat: Boolean; ParameterStyle: TParamStyle;`  
`var ParamBinding: TParamBinding) : String; Overload`  
`function ParseSQL(SQL: String; DoCreate: Boolean; EscapeSlash: Boolean;`  
`EscapeRepeat: Boolean; ParameterStyle: TParamStyle;`  
`var ParamBinding: TParamBinding;`  
`var ReplaceString: String) : String; Overload`

Visibility: public

Description: `ParseSQL` parses the SQL statement for parameter names in the form `:ParamName`. It replaces them with a SQL parameter placeholder. If `DoCreate` is `True` then a `TParam` instance is added to the collection with the found parameter name.

The parameter placeholder is determined by the `ParameterStyle` property, which can have the following values:

**psInterbaseParameters** are specified by a `?` character

**psPostgreSQLParameters** are specified by a `$N` character.

**psSimulatedParameters** are specified by a `$N` character.

`psInterbase` is the default.

If the `EscapeSlash` parameter is `True`, then backslash characters are used to quote the next character in the SQL statement. If it is `False`, the backslash character is regarded as a normal character.

If the `EscapeRepeat` parameter is `True` (the default) then embedded quotes in string literals are escaped by repeating themselves. If it is `false` then they should be quoted with backslashes.

`ParamBinding`, if specified, is filled with the indexes of the parameter instances in the parameter collection: for each SQL parameter placeholder, the index of the corresponding `TParam` instance is returned in the array.



`ReplaceString`, if specified, contains the placeholder used for the parameter names (by default, \$). It has effect only when `ParameterStyle` equals `psSimulated`.

The function returns the SQL statement with the parameter names replaced by placeholders.

See also: `TParam` (376), `TParam.Name` (??), `TParamStyle` (228)

### 10.49.13 TParams.RemoveParam

Synopsis: Remove a parameter from the collection

Declaration: `procedure RemoveParam(Value: TParam)`

Visibility: public

Description: `RemoveParam` removes the parameter `Value` from the collection, but does not free the instance.

Errors: `Value` must be a valid instance, or an exception will be raised.

See also: `TParam` (376)

### 10.49.14 TParams.CopyParamValuesFromDataset

Synopsis: Copy parameter values from a the fields in a dataset.

Declaration: `procedure CopyParamValuesFromDataset (ADataset: TDataSet;  
CopyBound: Boolean)`

Visibility: public

Description: `CopyParamValuesFromDataset` assigns values to all parameters in the collection by searching in `ADataset` for fields with the same name, and assigning the value of the field to the `TParam` instances using `TParam.AssignField` (??). By default, this operation is only performed on `TParam` instances with their `Bound` (??) property set to `False`. If `CopyBound` is true, then the operation is performed on all `TParam` instances in the collection.

Errors: If, for some `TParam` instance, `ADataset` misses a field with the same name, an `EDatabaseError` exception will be raised.

See also: `TParam` (376), `TParam.Bound` (??), `TParam.AssignField` (??), `TDataSet` (267), `TDataSet.FieldName` (??)

### 10.49.15 TParams.Dataset

Synopsis: Dataset that owns the `TParams` instance

Declaration: `Property Dataset : TDataSet`

Visibility: public

Access: Read

Description: `Dataset` is the `TDataSet` (267) instance that was specified when the `TParams` instance was created.

See also: `TParams.Create` (??), `TDataSet` (267)

### 10.49.16 TParams.Items

Synopsis: Indexed access to TParams instances in the collection

Declaration: `Property Items[Index: Integer]: TParam; default`

Visibility: public

Access: Read,Write

Description: `Items` is overridden by `TParams` so it has the proper type (`TParam`). The `Index` runs from 0 to `Count-1`.

See also: `TParams` ([388](#))

### 10.49.17 TParams.ParamValues

Synopsis: Named access to the parameter values.

Declaration: `Property ParamValues[ParamName: String]: Variant`

Visibility: public

Access: Read,Write

Description: `ParamValues` provides access to the parameter values (`TParam.Value` (??)) by name. It is equivalent to reading and writing

`ParamByName(ParamName).Value`

See also: `TParam.Value` (??), `TParams.ParamByName` (??)

## 10.50 TSmallIntField

### 10.50.1 Description

`TSmallIntField` is the class created when a dataset must manage 16-bit signed integer data, of datatype `ftSmallInt`. It exposes no new properties, but simply overrides some methods to manage 16-bit signed integer data.

It should never be necessary to create an instance of `TSmallIntField` manually, a field of this class will be instantiated automatically for each smallint field when a dataset is opened.

See also: `TField` ([315](#)), `TNumericField` ([374](#)), `TLongintField` ([365](#)), `TWordField` ([400](#))

### 10.50.2 Method overview

Page	Property	Description
<a href="#">394</a>	Create	Create a new instance of the <code>TSmallIntField</code> class.

### 10.50.3 TSmallintField.Create

Synopsis: Create a new instance of the TSmallintField class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the TSmallintField (393) class. It calls the inherited constructor and then simply sets some of the TField (315) properties to work with 16-bit signed integer data.

See also: TField (315)

## 10.51 TStringField

### 10.51.1 Description

TStringField is the class used whenever a dataset has to handle a string field type (data type `ftString`). This class overrides some of the standard TField (315) methods to handle string data, and introduces some properties that are only pertinent for data fields of string type. It should never be necessary to create an instance of TStringField manually, a field of this class will be instantiated automatically for each string field when a dataset is opened.

See also: TField (315), TWideStringField (399), TDataset (267)

### 10.51.2 Method overview

Page	Property	Description
394	CheckTypeSize	
394	Create	Create a new instance of the TStringField class
395	SetFieldType	Set the field type

### 10.51.3 Property overview

Page	Property	Access	Description
396	EditMask		Specify an edit mask for an edit control
395	FixedChar	rw	Is the string declared with a fixed length ?
396	Size		Maximum size of the string
395	Transliterate	rw	Should the field value be transliterated when reading or writing
395	Value	rw	Value of the field as a string

### 10.51.4 TStringField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(AValue: LongInt); Override`

Visibility: `default`

### 10.51.5 TStringField.Create

Synopsis: Create a new instance of the TStringField class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` is used to create a new instance of the `TStringField` class. It initializes some `TField` (315) properties after having called the inherited constructor.

### 10.51.6 TStringField.SetFieldType

Synopsis: Set the field type

Declaration: `procedure SetFieldType(AValue: TFieldType); Override`

Visibility: public

Description: `SetFieldType` is overridden in `TStringField` (394) to check the data type more accurately (`ftString` and `ftFixedChar`). No extra functionality is added.

See also: `TField.DataType` (??)

### 10.51.7 TStringField.FixedChar

Synopsis: Is the string declared with a fixed length ?

Declaration: `Property FixedChar : Boolean`

Visibility: public

Access: Read,Write

Description: `FixedChar` is `True` if the underlying data engine has declared the field with a fixed length, as in a SQL `CHAR()` declaration: the field's value will then always be padded with as many spaces as needed to obtain the declared length of the field. If it is `False` then the declared length is simply the maximum length for the field, and no padding with spaces is performed.

### 10.51.8 TStringField.Transliterate

Synopsis: Should the field value be transliterated when reading or writing

Declaration: `Property Transliterate : Boolean`

Visibility: public

Access: Read,Write

Description: `Transliterate` can be set to `True` if the field's contents should be transliterated prior to copying it from or to the field's buffer. Transliteration is done by a method of `TDataset`: `TDataset.Translate` (??).

See also: `TDataset.Translate` (??)

### 10.51.9 TStringField.Value

Synopsis: Value of the field as a string

Declaration: `Property Value : String`

Visibility: public

Access: Read,Write

**Description:** `Value` is overridden in `TField` to return the value of the field as a string. It returns the contents of `TField.AsString` (??) when read, or sets the `AsString` property when written to.

See also: `TField.AsString` (??), `TField.Value` (??)

### 10.51.10 TStringField.EditMask

**Synopsis:** Specify an edit mask for an edit control

**Declaration:** `Property EditMask :`

**Visibility:** published

**Access:**

**Description:** `EditMask` can be used to specify an edit mask for controls that allow to edit this field. It has no effect on the field value, and serves only to ensure that the user can enter only correct data for this field.

`TStringField` just changes the visibility of the `EditMask` property, it is introduced in `TField`.

For more information on valid edit masks, see the documentation of the GUI controls.

See also: `TField.EditMask` (??)

### 10.51.11 TStringField.Size

**Synopsis:** Maximum size of the string

**Declaration:** `Property Size :`

**Visibility:** published

**Access:**

**Description:** `Size` is made published by the `TStringField` class so it can be set in the IDE: it is the declared maximum size of the string (in characters) and is used to calculate the size of the dataset buffer.

See also: `TField.Size` (??)

## 10.52 TTimeField

### 10.52.1 Description

`TimeField` is the class used when a dataset must manage data of type time. (`TField.DataType` (??) equals `ftTime`). It initializes some of the properties of the `TField` (315) class to be able to work with time fields.

It should never be necessary to create an instance of `TTimeField` manually, a field of this class will be instantiated automatically for each time field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TDateTimeField` (307), `TDateField` (307)

### 10.52.2 Method overview

Page	Property	Description
397	Create	Create a new instance of a <code>TTimeField</code> class.

### 10.52.3 TTimeField.Create

**Synopsis:** Create a new instance of a `TTimeField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` initializes a new instance of the `TTimeField` class. It calls the inherited destructor, and then sets some `TField` (315) properties to configure the instance for working with time values.

See also: `TField` (315)

## 10.53 TVarBytesField

### 10.53.1 Description

`TVarBytesField` is the class used when a dataset must manage data of variable-size binary type. (`TField.DataType` (??) equals `ftVarBytes`). It initializes some of the properties of the `TField` (315) class to be able to work with variable-size byte fields.

It should never be necessary to create an instance of `TVarBytesField` manually, a field of this class will be instantiated automatically for each variable-sized binary data field when a dataset is opened.

See also: `TDataset` (267), `TField` (315), `TBytesField` (249)

### 10.53.2 Method overview

Page	Property	Description
397	Create	Create a new instance of a <code>TVarBytesField</code> class.

### 10.53.3 TVarBytesField.Create

**Synopsis:** Create a new instance of a `TVarBytesField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` initializes a new instance of the `TVarBytesField` class. It calls the inherited destructor, and then sets some `TField` (315) properties to configure the instance for working with variable-size binary data values.

See also: `TField` (315)

## 10.54 TVariantField

### 10.54.1 Description

`TVariantField` is the class used when a dataset must manage native variant-typed data. (`TField.DataType` (??) equals `ftVariant`). It initializes some of the properties of the `TField` (315) class and overrides some of its methods to be able to work with variant data.

It should never be necessary to create an instance of `TVariantField` manually, a field of this class will be instantiated automatically for each variant field when a dataset is opened.

See also: TDataSet (267), TField (315)

### 10.54.2 Method overview

Page	Property	Description
<a href="#">398</a>	CheckTypeSize	
<a href="#">398</a>	Create	Create a new instance of the TVariantField class

### 10.54.3 TVariantField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(aValue: Integer); Override`

Visibility: default

### 10.54.4 TVariantField.Create

Synopsis: Create a new instance of the TVariantField class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: Create initializes a new instance of the TVariantField class. It calls the inherited destructor, and then sets some TField (315) properties to configure the instance for working with variant values.

See also: TField (315)

## 10.55 TWideMemoField

### 10.55.1 Description

TWideMemoField is the class used when a dataset must manage memo (Text BLOB) data. (TField.DataType (??) equals ftWideMemo). It initializes some of the properties of the TField (315) class. All methods to be able to work with widestring memo fields have been implemented in the TBlobField (243) parent class.

It should never be necessary to create an instance of TWideMemoField manually, a field of this class will be instantiated automatically for each widestring memo field when a dataset is opened.

See also: TDataSet (267), TField (315), TBlobField (243), TMemoField (372), TGraphicField (356)

### 10.55.2 Method overview

Page	Property	Description
<a href="#">399</a>	Create	Create a new instance of the TWideMemoField class

### 10.55.3 Property overview

Page	Property	Access	Description
<a href="#">399</a>	Value	rw	Value of the field's contents as a widestring

### 10.55.4 TWideMemoField.Create

Synopsis: Create a new instance of the `TWideMemoField` class

Declaration: `constructor Create(aOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TWideMemoField` class. It calls the inherited destructor, and then sets some `TField` (315) properties to configure the instance for working with widestring memo values.

See also: `TField` (315)

### 10.55.5 TWideMemoField.Value

Synopsis: Value of the field's contents as a widestring

Declaration: `Property Value : WideString`

Visibility: `public`

Access: `Read,Write`

Description: `Value` is redefined by `TWideMemoField` as a `WideString` value. Reading and writing this property is equivalent to reading and writing the `TField.AsWideString` (??) property.

See also: `TField.Value` (??), `TField.AsWideString` (??)

## 10.56 TWideStringField

### 10.56.1 Description

`TWideStringField` is the string field class instantiated for fields of data type `ftWideString`. This class overrides some of the standard `TField` (315) methods to handle widestring data, and introduces some properties that are only pertinent for data fields of widestring type. It should never be necessary to create an instance of `TWideStringField` manually, a field of this class will be instantiated automatically for each widestring field when a dataset is opened.

See also: `TField` (315), `TStringField` (394), `TDataset` (267)

### 10.56.2 Method overview

Page	Property	Description
<a href="#">400</a>	<code>CheckTypeSize</code>	
<a href="#">400</a>	<code>Create</code>	Create a new instance of the <code>TWideStringField</code> class.
<a href="#">400</a>	<code>SetFieldType</code>	Set the field type

### 10.56.3 Property overview

Page	Property	Access	Description
<a href="#">400</a>	<code>Value</code>	<code>rw</code>	Value of the field as a widestring



### 10.56.4 TWideStringField.CheckTypeSize

Declaration: `class procedure CheckTypeSize(aValue: Integer); Override`

Visibility: default

### 10.56.5 TWideStringField.Create

Synopsis: Create a new instance of the `TWideStringField` class.

Declaration: `constructor Create(aOwner: TComponent); Override`

Visibility: public

Description: `Create` is used to create a new instance of the `TWideStringField` class. It initializes some `TField` (315) properties after having called the inherited constructor.

### 10.56.6 TWideStringField.SetFieldType

Synopsis: Set the field type

Declaration: `procedure SetFieldType(AValue: TFieldType); Override`

Visibility: public

Description: `SetFieldType` is overridden in `TWideStringField` (399) to check the data type more accurately (`ftWideString` and `ftFixedWideChar`). No extra functionality is added.

See also: `TField.DataType` (??)

### 10.56.7 TWideStringField.Value

Synopsis: Value of the field as a widestring

Declaration: `Property Value : WideString`

Visibility: public

Access: Read,Write

Description: `Value` is overridden by the `TWideStringField` to return a `WideString` value. It is the same value as the `TField.AsWideString` (??) property.

See also: `TField.AsWideString` (??), `TField.Value` (??)

## 10.57 TWordField

### 10.57.1 Description

`TWordField` is the class created when a dataset must manage 16-bit unsigned integer data, of datatype `ftWord`. It exposes no new properties, but simply overrides some methods to manage 16-bit unsigned integer data.

It should never be necessary to create an instance of `TWordField` manually, a field of this class will be instantiated automatically for each word field when a dataset is opened.

See also: `TField` (315), `TNumericField` (374), `TLongintField` (365), `TSmallIntField` (393)

### 10.57.2 Method overview

Page	Property	Description
<a href="#">401</a>	Create	Create a new instance of the TWordField class.

### 10.57.3 TWordField.Create

**Synopsis:** Create a new instance of the TWordField class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** public

**Description:** Create initializes a new instance of the TWordField ([400](#)) class. It calls the inherited constructor and then simply sets some of the TField ([315](#)) properties to work with 16-bit unsigned integer data.

**See also:** TField ([315](#))

## Chapter 11

# Reference for unit 'dbugintf'

### 11.1 Overview

Use `dbugintf` to add debug messages to your application. The messages are not sent to standard output, but are sent to a debug server process which collects messages from various clients and displays them somehow on screen.

The unit is transparent in its use: it does not need initialization, it will start the debug server by itself if it can find it: the program should be called `debugserver` and should be in the `PATH`. When the first debug message is sent, the unit will initialize itself.

The FCL contains a sample debug server (`dbugsvr`) which can be started in advance, and which writes debug message to the console (both on Windows and Linux). The Lazarus project contains a visual application which displays the messages in a GUI.

The `dbugintf` unit relies on the SimpleIPC (534) mechanism to communicate with the debug server, hence it works on all platforms that have a functional version of that unit. It also uses `TProcess` to start the debug server if needed, so the process (503) unit should also be functional.

### 11.2 Writing a debug server

Writing a debug server is relatively easy. It should instantiate a `TSimpleIPCServer` class from the SimpleIPC (534) unit, and use the `DebugServerID` as `ServerID` identification. This constant, as well as the record containing the message which is sent between client and server is defined in the `msgintf` unit.

The `dbugintf` unit relies on the SimpleIPC (534) mechanism to communicate with the debug server, hence it works on all platforms that have a functional version of that unit. It also uses `TProcess` to start the debug server if needed, so the process (503) unit should also be functional.

### 11.3 Constants, types and variables

#### 11.3.1 Resource strings

```
SEntering = '''> Entering '''
```

String used when sending method enter message.

```
SExiting = '''< Exiting '''
```

String used when sending method exit message.

```
SProcessID = '''Process %s'''
```

String used when sending identification message to the server.

```
SSeparator = '''>-----<'''
```

String used when sending a separator line.

```
SServerStartFailed = '''Failed to start debugserver. (%s)'''
```

String used to display an error message when the start of the debug server failed

### 11.3.2 Constants

```
SendError : String = ''
```

Whenever a call encounters an exception, the exception message is stored in this variable.

### 11.3.3 Types

```
TDebugLevel = (dlInformation, dlWarning, dlError)
```

Table 11.1: Enumeration values for type TDebugLevel

Value	Explanation
dlError	Error message
dlInformation	Informational message
dlWarning	Warning message

TDebugLevel indicates the severity level of the debug message to be sent. By default, an informational message is sent.

## 11.4 Procedures and functions

### 11.4.1 GetDebuggingEnabled

**Synopsis:** Check if sending of debug messages is enabled.

**Declaration:** `function GetDebuggingEnabled : Boolean`

**Visibility:** default

**Description:** GetDebuggingEnabled returns the value set by the last call to SetDebuggingEnabled. It is True by default.

**See also:** SetDebuggingEnabled ([407](#)), SendDebug ([404](#))

### 11.4.2 InitDebugClient

Synopsis: Initialize the debug client.

Declaration: `function InitDebugClient : Boolean`

Visibility: default

Description: `InitDebugClient` starts the debug server and then performs all necessary initialization of the debug IPC communication channel.

Normally this function should not be called. The `SendDebug` (404) call will initialize the debug client when it is first called.

Errors: None.

See also: `SendDebug` (404), `StartDebugServer` (407)

### 11.4.3 SendBoolean

Synopsis: Send the value of a boolean variable

Declaration: `procedure SendBoolean(const Identifier: String;const Value: Boolean)`

Visibility: default

Description: `SendBoolean` is a simple wrapper around `SendDebug` (404) which sends the name and value of a boolean value as an informational message.

Errors: None.

See also: `SendDebug` (404), `SendDateTime` (404), `SendInteger` (406), `SendPointer` (407)

### 11.4.4 SendDateTime

Synopsis: Send the value of a `TDateTime` variable.

Declaration: `procedure SendDateTime(const Identifier: String;const Value: TDateTime)`

Visibility: default

Description: `SendDateTime` is a simple wrapper around `SendDebug` (404) which sends the name and value of an integer value as an informational message. The value is converted to a string using the `DateTimeToStr` (??) call.

Errors: None.

See also: `SendDebug` (404), `SendBoolean` (404), `SendInteger` (406), `SendPointer` (407)

### 11.4.5 SendDebug

Synopsis: Send a message to the debug server.

Declaration: `procedure SendDebug(const Msg: String)`

Visibility: default

**Description:** `SendDebug` sends the message `Msg` to the debug server as an informational message (debug level `dlInformation`). If no debug server is running, then an attempt will be made to start the server first.

The binary that is started is called `debugserver` and should be somewhere on the `PATH`. A sample binary which writes received messages to standard output is included in the FCL, it is called `dbugsrv`. This binary can be renamed to `debugserver` or can be started before the program is started.

**Errors:** Errors are silently ignored, any exception messages are stored in `SendError` (403).

**See also:** `SendDebugEx` (405), `SendDebugFmt` (405), `SendDebugFmtEx` (405)

### 11.4.6 SendDebugEx

**Synopsis:** Send debug message other than informational messages

**Declaration:** `procedure SendDebugEx(const Msg: String; MType: TDebugLevel)`

**Visibility:** default

**Description:** `SendDebugEx` allows to specify the debug level of the message to be sent in `MType`. By default, `SendDebug` (404) uses informational messages.

Other than that the function of `SendDebugEx` is equal to that of `SendDebug`

**Errors:** None.

**See also:** `SendDebug` (404), `SendDebugFmt` (405), `SendDebugFmtEx` (405)

### 11.4.7 SendDebugFmt

**Synopsis:** Format and send a debug message

**Declaration:** `procedure SendDebugFmt(const Msg: String; const Args: Array of const)`

**Visibility:** default

**Description:** `SendDebugFmt` is a utility routine which formats a message by passing `Msg` and `Args` to `Format` (??) and sends the result to the debug server using `SendDebug` (404). It exists mainly to avoid the `Format` call in calling code.

**Errors:** None.

**See also:** `SendDebug` (404), `SendDebugEx` (405), `SendDebugFmtEx` (405), `#rtl.sysutils.format` (??)

### 11.4.8 SendDebugFmtEx

**Synopsis:** Format and send message with alternate type

**Declaration:** `procedure SendDebugFmtEx(const Msg: String; const Args: Array of const; MType: TDebugLevel)`

**Visibility:** default

**Description:** `SendDebugFmtEx` is a utility routine which formats a message by passing `Msg` and `Args` to `Format` (??) and sends the result to the debug server using `SendDebugEx` (405) with `Debug level MType`. It exists mainly to avoid the `Format` call in calling code.

**Errors:** None.

**See also:** `SendDebug` (404), `SendDebugEx` (405), `SendDebugFmt` (405), `#rtl.sysutils.format` (??)

### 11.4.9 SendInteger

Synopsis: Send the value of an integer variable.

Declaration: `procedure SendInteger(const Identifier: String; const Value: Integer;  
HexNotation: Boolean)`

Visibility: default

Description: `SendInteger` is a simple wrapper around `SendDebug` (404) which sends the name and value of an integer value as an informational message. If `HexNotation` is `True`, then the value will be displayed using hexadecimal notation.

Errors: None.

See also: `SendDebug` (404), `SendBoolean` (404), `SendDateTime` (404), `SendPointer` (407)

### 11.4.10 SendMethodEnter

Synopsis: Send method enter message

Declaration: `procedure SendMethodEnter(const MethodName: String)`

Visibility: default

Description: `SendMethodEnter` sends a "Entering `MethodName`" message to the debug server. After that it increases the message indentation (currently 2 characters). By sending a corresponding `SendMethodExit` (406), the indentation of messages can be decreased again.

By using the `SendMethodEnter` and `SendMethodExit` methods at the beginning and end of a procedure/method, it is possible to visually trace program execution.

Errors: None.

See also: `SendDebug` (404), `SendMethodExit` (406), `SendSeparator` (407)

### 11.4.11 SendMethodExit

Synopsis: Send method exit message

Declaration: `procedure SendMethodExit(const MethodName: String)`

Visibility: default

Description: `SendMethodExit` sends a "Exiting `MethodName`" message to the debug server. After that it decreases the message indentation (currently 2 characters). By sending a corresponding `SendMethodEnter` (406), the indentation of messages can be increased again.

By using the `SendMethodEnter` and `SendMethodExit` methods at the beginning and end of a procedure/method, it is possible to visually trace program execution.

Note that the indentation level will not be made negative.

Errors: None.

See also: `SendDebug` (404), `SendMethodEnter` (406), `SendSeparator` (407)

### 11.4.12 SendPointer

Synopsis: Send the value of a pointer variable.

Declaration: `procedure SendPointer(const Identifier: String;const Value: Pointer)`

Visibility: default

Description: `SendInteger` is a simple wrapper around `SendDebug` (404) which sends the name and value of a pointer value as an informational message. The pointer value is displayed using hexadecimal notation.

Errors: None.

See also: `SendDebug` (404), `SendBoolean` (404), `SendDateTime` (404), `SendInteger` (406)

### 11.4.13 SendSeparator

Synopsis: Send a separator message

Declaration: `procedure SendSeparator`

Visibility: default

Description: `SendSeparator` is a simple wrapper around `SendDebug` (404) which sends a short horizontal line to the debug server. It can be used to visually separate execution of blocks of code or blocks of values.

Errors: None.

See also: `SendDebug` (404), `SendMethodEnter` (406), `SendMethodExit` (406)

### 11.4.14 SetDebuggingEnabled

Synopsis: Temporary enables or disables debugging

Declaration: `procedure SetDebuggingEnabled(const AValue: Boolean)`

Visibility: default

Description: `SetDebuggingEnabled` can be used to temporarily enable or disable sending of debug messages: this allows to control the amount of messages sent to the debug server without having to remove the `SendDebug` (404) statements. By default, debugging is enabled. If set to false, debug messages are simply discarded till debugging is enabled again.

A value of `True` enables sending of debug messages. A value of `False` disables sending.

Errors: None.

See also: `GetDebuggingEnabled` (403), `SendDebug` (404)

### 11.4.15 StartDebugServer

Synopsis: Start the debug server

Declaration: `function StartDebugServer : Integer`

Visibility: default



**Description:** `StartDebugServer` attempts to start the debug server. The process started is called `debugserver` and should be located in the `PATH`.

Normally this function should not be called. The `SendDebug` (404) call will attempt to start the server by itself if it is not yet running.

**Errors:** On error, `False` is returned.

**See also:** `SendDebug` (404), `InitDebugClient` (404)

# Chapter 12

## Reference for unit 'dbugmsg'

### 12.1 Used units

Table 12.1: Used units by unit 'dbugmsg'

Name	Page
Classes	??
System	??

### 12.2 Overview

`dbugmsg` is an auxiliary unit used in the `dbugintf` ([402](#)) unit. It defines the message protocol used between the debug unit and the debug server.

### 12.3 Constants, types and variables

#### 12.3.1 Constants

```
DebugServerID : String = 'fpcdebugserver'
```

`DebugServerID` is a string which is used when creating the message protocol, it is used when identifying the server in the (platform dependent) client-server protocol.

```
lctError = 2
```

`lctError` is the identification of error messages.

```
lctIdentify = 3
```

`lctIdentify` is sent by the client to a server when it first connects. It's the first message, and contains the name of client application.

```
lctInformation = 0
```

`lctInformation` is the identification of informational messages.

`lctStop = -1`

`lctStop` is sent by the client to a server when it disconnects.

`lctWarning = 1`

`lctWarning` is the identification of warning messages.

### 12.3.2 Types

```
TDebugMessage = record
  MsgType : Integer;
  MsgTimeStamp : TDateTime;
  Msg : String;
end
```

`TDebugMessage` is a record that describes the message passed from the client to the server. It should not be passed directly in shared memory, as the string containing the message is allocated on the heap. Instead, the `WriteDebugMessageToStream` (411) and `ReadDebugMessageFromStream` (410) can be used to read or write the message from/to a stream.

## 12.4 Procedures and functions

### 12.4.1 DebugMessageName

**Synopsis:** Return the name of the debug message

**Declaration:** `function DebugMessageName(msgType: Integer) : String`

**Visibility:** default

**Description:** `DebugMessageName` returns the name of the message type. It can be used to examine the `MsgType` field of a `TDebugMessage` (410) record, and if `msgType` contains a known type, it returns a string describing this type.

**Errors:** If `MsgType` contains an unknown type, 'Unknown' is returned.

### 12.4.2 ReadDebugMessageFromStream

**Synopsis:** Read a message from stream

**Declaration:** `procedure ReadDebugMessageFromStream(AStream: TStream;
var Msg: TDebugMessage)`

**Visibility:** default

**Description:** `ReadDebugMessageFromStream` reads a `TDebugMessage` (410) record (`Msg`) from the stream `AStream`.

The record is not read in a byte-ordering safe way, i.e. it cannot be exchanged between little- and big-endian systems.

**Errors:** If the stream contains not enough bytes or is malformed, then an exception may be raised.

**See also:** `TDebugMessage` (410), `WriteDebugMessageToStream` (411)

### 12.4.3 WriteDebugMessageToStream

Synopsis: Write a message to stream

Declaration: `procedure WriteDebugMessageToStream(AStream: TStream;  
const Msg: TDebugMessage)`

Visibility: default

Description: `WriteDebugMessageFromStream` writes a `TDebugMessage` (410) record (Msg) to the stream `AStream`.

The record is not written in a byte-ordering safe way, i.e. it cannot be exchanged between little- and big-endian systems.

Errors: A stream write error may occur if the stream cannot be written to.

See also: `TDebugMessage` (410), `ReadDebugMessageFromStream` (410)

# Chapter 13

## Reference for unit 'eventlog'

### 13.1 Used units

Table 13.1: Used units by unit 'eventlog'

Name	Page
Classes	??
System	??
sysutils	??

### 13.2 Overview

The EventLog unit implements the TEventLog (414) component, which is a component that can be used to send log messages to the system log (if it is available) or to a file.

### 13.3 Constants, types and variables

#### 13.3.1 Resource strings

SErrLogFailedMsg = '''Failed to log entry (Error: %s)'''

Message used to format an error when an error exception is raised.

SLogCustom = '''Custom (%d)'''

Custom message formatting string

SLogDebug = '''Debug'''

Debug message name

SLogError = '''Error'''

Error message name

```
SLogInfo = '''Info'''
```

Informational message name

```
SLogWarning = '''Warning'''
```

Warning message name

### 13.3.2 Types

```
TLogCategoryEvent = procedure(Sender: TObject;var Code: Word) of object
```

`TLogCategoryEvent` is the event type for the `TEventLog.OnGetCustomCategory` (??) event handler. It should return a OS event category code for the `etCustom` log event type in the `Code` parameter.

```
TLogCodeEvent = procedure(Sender: TObject;var Code: DWord) of object
```

`TLogCodeEvent` is the event type for the `OnGetCustomEvent` (??) and `OnGetCustomEventID` (??) event handlers. It should return a OS system log code for the `etCustom` log event or event ID type in the `Code` parameter.

```
TLogType = (ltSystem,ltFile)
```

Table 13.2: Enumeration values for type `TLogType`

Value	Explanation
<code>ltFile</code>	Write to file
<code>ltSystem</code>	Use the system log

`TLogType` determines where the log messages are written. It is the type of the `TEventLog.LogType` (??) property. It can have 2 values:

**ltFile** This is used to write all messages to file. if no system logging mechanism exists, this is used as a fallback mechanism.

**ltSystem** This is used to send all messages to the system log mechanism. Which log mechanism this is, depends on the operating system.

## 13.4 ELogError

### 13.4.1 Description

`ELogError` is the exception used in the `TEventLog` (414) component to indicate errors.

See also: `TEventLog` (414)

## 13.5 TEventLog

### 13.5.1 Description

TEventLog is a component which can be used to send messages to the system log. In case no system log exists (such as on Windows 95/98 or DOS), the messages are written to a file. Messages can be logged using the general Log (??) call, or the specialized Warning (??), Error (??), Info (??) or Debug (??) calls, which have the event type predefined.

See also: Log (??), Warning (??), Error (??), Info (??), Debug (??)

### 13.5.2 Method overview

Page	Property	Description
<a href="#">417</a>	Debug	Log a debug message
<a href="#">414</a>	Destroy	Clean up TEventLog instance
<a href="#">417</a>	Error	Log an error message to
<a href="#">415</a>	EventTypeToString	Create a string representation of an event type
<a href="#">417</a>	Info	Log an informational message
<a href="#">416</a>	Log	Log a message to the system log.
<a href="#">415</a>	RegisterMessageFile	Register message file
<a href="#">416</a>	UnRegisterMessageFile	Unregister the message file (needed on windows only)
<a href="#">416</a>	Warning	Log a warning message.

### 13.5.3 Property overview

Page	Property	Access	Description
<a href="#">418</a>	Active	rw	Activate the log mechanism
<a href="#">417</a>	AppendContent	rw	Control whether output is appended to an existing file
<a href="#">420</a>	CustomLogType	rw	Custom log type ID
<a href="#">419</a>	DefaultEventType	rw	Default event type for the Log ( <a href="#">416</a> ) call.
<a href="#">420</a>	EventIDOffset	rw	Offset for event ID messages identifiers
<a href="#">419</a>	FileName	rw	File name for log file
<a href="#">418</a>	Identification	rw	Identification string for messages
<a href="#">418</a>	LogType	rw	Log type
<a href="#">420</a>	OnGetCustomCategory	rw	Event to retrieve custom message category
<a href="#">421</a>	OnGetCustomEvent	rw	Event to retrieve custom event Code
<a href="#">421</a>	OnGetCustomEventID	rw	Event to retrieve custom event ID
<a href="#">418</a>	RaiseExceptionOnError	rw	Determines whether logging errors are reported or ignored
<a href="#">419</a>	TimeStampFormat	rw	Format for the timestamp string

### 13.5.4 TEventLog.Destroy

Synopsis: Clean up TEventLog instance

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy cleans up the TEventLog instance. It cleans any log structures that might have been set up to perform logging, by setting the Active (??) property to False.

See also: Active (??)

### 13.5.5 TEventLog.EventTypeToString

Synopsis: Create a string representation of an event type

Declaration: `function EventTypeToString(E: TEventType) : String`

Visibility: public

Description: `EventTypeToString` converts the event type `E` to a suitable string representation for logging purposes. It's mainly used when writing messages to file, as the system log usually has it's own mechanisms for displaying the various event types.

See also: `#rtl.sysutils.TEventType` (??)

### 13.5.6 TEventLog.RegisterMessageFile

Synopsis: Register message file

Declaration: `function RegisterMessageFile(AFileName: String) : Boolean; Virtual`

Visibility: public

Description: `RegisterMessageFile` is used on Windows to register the file `AFileName` containing the formatting strings for the system messages. This should be a file containing resource strings. If `AFileName` is empty, the filename of the application binary is substituted.

When a message is logged to the windows system log, Windows looks for a formatting string in the file registered with this call.

There are 2 kinds of formatting strings:

**Category strings** these should be numbered from 1 to 4

1Should contain the description of the `etInfo` event type.

2Should contain the description of the `etWarning` event type.

4Should contain the description of the `etError` event type.

4Should contain the description of the `etDebug` event type.

None of these strings should have a string substitution placeholder.

The second type of strings are the **message definitions**. Their number starts at `EventIDOffset` (??) (default is 1000) and each string should have 1 placeholder.

Free Pascal comes with a `fclel.res` resource file which contains default values for the 8 strings, in english. It can be linked in the application binary with the statement

```
{ $R fclel.res }
```

This file is generated from the `fclel.mc` and `fclel.rc` files that are distributed with the Free Pascal sources.

If the strings are not registered, windows will still display the event messages, but they will not be formatted nicely.

Note that while any messages logged with the event logger are displayed in the event viewern Windows locks the file registered here. This usually means that the binary is locked.

On non-windows operating systems, this call is ignored.

Errors: If `AFileName` is invalid, false is returned.



### 13.5.7 TEventLog.UnRegisterMessageFile

Synopsis: Unregister the message file (needed on windows only)

Declaration: `function UnRegisterMessageFile : Boolean; Virtual`

Visibility: `public`

Description: `UnRegisterMessageFile` can be used to unregister a message file previously registered with `TEventLog.RegisterMessageFile (??)`. This function is usable only on windows, it has no effect on other platforms. Note that windows locks the registered message file while viewing messages, so unregistering helps to avoid file locks while event viewer is open.

See also: `TEventLog.RegisterMessageFile (??)`

### 13.5.8 TEventLog.Log

Synopsis: Log a message to the system log.

Declaration: `procedure Log (EventType: TEventType; const Msg: String); Overload`  
`procedure Log (EventType: TEventType; const Fmt: String;`  
`Args: Array of const); Overload`  
`procedure Log (const Msg: String); Overload`  
`procedure Log (const Fmt: String; Args: Array of const); Overload`

Visibility: `public`

Description: `Log` sends a log message to the system log. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters. If `EventType` is specified, then it is used as the message event type. If `EventType` is omitted, then the event type is determined from `Default-EventType (??)`.

If `EventType` is `etCustom`, then the `OnGetCustomEvent (??)`, `OnGetCustomEventID (??)` and `OnGetCustomCategory (??)`.

The other logging calls: `Info (??)`, `Warning (??)`, `Error (??)` and `Debug (??)` use the `Log` call to do the actual work.

See also: `Info (??)`, `Warning (??)`, `Error (??)`, `Debug (??)`, `OnGetCustomEvent (??)`, `OnGetCustomEventID (??)`, `OnGetCustomCategory (??)`

### 13.5.9 TEventLog.Warning

Synopsis: Log a warning message.

Declaration: `procedure Warning (const Msg: String); Overload`  
`procedure Warning (const Fmt: String; Args: Array of const); Overload`

Visibility: `public`

Description: `Warning` is a utility function which logs a message with the `etWarning` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `Log (??)`, `Info (??)`, `Error (??)`, `Debug (??)`

### 13.5.10 TEventLog.Error

Synopsis: Log an error message to

Declaration: `procedure Error(const Msg: String); Overload`  
`procedure Error(const Fmt: String; Args: Array of const); Overload`

Visibility: public

Description: `Error` is a utility function which logs a message with the `etError` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `Log (??)`, `Info (??)`, `Warning (??)`, `Debug (??)`

### 13.5.11 TEventLog.Debug

Synopsis: Log a debug message

Declaration: `procedure Debug(const Msg: String); Overload`  
`procedure Debug(const Fmt: String; Args: Array of const); Overload`

Visibility: public

Description: `Debug` is a utility function which logs a message with the `etDebug` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `Log (??)`, `Info (??)`, `Warning (??)`, `Error (??)`

### 13.5.12 TEventLog.Info

Synopsis: Log an informational message

Declaration: `procedure Info(const Msg: String); Overload`  
`procedure Info(const Fmt: String; Args: Array of const); Overload`

Visibility: public

Description: `Info` is a utility function which logs a message with the `etInfo` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `Log (??)`, `Warning (??)`, `Error (??)`, `Debug (??)`

### 13.5.13 TEventLog.AppendContent

Synopsis: Control whether output is appended to an existing file

Declaration: `Property AppendContent : Boolean`

Visibility: published

Access: Read, Write

Description: `AppendContent` determines what is done when the log type is `ltFile` and a log file already exists. If the log file already exists, then the default behaviour (`AppendContent=False`) is to re-create the log file when the log is activated. If `AppendContent` is `True` then output will be appended to the existing file.

See also: `LogType (??)`, `FileName (??)`

### 13.5.14 TEventLog.Identification

Synopsis: Identification string for messages

Declaration: `Property Identification : String`

Visibility: published

Access: Read,Write

Description: `Identification` is used as a string identifying the source of the messages in the system log. If it is empty, the filename part of the application binary is used.

See also: `Active (??)`, `TimeStampFormat (??)`

### 13.5.15 TEventLog.LogType

Synopsis: Log type

Declaration: `Property LogType : TLogType`

Visibility: published

Access: Read,Write

Description: `LogType` is the type of the log: if it is `ltSystem`, then the system log is used, if it is available. If it is `ltFile` or there is no system log available, then the log messages are written to a file. The name for the log file is taken from the `FileName (??)` property.

See also: `FileName (??)`

### 13.5.16 TEventLog.Active

Synopsis: Activate the log mechanism

Declaration: `Property Active : Boolean`

Visibility: published

Access: Read,Write

Description: `Active` determines whether the log mechanism is active: if set to `True`, the component connects to the system log mechanism, or opens the log file if needed. Any attempt to log a message while the log is not active will try to set this property to `True`. Disconnecting from the system log or closing the log file is done by setting the `Active` property to `False`.

If the connection to the system logger fails, or the log file cannot be opened, then setting this property may result in an exception.

See also: `Log (??)`

### 13.5.17 TEventLog.RaiseExceptionOnError

Synopsis: Determines whether logging errors are reported or ignored

Declaration: `Property RaiseExceptionOnError : Boolean`

Visibility: published

Access: Read,Write

**Description:** `RaiseExceptionOnError` determines whether an error during a logging operation will be signaled with an exception or not. If set to `False`, errors will be silently ignored, thus not disturbing normal operation of the program.

### 13.5.18 TEventLog.DefaultEventType

**Synopsis:** Default event type for the `Log` (416) call.

**Declaration:** `Property DefaultEventType : TEventType`

**Visibility:** published

**Access:** Read,Write

**Description:** `DefaultEventType` is the event type used by the `Log` (??) call if it's `EventType` parameter is omitted.

**See also:** `Log` (??)

### 13.5.19 TEventLog.FileName

**Synopsis:** File name for log file

**Declaration:** `Property FileName : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `FileName` is the name of the log file used to log messages if no system logger is available or the `LogType` (??) is `ltFile`. If none is specified, then the name of the application binary is used, with the extension replaced by `.log`. The file is then located in the `/tmp` directory on unix-like systems, or in the application directory for Dos/Windows like systems.

**See also:** `LogType` (??)

### 13.5.20 TEventLog.TimeStampFormat

**Synopsis:** Format for the timestamp string

**Declaration:** `Property TimeStampFormat : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `TimeStampFormat` is the formatting string used to create a timestamp string when writing log messages to file. It should have a format suitable for the `FormatDateTime` (??) call. If it is left empty, then `yyyy-mm-dd hh:nn:ss.zzz` is used.

**See also:** `TEventLog.Identification` (??)

### 13.5.21 TEventLog.CustomLogType

Synopsis: Custom log type ID

Declaration: `Property CustomLogType : Word`

Visibility: published

Access: Read,Write

Description: `CustomLogType` is used in the `EventTypeToString (??)` to format the custom log event type string.

See also: `EventTypeToString (??)`

### 13.5.22 TEventLog.EventIDOffset

Synopsis: Offset for event ID messages identifiers

Declaration: `Property EventIDOffset : DWord`

Visibility: published

Access: Read,Write

Description: `EventIDOffset` is the offset for the message formatting strings in the windows resource file. This property is ignored on other platforms.

The message strings in the file registered with the `RegisterMessageFile (??)` call are windows resource strings. They each have a unique ID, which must be communicated to windows. In the resource file distributed by Free Pascal, the resource strings are numbered from 1000 to 1004. The actual number communicated to windows is formed by adding the ordinal value of the message's eventtype to `EventIDOffset` (which is by default 1000), which means that by default, the string numbers are:

**1000**Custom event types

**1001**Information event type

**1002**Warning event type

**1003**Error event type

**1004**Debug event type

See also: `RegisterMessageFile (??)`

### 13.5.23 TEventLog.OnGetCustomCategory

Synopsis: Event to retrieve custom message category

Declaration: `Property OnGetCustomCategory : TLogCategoryEvent`

Visibility: published

Access: Read,Write

Description: `OnGetCustomCategory` is called on the windows platform to determine the category of a custom event type. It should return an ID which will be used by windows to look up the string which describes the message category in the file containing the resource strings.

See also: `OnGetCustomEventID (??)`, `OnGetCustomEvent (??)`

### 13.5.24 TEventLog.OnGetCustomEventID

Synopsis: Event to retrieve custom event ID

Declaration: Property OnGetCustomEventID : TLogCodeEvent

Visibility: published

Access: Read,Write

Description: OnGetCustomEventID is called on the windows platform to determine the category of a custom event type. It should return an ID which will be used by windows to look up the string which formats the message, in the file containing the resource strings.

See also: OnGetCustomCategory (??), OnGetCustomEvent (??)

### 13.5.25 TEventLog.OnGetCustomEvent

Synopsis: Event to retrieve custom event Code

Declaration: Property OnGetCustomEvent : TLogCodeEvent

Visibility: published

Access: Read,Write

Description: OnGetCustomEvent is called on the windows platform to determine the event code of a custom event type. It should return an ID.

See also: OnGetCustomCategory (??), OnGetCustomEventID (??)

## Chapter 14

# Reference for unit 'ezcgi'

### 14.1 Used units

Table 14.1: Used units by unit 'ezcgi'

Name	Page
Classes	??
System	??
sysutils	??

### 14.2 Overview

`ezcgi`, written by Michael Hess, provides a single class which offers simple access to the CGI environment which a CGI program operates under. It supports both GET and POST methods. It's intended for simple CGI programs which do not need full-blown CGI support. File uploads are not supported by this component.

To use the unit, a descendent of the `TEZCGI` class should be created and the `DoPost` (??) or `DoGet` (??) methods should be overridden.

### 14.3 Constants, types and variables

#### 14.3.1 Constants

```
hexTable = '0123456789ABCDEF'
```

String constant used to convert a number to a hexadecimal code or back.

### 14.4 ECGIException

#### 14.4.1 Description

Exception raised by `TEZcgi` ([423](#))

See also: `TEZcgi` ([423](#))

## 14.5 TEZcgi

### 14.5.1 Description

`TEZcgi` implements all functionality to analyze the CGI environment and query the variables present in it. It's main use is the exposed variables.

Programs wishing to use this class should make a descendent class of this class and override the `DoPost` (??) or `DoGet` (??) methods. To run the program, an instance of this class must be created, and it's `Run` (??) method should be invoked. This will analyze the environment and call the `DoPost` or `DoGet` method, depending on what HTTP method was used to invoke the program.

### 14.5.2 Method overview

Page	Property	Description
<a href="#">423</a>	Create	Creates a new instance of the <code>TEZCGI</code> component
<a href="#">423</a>	Destroy	Removes the <code>TEZCGI</code> component from memory
<a href="#">425</a>	DoGet	Method to handle <code>GET</code> requests
<a href="#">425</a>	DoPost	Method to handle <code>POST</code> requests
<a href="#">425</a>	GetValue	Return the value of a request variable.
<a href="#">424</a>	PutLine	Send a line of output to the web-client
<a href="#">424</a>	Run	Run the CGI application.
<a href="#">424</a>	WriteContent	Writes the content type to standard output

### 14.5.3 Property overview

Page	Property	Access	Description
<a href="#">427</a>	Email	rw	Email of the server administrator
<a href="#">427</a>	Name	rw	Name of the server administrator
<a href="#">426</a>	Names	r	Indexed array with available variable names.
<a href="#">425</a>	Values	r	Variables passed to the CGI script
<a href="#">427</a>	VariableCount	r	Number of available variables.
<a href="#">426</a>	Variables	r	Indexed array with variables as name=value pairs.

### 14.5.4 TEZcgi.Create

Synopsis: Creates a new instance of the `TEZCGI` component

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes the CGI program's environment: it reads the environment variables passed to the CGI program and stores them in the `Variable` (??) property.

See also: `Variables` (??), `Names` (??), `Values` (??)

### 14.5.5 TEZcgi.Destroy

Synopsis: Removes the `TEZCGI` component from memory



**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` removes all variables from memory and then calls the inherited `destroy`, removing the `TEZCGI` instance from memory.

`Destroy` should never be called directly. Instead `Free` should be used, or `FreeAndNil`

**See also:** `Create (??)`

### 14.5.6 TEZcgi.Run

**Synopsis:** Run the CGI application.

**Declaration:** `procedure Run`

**Visibility:** `public`

**Description:** `Run` analyses the variables passed to the application, processes the request variables (it stores them in the `Variables (??)` property) and calls the `DoPost (??)` or `DoGet (??)` methods, depending on the method passed to the web server.

After creating the instance of `TEZCGI`, the `Run` method is the only method that should be called when using this component.

**See also:** `Variables (??)`, `DoPost (??)`, `DoGet (??)`

### 14.5.7 TEZcgi.WriteContent

**Synopsis:** Writes the content type to standard output

**Declaration:** `procedure WriteContent(cType: String)`

**Visibility:** `public`

**Description:** `WriteContent` writes the content type `cType` to standard output, followed by an empty line. After this method was called, no more HTTP headers may be written to standard output. Any HTTP headers should be written before `WriteContent` is called. It should be called from the `DoPost (??)` or `DoGet (??)` methods.

**See also:** `DoPost (??)`, `DoGet (??)`, `PutLine (??)`

### 14.5.8 TEZcgi.PutLine

**Synopsis:** Send a line of output to the web-client

**Declaration:** `procedure PutLine(sOut: String)`

**Visibility:** `public`

**Description:** `PutLine` writes a line of text (`sOut`) to the web client (currently, to standard output). It should be called only after `WriteContent (??)` was called with a content type of `text`. The sent text is not processed in any way, i.e. no HTML entities or so are inserted instead of special HTML characters. This should be done by the user.

**Errors:** No check is performed whether the content type is right.

**See also:** `WriteContent (??)`

### 14.5.9 TEZcgi.GetValue

Synopsis: Return the value of a request variable.

Declaration: `function GetValue(Index: String; defaultValue: String) : String`

Visibility: public

Description: `GetValue` returns the value of the variable named `Index`, and returns `DefaultValue` if it is empty or does not exist.

See also: `Values (??)`

### 14.5.10 TEZcgi.DoPost

Synopsis: Method to handle POST requests

Declaration: `procedure DoPost; Virtual`

Visibility: public

Description: `DoPost` is called by the `Run (??)` method the POST method was used to invoke the CGI application. It should be overridden in descendents of `TEZcgi` to actually handle the request.

See also: `Run (??)`, `DoGet (??)`

### 14.5.11 TEZcgi.DoGet

Synopsis: Method to handle GET requests

Declaration: `procedure DoGet; Virtual`

Visibility: public

Description: `DoGet` is called by the `Run (??)` method the GET method was used to invoke the CGI application. It should be overridden in descendents of `TEZcgi` to actually handle the request.

See also: `Run (??)`, `DoPost (??)`

### 14.5.12 TEZcgi.Values

Synopsis: Variables passed to the CGI script

Declaration: `Property Values[Index: String]: String`

Visibility: public

Access: Read

Description: `Values` is a name-based array of variables that were passed to the script by the web server or the HTTP request. The `Index` variable is the name of the variable whose value should be retrieved. The following standard values are available:

**AUTH\_TYPE**Authorization type

**CONTENT\_LENGTH**Content length

**CONTENT\_TYPE**Content type

**GATEWAY\_INTERFACE**Used gateway interface  
**PATH\_INFO**Requested URL  
**PATH\_TRANSLATED**Transformed URL  
**QUERY\_STRING**Client query string  
**REMOTE\_ADDR**Address of remote client  
**REMOTE\_HOST**DNS name of remote client  
**REMOTE\_IDENT**Remote identity.  
**REMOTE\_USER**Remote user  
**REQUEST\_METHOD**Request methods (POST or GET)  
**SCRIPT\_NAME**Script name  
**SERVER\_NAME**Server host name  
**SERVER\_PORT**Server port  
**SERVER\_PROTOCOL**Server protocol  
**SERVER\_SOFTWARE**Web server software  
**HTTP\_ACCEPT**Accepted responses  
**HTTP\_ACCEPT\_CHARSET**Accepted character sets  
**HTTP\_ACCEPT\_ENCODING**Accepted encodings  
**HTTP\_IF\_MODIFIED\_SINCE**Proxy information  
**HTTP\_REFERER**Referring page  
**HTTP\_USER\_AGENT**Client software name

Other than the standard list, any variables that were passed by the web-client request, are also available. Note that the variables are case insensitive.

See also: `TEZCGI.Variables` (??), `TEZCGI.Names` (??), `TEZCGI.GetValue` (??), `TEZcgi.VariableCount` (??)

### 14.5.13 TEZcgi.Names

Synopsis: Indexed array with available variable names.

Declaration: `Property Names[Index: Integer]: String`

Visibility: public

Access: Read

Description: `Names` provides indexed access to the available variable names. The `Index` may run from 0 to `VariableCount` (??). Any other value will result in an exception being raised.

See also: `TEZcgi.Variables` (??), `TEZcgi.Values` (??), `TEZcgi.GetValue` (??), `TEZcgi.VariableCount` (??)

### 14.5.14 TEZcgi.Variables

Synopsis: Indexed array with variables as name=value pairs.

Declaration: `Property Variables[Index: Integer]: String`

Visibility: public

Access: Read

**Description:** `Variables` provides indexed access to the available variable names and values. The variables are returned as `Name=Value` pairs. The `Index` may run from 0 to `VariableCount (??)`. Any other value will result in an exception being raised.

See also: `TEZcgi.Names (??)`, `TEZcgi.Values (??)`, `TEZcgi.GetValue (??)`, `TEZcgi.VariableCount (??)`

### 14.5.15 TEZcgi.VariableCount

**Synopsis:** Number of available variables.

**Declaration:** `Property VariableCount : Integer`

**Visibility:** `public`

**Access:** `Read`

**Description:** `TEZcgi.VariableCount` returns the number of available CGI variables. This includes both the standard CGI environment variables and the request variables. The actual names and values can be retrieved with the `Names (??)` and `Variables (??)` properties.

See also: `Names (??)`, `Variables (??)`, `TEZcgi.Values (??)`, `TEZcgi.GetValue (??)`

### 14.5.16 TEZcgi.Name

**Synopsis:** Name of the server administrator

**Declaration:** `Property Name : String`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Name` is used when displaying an error message to the user. This should set prior to calling the `TEZcgi.Run (??)` method.

See also: `TEZcgi.Run (??)`, `TEZcgi.Email (??)`

### 14.5.17 TEZcgi.Email

**Synopsis:** Email of the server administrator

**Declaration:** `Property Email : String`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Email` is used when displaying an error message to the user. This should set prior to calling the `TEZcgi.Run (??)` method.

See also: `TEZcgi.Run (??)`, `TEZcgi.Name (??)`

## Chapter 15

# Reference for unit 'fpTimer'

### 15.1 Used units

Table 15.1: Used units by unit 'fpTimer'

Name	Page
Classes	??
System	??

### 15.2 Overview

The `fpTimer` unit implements a timer class `TFPTimer` (430) which can be used on all supported platforms. The timer class uses a driver class `TFPTimerDriver` (431) which does the actual work.

A default timer driver class is implemented on all platforms. It will work in GUI and non-gui applications, but only in the application's main thread.

An alternative driver class can be used by setting the `DefaultTimerDriverClass` (428) variable to the class pointer of the driver class. The driver class should descend from `TFPTimerDriver` (431).

### 15.3 Constants, types and variables

#### 15.3.1 Types

```
TFPTimerDriverClass = Class of TFPTimerDriver
```

`TFPTimerDriverClass` is the class pointer of `TFPTimerDriver` (431) it exists mainly for the purpose of being able to set `DefaultTimerDriverClass` (428), so a custom timer driver can be used for the timer instances.

#### 15.3.2 Variables

```
DefaultTimerDriverClass : TFPTimerDriverClass = nil
```

`DefaultTimerDriverClass` contains the `TFPTimerDriver` (431) class pointer that should be used when a new instance of `TFPCustomTimer` (429) is created. It is by default set to the system timer class.

Setting this class pointer to another descendent of `TFPTimerDriver` allows to customize the default timer implementation used in the entire application.

## 15.4 TFPCustomTimer

### 15.4.1 Description

`TFPCustomTimer` is the timer class containing the timer's implementation. It relies on an extra driver instance (of type `TFPTimerDriver` (431)) to do the actual work.

`TFPCustomTimer` publishes no events or properties, so it is unsuitable for handling in an IDE. The `TFPTimer` (430) descendent class publishes all needed events of `TFPCustomTimer`.

See also: `TFPTimerDriver` (431), `TFPTimer` (430)

### 15.4.2 Method overview

Page	Property	Description
429	Create	Create a new timer
429	Destroy	Release a timer instance from memory
430	StartTimer	Start the timer
430	StopTimer	Stop the timer

### 15.4.3 TFPCustomTimer.Create

Synopsis: Create a new timer

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` instantiates a new `TFPCustomTimer` instance. It creates the timer driver instance from the `DefaultTimerDriverClass` class pointer.

See also: `TFPCustomTimer.Destroy` (??)

### 15.4.4 TFPCustomTimer.Destroy

Synopsis: Release a timer instance from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` releases the timer driver component from memory, and then calls `Inherited` to clean the `TFPCustomTimer` instance from memory.

See also: `TFPCustomTimer.Create` (??)

### 15.4.5 TFPCustomTimer.StartTimer

Synopsis: Start the timer

Declaration: `procedure StartTimer; Virtual`

Visibility: `public`

Description: `StartTimer` starts the timer. After a call to `StartTimer`, the timer will start producing timer ticks.

The timer stops producing ticks only when the `StopTimer (??)` event is called.

See also: `StopTimer (??)`, `Enabled (??)`, `OnTimer (??)`

### 15.4.6 TFPCustomTimer.StopTimer

Synopsis: Stop the timer

Declaration: `procedure StopTimer; Virtual`

Visibility: `public`

Description: `StopTimer` stops a started timer. After a call to `StopTimer`, the timer no longer produces timer ticks.

See also: `StartTimer (??)`, `Enabled (??)`, `OnTimer (??)`

## 15.5 TFPTimer

### 15.5.1 Description

`TFPTimer` implements no new events or properties, but merely publishes events and properties already implemented in `TFPCustomTimer` (429): `Enabled (??)`, `OnTimer (??)` and `Interval (??)`.

The `TFPTimer` class is suitable for use in an IDE.

See also: `TFPCustomTimer` (429), `Enabled (??)`, `OnTimer (??)`, `Interval (??)`

### 15.5.2 Property overview

Page	Property	Access	Description
<a href="#">430</a>	<code>Enabled</code>		Start or stop the timer
<a href="#">431</a>	<code>Interval</code>		Timer tick interval in milliseconds.
<a href="#">431</a>	<code>OnTimer</code>		Event called on each timer tick.

### 15.5.3 TFPTimer.Enabled

Synopsis: Start or stop the timer

Declaration: `Property Enabled :`

Visibility: `published`

Access:

Description: `Enabled` controls whether the timer is active. Setting `Enabled` to `True` will start the timer (calling `StartTimer (??)`), setting it to `False` will stop the timer (calling `StopTimer (??)`).

See also: `StartTimer (??)`, `StopTimer (??)`, `OnTimer (??)`, `Interval (??)`

### 15.5.4 TFPTimer.Interval

Synopsis: Timer tick interval in milliseconds.

Declaration: `Property Interval :`

Visibility: `published`

Access:

Description: `Interval` specifies the timer interval in milliseconds. Every `Interval` milliseconds, the `OnTimer (??)` event handler will be called.

Note that the milliseconds interval is a minimum interval. Under high system load, the timer tick may arrive later.

See also: `OnTimer (??)`, `Enabled (??)`

### 15.5.5 TFPTimer.OnTimer

Synopsis: Event called on each timer tick.

Declaration: `Property OnTimer :`

Visibility: `published`

Access:

Description: `OnTimer` is called on each timer tick. The event handler must be assigned to a method that will do the actual work that should occur when the timer fires.

See also: `Interval (??)`, `Enabled (??)`

## 15.6 TFPTimerDriver

### 15.6.1 Description

`TFPTimerDriver` is the abstract timer driver class: it simply provides an interface for the `TFP-CustomTimer (429)` class to use.

The `fpTimer` unit implements a descendent of this class which implements the default timer mechanism.

See also: `TFPCustomTimer (429)`, `DefaultTimerDriverClass (428)`

### 15.6.2 Method overview

Page	Property	Description
<a href="#">432</a>	<code>Create</code>	Create new driver instance
<a href="#">432</a>	<code>StartTimer</code>	Start the timer
<a href="#">432</a>	<code>StopTimer</code>	Stop the timer

### 15.6.3 Property overview

Page	Property	Access	Description
<a href="#">432</a>	<code>Timer</code>	<code>r</code>	Timer tick



#### 15.6.4 TFPTimerDriver.Create

Synopsis: Create new driver instance

Declaration: `constructor Create(ATimer: TFPCustomTimer); Virtual`

Visibility: public

Description: `Create` should be overridden by descendents of `TFPTimerDriver` to do additional initialization of the timer driver. `Create` just stores (in `Timer` (??)) a reference to the `ATimer` instance which created the driver instance.

See also: `Timer` (??), `TFPTimer` (430)

#### 15.6.5 TFPTimerDriver.StartTimer

Synopsis: Start the timer

Declaration: `procedure StartTimer; Virtual; Abstract`

Visibility: public

Description: `StartTimer` is called by `TFPCustomTimer.StartTimer` (??). It should be overridden by descendents of `TFPTimerDriver` to actually start the timer.

See also: `TFPCustomTimer.StartTimer` (??), `TFPTimerDriver.StopTimer` (??)

#### 15.6.6 TFPTimerDriver.StopTimer

Synopsis: Stop the timer

Declaration: `procedure StopTimer; Virtual; Abstract`

Visibility: public

Description: `StopTimer` is called by `TFPCustomTimer.StopTimer` (??). It should be overridden by descendents of `TFPTimerDriver` to actually stop the timer.

See also: `TFPCustomTimer.StopTimer` (??), `TFPTimerDriver.StartTimer` (??)

#### 15.6.7 TFPTimerDriver.Timer

Synopsis: Timer tick

Declaration: `Property Timer : TFPCustomTimer`

Visibility: public

Access: Read

Description: `Timer` calls the `TFPCustomTimer` (429) timer event. Descendents of `TFPTimerDriver` should call `Timer` whenever a timer tick occurs.

See also: `TFPTimer.OnTimer` (??), `TFPTimerDriver.StartTimer` (??), `TFPTimerDriver.StopTimer` (??)

# Chapter 16

## Reference for unit 'gettext'

### 16.1 Used units

Table 16.1: Used units by unit 'gettext'

Name	Page
Classes	??
System	??
sysutils	??

### 16.2 Overview

The `gettext` unit can be used to hook into the resource string mechanism of Free Pascal to provide translations of the resource strings, based on the GNU `gettext` mechanism. The unit provides a class (`TMOFile` ([435](#))) to read the `.mo` files with localizations for various languages. It also provides a couple of calls to translate all resource strings in an application based on the translations in a `.mo` file.

### 16.3 Constants, types and variables

#### 16.3.1 Constants

```
MOFileHeaderMagic = $950412de
```

This constant is found as the first integer in a `.mo`

#### 16.3.2 Types

```
PLongWordArray = ^TLongWordArray
```

Pointer to a `TLongWordArray` ([434](#)) array.

```
PMOStringTable = ^TMOStringTable
```

Pointer to a TMOStringTable (434) array.

```
PPCharArray = ^TPCharArray
```

Pointer to a TPCharArray (434) array.

```
TLongWordArray = Array[0..(1 shl 30) div SizeOf(LongWord)] of LongWord
```

TLongWordArray is an array used to define the PLongWordArray (433) pointer. A variable of type TLongWordArray should never be directly declared, as it would occupy too much memory. The PLongWordArray type can be used to allocate a dynamic number of elements.

```
TMOFileHeader = packed record
  magic : LongWord;
  revision : LongWord;
  nstrings : LongWord;
  OrigTabOffset : LongWord;
  TransTabOffset : LongWord;
  HashTabSize : LongWord;
  HashTabOffset : LongWord;
end
```

This structure describes the structure of a .mo file with string localizations.

```
TMOStringInfo = packed record
  length : LongWord;
  offset : LongWord;
end
```

This record is one element in the string tables describing the original and translated strings. It describes the position and length of the string. The location of these tables is stored in the TMOFileHeader (434) record at the start of the file.

```
TMOStringTable = Array[0..(1 shl 30) div SizeOf(TMOStringInfo)] of TMOStringInfo
```

TMOStringTable is an array type containing TMOStringInfo (434) records. It should never be used directly, as it would occupy too much memory.

```
TPCharArray = Array[0..(1 shl 30) div SizeOf(PChar)] of PChar
```

TLongWordArray is an array used to define the PPCharArray (434) pointer. A variable of type TPCharArray should never be directly declared, as it would occupy too much memory. The PPCharArray type can be used to allocate a dynamic number of elements.

## 16.4 Procedures and functions

### 16.4.1 GetLanguageIDs

Synopsis: Return the current language IDs

**Declaration:** `procedure GetLanguageIDs (var Lang: String; var FallbackLang: String)`

**Visibility:** default

**Description:** `GetLanguageIDs` returns the current language IDs (an ISO string) as returned by the operating system. On windows, the `GetUserDefaultLCID` and `GetLocaleInfo` calls are used. On other operating systems, the `LC_ALL`, `LC_MESSAGES` or `LANG` environment variables are examined.

### 16.4.2 TranslateResourceStrings

**Synopsis:** Translate the resource strings of the application.

**Declaration:** `procedure TranslateResourceStrings (AFile: TMOFile)`  
`procedure TranslateResourceStrings (const AFilename: String)`

**Visibility:** default

**Description:** `TranslateResourceStrings` translates all the resource strings in the application based on the values in the `.mo` file `AFilename` or `AFile`. The procedure creates an `TMOFile` (435) instance to read the `.mo` file if a filename is given.

**Errors:** If the file does not exist or is an invalid `.mo` file.

**See also:** `TranslateUnitResourceStrings` (435), `TMOFile` (435)

### 16.4.3 TranslateUnitResourceStrings

**Synopsis:** Translate the resource strings of a unit.

**Declaration:** `procedure TranslateUnitResourceStrings (const AUnitName: String;`  
`AFile: TMOFile)`  
`procedure TranslateUnitResourceStrings (const AUnitName: String;`  
`const AFilename: String)`

**Visibility:** default

**Description:** `TranslateUnitResourceStrings` is identical in function to `TranslateResourceStrings` (435), but translates the strings of a single unit (`AUnitName`) which was used to compile the application. This can be more convenient, since the resource string files are created on a unit basis.

**See also:** `TranslateResourceStrings` (435), `TMOFile` (435)

## 16.5 EMOFileError

### 16.5.1 Description

`EMOFileError` is raised in case an `TMOFile` (435) instance is created with an invalid `.mo`.

**See also:** `TMOFile` (435)

## 16.6 TMOFile

### 16.6.1 Description

`TMOFile` is a class providing easy access to a `.mo` file. It can be used to translate any of the strings that reside in the `.mo` file. The internal structure of the `.mo` is completely hidden.

### 16.6.2 Method overview

Page	Property	Description
<a href="#">436</a>	Create	Create a new instance of the <code>TMOFile</code> class.
<a href="#">436</a>	Destroy	Removes the <code>TMOFile</code> instance from memory
<a href="#">436</a>	Translate	Translate a string

### 16.6.3 TMOFile.Create

**Synopsis:** Create a new instance of the `TMOFile` class.

**Declaration:** `constructor Create(const AFilename: String)`  
`constructor Create(AStream: TStream)`

**Visibility:** `public`

**Description:** `Create` creates a new instance of the `MOFile` class. It opens the file `AFilename` or the stream `AStream`. If a stream is provided, it should be seekable.

The whole contents of the file is read into memory during the `Create` call. This means that the stream is no longer needed after the `Create` call.

**Errors:** If the named file does not exist, then an exception may be raised. If the file does not contain a valid `TMOFileHeader` ([434](#)) structure, then an `EMOFileError` ([435](#)) exception is raised.

See also: `TMOFile.Destroy` (??)

### 16.6.4 TMOFile.Destroy

**Synopsis:** Removes the `TMOFile` instance from memory

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` cleans the internal structures with the contents of the `.mo`. After this the `TMOFile` instance is removed from memory.

See also: `TMOFile.Create` (??)

### 16.6.5 TMOFile.Translate

**Synopsis:** Translate a string

**Declaration:** `function Translate(AOrig: PChar; ALen: Integer; AHash: LongWord) : String`  
`function Translate(AOrig: String; AHash: LongWord) : String`  
`function Translate(AOrig: String) : String`

**Visibility:** `public`

**Description:** `Translate` translates the string `AOrig`. The string should be in the `.mo` file as-is. The string can be given as a plain string, as a `PChar` (with length `ALen`). If the hash value (`AHash`) of the string is not given, it is calculated.

If the string is in the `.mo` file, the translated string is returned. If the string is not in the file, an empty string is returned.

**Errors:** None.

## Chapter 17

# Reference for unit 'idea'

### 17.1 Used units

Table 17.1: Used units by unit 'idea'

Name	Page
Classes	??
System	??
sysutils	??

### 17.2 Overview

Besides some low level IDEA encryption routines, the IDEA unit also offers 2 streams which offer on-the-fly encryption or decryption: there are 2 stream objects: A write-only encryption stream which encrypts anything that is written to it, and a decryption stream which decrypts anything that is read from it.

### 17.3 Constants, types and variables

#### 17.3.1 Constants

`IDEABLOCKSIZE = 8`

IDEA block size

`IDEAKEYSIZE = 16`

IDEA Key size constant.

`KEYLEN = 6 * ROUNDS + 4`

Key length

`ROUNDS = 8`

Number of rounds to encrypt

### 17.3.2 Types

`IdeaCryptData = TideaCryptData`

Provided for backward functionality.

`IdeaCryptKey = TideaCryptKey`

Provided for backward functionality.

`IDEAkey = TIDEAKey`

Provided for backward functionality.

`TideaCryptData = Array[0..3] of Word`

`TideaCryptData` is an internal type, defined to hold data for encryption/decryption.

`TideaCryptKey = Array[0..7] of Word`

The actual encryption or decryption key for IDEA is 64-bit long. This type is used to hold such a key. It can be generated with the `EnKeyIDEA` (439) or `DeKeyIDEA` (438) algorithms depending on whether an encryption or decryption key is needed.

`TIDEAKey = Array[0..keylen-1] of Word`

The IDEA key should be filled by the user with some random data (say, a passphrase). This key is used to generate the actual encryption/decryption keys.

## 17.4 Procedures and functions

### 17.4.1 CipherIdea

**Synopsis:** Encrypt or decrypt a buffer.

**Declaration:** `procedure CipherIdea(Input: TideaCryptData; var outdata: TideaCryptData;  
z: TIDEAKey)`

**Visibility:** default

**Description:** `CipherIdea` encrypts or decrypts a buffer with data (`Input`) using key `z`. The resulting encrypted or decrypted data is returned in `Output`.

**Errors:** None.

**See also:** `EnKeyIdea` (439), `DeKeyIdea` (438), `TIDEAEncryptStream` (441), `TIDEADecryptStream` (439)

### 17.4.2 DeKeyIdea

**Synopsis:** Create a decryption key from an encryption key.

**Declaration:** `procedure DeKeyIdea(z: TIDEAKey; var dk: TIDEAKey)`

**Visibility:** default

**Description:** `DeKeyIdea` creates a decryption key based on the encryption key `z`. The decryption key is returned in `dk`. Note that only a decryption key generated from the encryption key that was used to encrypt the data can be used to decrypt the data.

Errors: None.

See also: `EnKeyIdea` (439), `CipherIdea` (438)

### 17.4.3 EnKeyIdea

**Synopsis:** Create an IDEA encryption key from a user key.

**Declaration:** `procedure EnKeyIdea (UserKey: TIDEACryptKey; var z: TIDEAKey)`

Visibility: default

**Description:** `EnKeyIdea` creates an IDEA encryption key from user-supplied data in `UserKey`. The Encryption key is stored in `z`.

Errors: None.

See also: `DeKeyIdea` (438), `CipherIdea` (438)

## 17.5 EIDEAError

### 17.5.1 Description

`EIDEAError` is used to signal errors in the IDEA encryption decryption streams.

## 17.6 TIDEADeCryptStream

### 17.6.1 Description

`TIDEADeCryptStream` is a stream which decrypts anything that is read from it using the IDEA mechanism. It reads the encrypted data from a source stream and decrypts it using the `CipherIDEA` (438) algorithm. It is a read-only stream: it is not possible to write data to this stream.

When creating a `TIDEADeCryptStream` instance, an IDEA decryption key should be passed to the constructor, as well as the stream from which encrypted data should be read written.

The encrypted data can be created with a `TIDEAEncryptStream` (441) encryption stream.

See also: `TIDEAEncryptStream` (441), `TIDEAStream.Create` (??), `CipherIDEA` (438)

### 17.6.2 Method overview

Page	Property	Description
440	Create	Constructor to create a new <code>TIDEADeCryptStream</code> instance
440	Read	Reads data from the stream, decrypting it as needed
440	Seek	Set position on the stream



### 17.6.3 TIDEADeCryptStream.Create

Synopsis: Constructor to create a new `TIDEADeCryptStream` instance

Declaration: `constructor Create(const AKey: String; Dest: TStream); Overload`

Visibility: public

Description: `Create` creates a new `TIDEADeCryptStream` instance using the the string `AKey` to compute the encryption key (438), which is then passed on to the inherited constructor `TIDEAStream.Create` (??). It is an easy-access function which introduces no new functionality.

The string is truncated at the maximum length of the `TIdeaCryptKey` (438) structure, so it makes no sense to provide a string with length longer than this structure.

See also: `TIdeaCryptKey` (438), `TIDEAStream.Create` (??), `TIDEAEncryptStream.Create` (??)

### 17.6.4 TIDEADeCryptStream.Read

Synopsis: Reads data from the stream, decrypting it as needed

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Read` attempts to read `Count` bytes from the stream, placing them in `Buffer` the bytes are read from the source stream and decrypted as they are read. (bytes are read from the source stream in blocks of 8 bytes. The function returns the number of bytes actually read.

Errors: If an error occurs when reading data from the source stream, an exception may be raised.

See also: `Write` (??), `Seek` (??), `TIDEAEncryptStream` (441)

### 17.6.5 TIDEADeCryptStream.Seek

Synopsis: Set position on the stream

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: public

Description: `Seek` will only work on a forward seek. It emulates a forward seek by reading and discarding bytes from the input stream. The `TIDEADeCryptStream` stream tries to provide seek capabilities for the following limited number of cases:

**Origin=soFromBeginning** If `Offset` is larger than the current position, then the remaining bytes are skipped by reading them from the stream and discarding them.

**Origin=soFromCurrent** If `Offset` is zero, the current position is returned. If it is positive, then `Offset` bytes are skipped by reading them from the stream and discarding them.

Errors: An `EIDEAError` (439) exception is raised if the stream does not allow the requested seek operation.

See also: `Read` (??)

## 17.7 TIDEAEncryptStream

### 17.7.1 Description

`TIDEAEncryptStream` is a stream which encrypts anything that is written to it using the IDEA mechanism, and then writes the encrypted data to the destination stream using the `CipherIDEA` (438) algorithm. It is a write-only stream: it is not possible to read data from this stream.

When creating a `TIDEAEncryptStream` instance, an IDEA encryption key should be passed to the constructor, as well as the stream to which encrypted data should be written.

The resulting encrypted data can be read again with a `TIDEADecryptStream` (439) decryption stream.

See also: `TIDEADecryptStream` (439), `TIDEAStream.Create` (??), `CipherIDEA` (438)

### 17.7.2 Method overview

Page	Property	Description
<a href="#">441</a>	Create	Constructor to create a new <code>TIDEAEncryptStream</code> instance
<a href="#">441</a>	Destroy	Flush data buffers and free the stream instance.
<a href="#">442</a>	Flush	Write remaining bytes from the stream
<a href="#">442</a>	Seek	Set stream position
<a href="#">442</a>	Write	Write bytes to the stream to be encrypted

### 17.7.3 TIDEAEncryptStream.Create

Synopsis: Constructor to create a new `TIDEAEncryptStream` instance

Declaration: `constructor Create(const AKey: String; Dest: TStream);` Overload

Visibility: public

Description: `Create` creates a new `TIDEAEncryptStream` instance using the the string `AKey` to compute the encryption key (438), which is then passed on to the inherited constructor `TIDEAStream.Create` (??). It is an easy-access function which introduces no new functionality.

The string is truncated at the maximum length of the `TIdeaCryptKey` (438) structure, so it makes no sense to provide a string with length longer than this structure.

See also: `TIdeaCryptKey` (438), `TIDEAStream.Create` (??), `TIDEADeCryptStream.Create` (??)

### 17.7.4 TIDEAEncryptStream.Destroy

Synopsis: Flush data buffers and free the stream instance.

Declaration: `destructor Destroy;` Override

Visibility: public

Description: `Destroy` flushes any data still remaining in the internal encryption buffer, and then calls the inherited `Destroy`

By default, the destination stream is not freed when the encryption stream is freed.

Errors: None.

See also: `TIDEAStream.Create` (??)

### 17.7.5 TIDEAEncryptStream.Write

Synopsis: Write bytes to the stream to be encrypted

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` writes `Count` bytes from `Buffer` to the stream, encrypting the bytes as they are written (encryption in blocks of 8 bytes).

Errors: If an error occurs writing to the destination stream, an error may occur.

See also: `Read` (??)

### 17.7.6 TIDEAEncryptStream.Seek

Synopsis: Set stream position

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` return the current position if called with 0 and `soFromCurrent` as arguments. With all other values, it will always raise an exception, since it is impossible to set the position on an encryption stream.

Errors: An `EIDEAError` (439) will be raised unless called with 0 and `soFromCurrent` as arguments.

See also: `Write` (??), `EIDEAError` (439)

### 17.7.7 TIDEAEncryptStream.Flush

Synopsis: Write remaining bytes from the stream

Declaration: `procedure Flush`

Visibility: public

Description: `Flush` writes the current encryption buffer to the stream. Encryption always happens in blocks of 8 bytes, so if the buffer is not completely filled at the end of the writing operations, it must be flushed. It should never be called directly, unless at the end of all writing operations. It is called automatically when the stream is destroyed.

Errors: None.

See also: `Write` (??)

## 17.8 TIDEAStream

### 17.8.1 Description

Do not create instances of `TIDEAStream` directly. It implements no useful functionality: it serves as a common ancestor of the `TIDEAEncryptStream` (441) and `TIDEADeCryptStream` (439), and simply provides some fields that these descendent classes use when encrypting/decrypting. One of these classes should be created, depending on whether one wishes to encrypt or to decrypt.

See also: `TIDEAEncryptStream` (441), `TIDEADeCryptStream` (439)

### 17.8.2 Method overview

Page	Property	Description
<a href="#">443</a>	Create	Creates a new instance of the <code>TIDEAStream</code> class

### 17.8.3 Property overview

Page	Property	Access	Description
<a href="#">443</a>	Key	r	Key used when encrypting/decrypting

### 17.8.4 TIDEAStream.Create

Synopsis: Creates a new instance of the `TIDEAStream` class

Declaration: constructor `Create(AKey: TIDEAKey; Dest: TStream);` Overload

Visibility: public

Description: `Create` stores the encryption/decryption key and then calls the inherited `Create` to store the `Dest` stream.

Errors: None.

See also: `TIDEAEncryptStream` ([441](#)), `TIDEADeCryptStream` ([439](#))

### 17.8.5 TIDEAStream.Key

Synopsis: Key used when encrypting/decrypting

Declaration: Property `Key : TIDEAKey`

Visibility: public

Access: Read

Description: `Key` is the key as it was passed to the constructor of the stream. It cannot be changed while data is read or written. It is the key as it is used when encrypting/decrypting.

See also: `CipherIdea` ([438](#))

## Chapter 18

# Reference for unit 'inicol'

### 18.1 Used units

Table 18.1: Used units by unit 'inicol'

Name	Page
Classes	??
Inifiles	<a href="#">454</a>
System	??
sysutils	??

### 18.2 Overview

`inicol` contains an implementation of `TCollection` and `TCollectionItem` descendents which cooperate to read and write the collection from and to a `.ini` file. It uses the `TCustomIniFile` ([454](#)) class for this.

### 18.3 Constants, types and variables

#### 18.3.1 Constants

```
KeyCount = 'Count'
```

`KeyCount` is used as a key name when reading or writing the number of items in the collection from the global section.

```
SGlobal = 'Global'
```

`SGlobal` is used as the default name of the global section when reading or writing the collection.

## 18.4 EIniCol

### 18.4.1 Description

EIniCol is used to report error conditions in the load and save methods of TIniCollection (445).

## 18.5 TIniCollection

### 18.5.1 Description

TIniCollection is a collection (??) descendent which has the capability to write itself to an .ini file. It introduces some load and save mechanisms, which can be used to write all items in the collection to disk. The items should be descendents of the type TIniCollectionItem (449).

All methods work using a TCustomIniFile class, making it possible to save to alternate file formats, or even databases.

An instance of TIniCollection should never be used directly. Instead, a descendent should be used, which sets the FPrefix and FSectionPrefix protected variables.

See also: TIniCollection.LoadFromFile (??), TIniCollection.LoadFromIni (??), TIniCollection.SaveToIni (??), TIniCollection.SaveToFile (??)

### 18.5.2 Method overview

Page	Property	Description
445	Load	Loads the collection from the default filename.
447	LoadFromFile	Load collection from file.
447	LoadFromIni	Load collection from a file in .ini file format.
446	Save	Save the collection to the default filename.
446	SaveToFile	Save collection to a file in .ini file format
446	SaveToIni	Save the collection to a TCustomIniFile descendent

### 18.5.3 Property overview

Page	Property	Access	Description
448	FileName	rw	Filename of the collection
448	GlobalSection	rw	Name of the global section
447	Prefix	r	Prefix used in global section
448	SectionPrefix	r	Prefix string for section names

### 18.5.4 TIniCollection.Load

Synopsis: Loads the collection from the default filename.

Declaration: procedure Load

Visibility: public

Description: Load loads the collection from the file as specified in the FileName (??) property. It calls the LoadFromFile (??) method to do this.

Errors: If the collection was not loaded or saved to file before this call, an EIniCol exception will be raised.

See also: `TIniCollection.LoadFromFile (??)`, `TIniCollection.LoadFromIni (??)`, `TIniCollection.Save (??)`, `FileName (??)`

### 18.5.5 TIniCollection.Save

Synopsis: Save the collection to the default filename.

Declaration: `procedure Save`

Visibility: `public`

Description: `Save` writes the collection to the file as specified in the `FileName (??)` property, using `GlobalSection (??)` as the section. It calls the `SaveToFile (??)` method to do this.

Errors: If the collection was not loaded or saved to file before this call, an `EIniCol` exception will be raised.

See also: `TIniCollection.SaveToFile (??)`, `TIniCollection.SaveToIni (??)`, `TIniCollection.Load (??)`, `FileName (??)`

### 18.5.6 TIniCollection.SaveToIni

Synopsis: Save the collection to a `TCustomIniFile` descendent

Declaration: `procedure SaveToIni (Ini: TCustomInifile; Section: String); Virtual`

Visibility: `public`

Description: `SaveToIni` does the actual writing. It writes the number of elements in the global section (as specified by the `Section` argument), as well as the section name for each item in the list. The item names are written using the `Prefix (??)` property for the key. After this it calls the `SaveToIni (??)` method of all `TIniCollectionItem` (449) instances.

This means that the global section of the .ini file will look something like this:

```
[globalsection]
Count=3
Prefix1=SectionPrefixFirstItemName
Prefix2=SectionPrefixSecondItemName
Prefix3=SectionPrefixThirdItemName
```

This construct allows to re-use an ini file for multiple collections.

After this method is called, the `GlobalSection (??)` property contains the value of `Section`, it will be used in the `Save (??)` method.

See also: `TIniCollectionItem.SaveToIni (??)`

### 18.5.7 TIniCollection.SaveToFile

Synopsis: Save collection to a file in .ini file format

Declaration: `procedure SaveToFile (AFileName: String; Section: String)`

Visibility: `public`

**Description:** `SaveToFile` will create a `TMemIniFile` instance with the `AFileName` argument as a filename. This instance is passed on to the `SaveToIni (??)` method, together with the `Section` argument, to do the actual saving.

**Errors:** An exception may be raised if the path in `AFileName` does not exist.

**See also:** `TIniCollection.SaveToIni (??)`, `TIniCollection.LoadFromFile (??)`

### 18.5.8 TIniCollection.LoadFromIni

**Synopsis:** Load collection from a file in .ini file format.

**Declaration:** `procedure LoadFromIni (Ini: TCustomInifile; Section: String); Virtual`

**Visibility:** `public`

**Description:** `LoadFromIni` will load the collection from the `Ini` instance. It first clears the collection, and reads the number of items from the global section with the name as passed through the `Section` argument. After this, an item is created and added to the collection, and its data is read by calling the `TIniCollectionItem.LoadFromIni (??)` method, passing the appropriate section name as found in the global section.

The description of the global section can be found in the `TIniCollection.SaveToIni (??)` method description.

**See also:** `TIniCollection.LoadFromFile (??)`, `TIniCollectionItem.LoadFromIni (??)`, `TIniCollection.SaveToIni (??)`

### 18.5.9 TIniCollection.LoadFromFile

**Synopsis:** Load collection from file.

**Declaration:** `procedure LoadFromFile (AFileName: String; Section: String)`

**Visibility:** `public`

**Description:** `LoadFromFile` creates a `TMemIniFile` instance using `AFileName` as the filename. It calls `LoadFromIni (??)` using this instance and `Section` as the parameters.

**See also:** `TIniCollection.LoadFromIni (??)`, `TIniCollection.Load (??)`, `TIniCollection.SaveToIni (??)`, `TIniCollection.SaveToFile (??)`

### 18.5.10 TIniCollection.Prefix

**Synopsis:** Prefix used in global section

**Declaration:** `Property Prefix : String`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Prefix` is used when writing the section names of the items in the collection to the global section, or when reading the names from the global section. If the prefix is set to `Item` then the global section might look something like this:



```

[MyCollection]
Count=2
Item1=FirstItem
Item2=SecondItem

```

A descendent of `TIniCollection` should set the value of this property, it cannot be empty.

See also: `TIniCollection.SectionPrefix` (??), `TIniCollection.GlobalSection` (??)

### 18.5.11 `TIniCollection.SectionPrefix`

Synopsis: Prefix string for section names

Declaration: `Property SectionPrefix : String`

Visibility: public

Access: Read

Description: `SectionPrefix` is a string that is prepended to the section name as returned by the `TIniCollectionItem.SectionName` (??) property to return the exact section name. It can be empty.

See also: `TIniCollection.Section` (??), `TIniCollection.GlobalSection` (??)

### 18.5.12 `TIniCollection.FileName`

Synopsis: Filename of the collection

Declaration: `Property FileName : String`

Visibility: public

Access: Read,Write

Description: `FileName` is the filename as used in the last `LoadFromFile` (??) or `SaveToFile` (??) operation. It is used in the `Load` (??) or `Save` (??) calls.

See also: `Save` (??), `LoadFromFile` (??), `SaveToFile` (??), `Load` (??)

### 18.5.13 `TIniCollection.GlobalSection`

Synopsis: Name of the global section

Declaration: `Property GlobalSection : String`

Visibility: public

Access: Read,Write

Description: `GlobalSection` contains the value of the `Section` argument in the `LoadFromIni` (??) or `SaveToIni` (??) calls. It's used in the `Load` (??) or `Save` (??) calls.

See also: `Save` (??), `LoadFromFile` (??), `SaveToFile` (??), `Load` (??)

## 18.6 TIniCollectionItem

### 18.6.1 Description

TIniCollectionItem is a #rtl.classes.tcollectionitem (??) descendent which has some extra methods for saving/loading the item to or from an .ini file.

To use this class, a descendent should be made, and the SaveToIni (??) and LoadFromIni (??) methods should be overridden. They should implement the actual loading and saving. The loading and saving is always initiated by the methods in TIniCollection (445), TIniCollection.LoadFromIni (??) and TIniCollection.SaveToIni (??) respectively.

See also: TIniCollection (445), TIniCollectionItem.SaveToIni (??), TIniCollectionItem.LoadFromIni (??), TIniCollection.LoadFromIni (??), TIniCollection.SaveToIni (??)

### 18.6.2 Method overview

Page	Property	Description
<a href="#">450</a>	LoadFromFile	Load item from a file
<a href="#">449</a>	LoadFromIni	Method called when the item must be loaded
<a href="#">450</a>	SaveToFile	Save item to a file
<a href="#">449</a>	SaveToIni	Method called when the item must be saved

### 18.6.3 Property overview

Page	Property	Access	Description
<a href="#">450</a>	SectionName	rw	Default section name

### 18.6.4 TIniCollectionItem.SaveToIni

Synopsis: Method called when the item must be saved

Declaration: `procedure SaveToIni (Ini: TCustomIniFile; Section: String); Virtual  
; Abstract`

Visibility: public

Description: SaveToIni is called by TIniCollection.SaveToIni (??) when it saves this item. Descendent classes should override this method to save the data they need to save. All write methods of the TCustomIniFile instance passed in Ini can be used, as long as the writing happens in the section passed in Section.

Errors: No checking is done to see whether the values are actually written to the correct section.

See also: TIniCollection.SaveToIni (??), LoadFromIni (??), SaveToFile (??), LoadFromFile (??)

### 18.6.5 TIniCollectionItem.LoadFromIni

Synopsis: Method called when the item must be loaded

Declaration: `procedure LoadFromIni (Ini: TCustomIniFile; Section: String); Virtual  
; Abstract`

Visibility: public

**Description:** `LoadFromIni` is called by `TIniCollection.LoadFromIni (??)` when it saves this item. Descendent classes should override this method to load the data they need to load. All read methods of the `TCustomIniFile` instance passed in `Ini` can be used, as long as the reading happens in the section passed in `Section`.

**Errors:** No checking is done to see whether the values are actually read from the correct section.

**See also:** `TIniCollection.LoadFromIni (??)`, `SaveToIni (??)`, `LoadFromFile (??)`, `SaveToFile (??)`

### 18.6.6 TIniCollectionItem.SaveToFile

**Synopsis:** Save item to a file

**Declaration:** `procedure SaveToFile (FileName: String; Section: String)`

**Visibility:** public

**Description:** `SaveToFile` creates an instance of `TIniFile` with the indicated `FileName` calls `SaveToIni (??)` to save the item to the indicated file in .ini format under the section `Section`

**Errors:** An exception can occur if the file is not writeable.

**See also:** `SaveToIni (??)`, `LoadFromFile (??)`

### 18.6.7 TIniCollectionItem.LoadFromFile

**Synopsis:** Load item from a file

**Declaration:** `procedure LoadFromFile (FileName: String; Section: String)`

**Visibility:** public

**Description:** `LoadFromFile` creates an instance of `TMemIniFile` and calls `LoadFromIni (??)` to load the item from the indicated file in .ini format from the section `Section`.

**Errors:** None.

**See also:** `SaveToFile (??)`, `LoadFromIni (??)`

### 18.6.8 TIniCollectionItem.SectionName

**Synopsis:** Default section name

**Declaration:** `Property SectionName : String`

**Visibility:** public

**Access:** Read, Write

**Description:** `SectionName` is the section name under which the item will be saved or from which it should be read. The read/write functions should be overridden in descendents to determine a unique section name within the .ini file.

**See also:** `SaveToFile (??)`, `LoadFromIni (??)`

## 18.7 TNamedIniCollection

### 18.7.1 Description

TNamedIniCollection is the collection to go with the TNamedIniCollectionItem (452) item class. it provides some functions to look for items based on the UserData (??) or based on the Name (??).

See also: TNamedIniCollectionItem (452), IndexOfUserData (??), IndexOfName (??)

### 18.7.2 Method overview

Page	Property	Description
452	FindByName	Return the item based on its name
452	FindByUserData	Return the item based on its UserData
451	IndexOfName	Search for an item, based on its name, and return its position
451	IndexOfUserData	Search for an item based on it's UserData property

### 18.7.3 Property overview

Page	Property	Access	Description
452	NamedItems	rw	Indexed access to the TNamedIniCollectionItem items

### 18.7.4 TNamedIniCollection.IndexOfUserData

Synopsis: Search for an item based on it's UserData property

Declaration: `function IndexOfUserData(UserData: TObject) : Integer`

Visibility: public

Description: IndexOfUserData searches the list of items and returns the index of the item which has UserData in its UserData (??) property. If no such item exists, -1 is returned.

Note that the (linear) search starts at the last element and works it's way back to the first.

Errors: If no item exists, -1 is returned.

See also: IndexOfName (??), TNamedIniCollectionItem.UserData (??)

### 18.7.5 TNamedIniCollection.IndexOfName

Synopsis: Search for an item, based on its name, and return its position

Declaration: `function IndexOfName(const AName: String) : Integer`

Visibility: public

Description: IndexOfName searches the list of items and returns the index of the item which has name equal to AName (case insensitive). If no such item exists, -1 is returned.

Note that the (linear) search starts at the last element and works it's way back to the first.

Errors: If no item exists, -1 is returned.

See also: IndexOfUserData (??), TNamedIniCollectionItem.Name (??)

### 18.7.6 TNamedIniCollection.FindByName

Synopsis: Return the item based on its name

Declaration: `function FindByName(const AName: String) : TNamedIniCollectionItem`

Visibility: public

Description: `FindByName` returns the collection item whose name matches `AName` (case insensitive match). It calls `IndexOfName (??)` and returns the item at the found position. If no item is found, `Nil` is returned.

Errors: If no item is found, `Nil` is returned.

See also: `IndexOfName (??)`, `FindByUserData (??)`

### 18.7.7 TNamedIniCollection.FindByUserData

Synopsis: Return the item based on its `UserData`

Declaration: `function FindByUserData(UserData: TObject) : TNamedIniCollectionItem`

Visibility: public

Description: `FindByName` returns the collection item whose `UserData (??)` property value matches the `UserData` parameter. If no item is found, `Nil` is returned.

Errors: If no item is found, `Nil` is returned.

### 18.7.8 TNamedIniCollection.NamedItems

Synopsis: Indexed access to the `TNamedIniCollectionItem` items

Declaration: `Property NamedItems[Index: Integer]: TNamedIniCollectionItem; default`

Visibility: public

Access: Read,Write

Description: `NamedItem` is the default property of the `TNamedIniCollection` collection. It allows indexed access to the `TNamedIniCollectionItem` (452) items. The index is zero based.

See also: `TNamedIniCollectionItem` (452)

## 18.8 TNamedIniCollectionItem

### 18.8.1 Description

`TNamedIniCollectionItem` is a `TIniCollectionItem` (449) descent with a published name property. The name is used as the section name when saving the item to the ini file.

See also: `TIniCollectionItem` (449)

### 18.8.2 Property overview

Page	Property	Access	Description
<a href="#">453</a>	<code>Name</code>	rw	Name of the item
<a href="#">453</a>	<code>UserData</code>	rw	User-defined data

### 18.8.3 TNamedIniCollectionItem.UserData

Synopsis: User-defined data

Declaration: `Property UserData : TObject`

Visibility: `public`

Access: `Read,Write`

Description: `UserData` can be used to associate an arbitrary object with the item - much like the `Objects` property of a `TStrings`.

### 18.8.4 TNamedIniCollectionItem.Name

Synopsis: Name of the item

Declaration: `Property Name : String`

Visibility: `published`

Access: `Read,Write`

Description: `Name` is the name of this item. It is also used as the section name when writing the collection item to the `.ini` file.

See also: `TNamedIniCollectionItem.UserData` (??)

## Chapter 19

# Reference for unit 'IniFiles'

### 19.1 Used units

Table 19.1: Used units by unit 'IniFiles'

Name	Page
Classes	??
contnrs	<a href="#">105</a>
System	??
sysutils	??

### 19.2 Overview

IniFiles provides support for handling .ini files. It contains an implementation completely independent of the Windows API for handling such files. The basic (abstract) functionality is defined in TCustomIniFile ([454](#)) and is implemented in TIniFile ([465](#)) and TMemIniFile ([474](#)). The API presented by these components is Delphi compatible.

### 19.3 TCustomIniFile

#### 19.3.1 Description

TCustomIniFile implements all calls for manipulating a .ini. It does not implement any of this behaviour, the behaviour must be implemented in a descendent class like TIniFile ([465](#)) or TMemIniFile ([474](#)).

Since TCustomIniFile is an abstract class, it should never be created directly. Instead, one of the TIniFile or TMemIniFile classes should be created.

See also: TIniFile ([465](#)), TMemIniFile ([474](#))

### 19.3.2 Method overview

Page	Property	Description
<a href="#">455</a>	Create	Instantiate a new instance of TCustomIniFile.
<a href="#">462</a>	DeleteKey	Delete a key from a section
<a href="#">456</a>	Destroy	Remove the TCustomIniFile instance from memory
<a href="#">462</a>	EraseSection	Clear a section
<a href="#">459</a>	ReadBinaryStream	Read binary data
<a href="#">457</a>	ReadBool	
<a href="#">458</a>	ReadDate	Read a date value
<a href="#">458</a>	ReadDateTime	Read a Date/Time value
<a href="#">459</a>	ReadFloat	Read a floating point value
<a href="#">457</a>	ReadInteger	Read an integer value from the file
<a href="#">461</a>	ReadSection	Read the key names in a section
<a href="#">461</a>	ReadSections	Read the list of sections
<a href="#">462</a>	ReadSectionValues	Read names and values of a section
<a href="#">456</a>	ReadString	Read a string valued key
<a href="#">459</a>	ReadTime	Read a time value
<a href="#">456</a>	SectionExists	Check if a section exists.
<a href="#">462</a>	UpdateFile	Update the file on disk
<a href="#">463</a>	ValueExists	Check if a value exists
<a href="#">461</a>	WriteBinaryStream	Write binary data
<a href="#">458</a>	WriteBool	Write boolean value
<a href="#">460</a>	WriteDate	Write date value
<a href="#">460</a>	WriteDateTime	Write date/time value
<a href="#">460</a>	WriteFloat	Write a floating-point value
<a href="#">457</a>	WriteInteger	Write an integer value
<a href="#">457</a>	WriteString	Write a string value
<a href="#">460</a>	WriteTime	Write time value

### 19.3.3 Property overview

Page	Property	Access	Description
<a href="#">463</a>	CaseSensitive	rw	Are key and section names case sensitive
<a href="#">463</a>	EscapeLineFeeds	r	Should linefeeds be escaped ?
<a href="#">463</a>	FileName	r	Name of the .ini file
<a href="#">464</a>	StripQuotes	rw	Should quotes be stripped from string values

### 19.3.4 TCustomIniFile.Create

Synopsis: Instantiate a new instance of TCustomIniFile.

Declaration: `constructor Create(const AFileName: String; AEscapeLineFeeds: Boolean)  
; Virtual`

Visibility: public

Description: Create creates a new instance of TCustomIniFile and loads it with the data from AFileName, if this file exists. If the AEscapeLineFeeds parameter is True, then lines which have their end-of-line markers escaped with a backslash, will be concatenated. This means that the following 2 lines

```
Description=This is a \
line with a long text
```



is equivalent to

```
Description=This is a line with a long text
```

By default, not escaping of linefeeds is performed (for Delphi compatibility)

Errors: If the file cannot be read, an exception may be raised.

See also: `Destroy` (??)

### 19.3.5 TCustomIniFile.Destroy

Synopsis: Remove the `TCustomIniFile` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up all internal structures and then calls the inherited `Destroy`.

See also: `TCustomIniFile` ([454](#))

### 19.3.6 TCustomIniFile.SectionExists

Synopsis: Check if a section exists.

Declaration: `function SectionExists(const Section: String) : Boolean; Virtual`

Visibility: `public`

Description: `SectionExists` returns `True` if a section with name `Section` exists, and contains keys. (comments are not considered keys)

See also: `TCustomIniFile.ValueExists` (??)

### 19.3.7 TCustomIniFile.ReadString

Synopsis: Read a string valued key

Declaration: `function ReadString(const Section: String; const Ident: String;  
const Default: String) : String; Virtual; Abstract`

Visibility: `public`

Description: `ReadString` reads the key `Ident` in section `Section`, and returns the value as a string. If the specified key or section do not exist, then the value in `Default` is returned. Note that if the key exists, but is empty, an empty string will be returned.

See also: `WriteString` (??), `ReadInteger` (??), `ReadBool` (??), `ReadDate` (??), `ReadDateTime` (??), `ReadTime` (??), `ReadFloat` (??), `ReadBinaryStream` (??)

### 19.3.8 TCustomIniFile.WriteString

Synopsis: Write a string value

Declaration: `procedure WriteString(const Section: String;const Ident: String;  
const Value: String); Virtual; Abstract`

Visibility: public

Description: `WriteString` writes the string `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

See also: `ReadString` (??), `WriteInteger` (??), `WriteBool` (??), `WriteDate` (??), `WriteDateTime` (??), `WriteTime` (??), `WriteFloat` (??), `WriteBinaryStream` (??)

### 19.3.9 TCustomIniFile.ReadInteger

Synopsis: Read an integer value from the file

Declaration: `function ReadInteger(const Section: String;const Ident: String;  
Default: LongInt) : LongInt; Virtual`

Visibility: public

Description: `ReadInteger` reads the key `Ident` in section `Section`, and returns the value as an integer. If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid integer value, `Default` is also returned.

See also: `WriteInteger` (??), `ReadString` (??), `ReadBool` (??), `ReadDate` (??), `ReadDateTime` (??), `ReadTime` (??), `ReadFloat` (??), `ReadBinaryStream` (??)

### 19.3.10 TCustomIniFile.WriteInteger

Synopsis: Write an integer value

Declaration: `procedure WriteInteger(const Section: String;const Ident: String;  
Value: LongInt); Virtual`

Visibility: public

Description: `WriteInteger` writes the integer `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

See also: `ReadInteger` (??), `WriteString` (??), `WriteBool` (??), `WriteDate` (??), `WriteDateTime` (??), `WriteTime` (??), `WriteFloat` (??), `WriteBinaryStream` (??)

### 19.3.11 TCustomIniFile.ReadBool

Synopsis:

Declaration: `function ReadBool(const Section: String;const Ident: String;  
Default: Boolean) : Boolean; Virtual`

Visibility: public

Description: `ReadString` reads the key `Ident` in section `Section`, and returns the value as a boolean (valid values are 0 and 1). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid integer value, `False` is also returned.

See also: `WriteBool` (??), `ReadInteger` (??), `ReadString` (??), `ReadDate` (??), `ReadDateTime` (??), `ReadTime` (??), `ReadFloat` (??), `ReadBinaryStream` (??)

### 19.3.12 TCustomIniFile.WriteBool

Synopsis: Write boolean value

Declaration: `procedure WriteBool(const Section: String;const Ident: String;  
Value: Boolean); Virtual`

Visibility: public

Description: `WriteBool` writes the boolean `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

See also: `ReadBool` (??), `WriteInteger` (??), `WriteString` (??), `WriteDate` (??), `WriteDateTime` (??), `WriteTime` (??), `WriteFloat` (??), `WriteBinaryStream` (??)

### 19.3.13 TCustomIniFile.ReadDate

Synopsis: Read a date value

Declaration: `function ReadDate(const Section: String;const Ident: String;  
Default: TDateTime) : TDateTime; Virtual`

Visibility: public

Description: `ReadDate` reads the key `Ident` in section `Section`, and returns the value as a date (`TDateTime`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid date value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct date.

See also: `WriteDate` (??), `ReadInteger` (??), `ReadBool` (??), `ReadString` (??), `ReadDateTime` (??), `ReadTime` (??), `ReadFloat` (??), `ReadBinaryStream` (??)

### 19.3.14 TCustomIniFile.ReadDateTime

Synopsis: Read a Date/Time value

Declaration: `function ReadDateTime(const Section: String;const Ident: String;  
Default: TDateTime) : TDateTime; Virtual`

Visibility: public

Description: `ReadDateTime` reads the key `Ident` in section `Section`, and returns the value as a date/time (`TDateTime`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid date/time value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct date/time.

See also: `WriteDateTime` (??), `ReadInteger` (??), `ReadBool` (??), `ReadDate` (??), `ReadString` (??), `ReadTime` (??), `ReadFloat` (??), `ReadBinaryStream` (??)

### 19.3.15 TCustomIniFile.ReadFloat

Synopsis: Read a floating point value

Declaration: `function ReadFloat(const Section: String;const Ident: String;  
Default: Double) : Double; Virtual`

Visibility: public

Description: `ReadFloat` reads the key `Ident` in section `Section`, and returns the value as a float (`Double`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid float value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct float.

See also: `WriteFloat` (??), `ReadInteger` (??), `ReadBool` (??), `ReadDate` (??), `ReadDateTime` (??), `ReadTime` (??), `ReadString` (??), `ReadBinaryStream` (??)

### 19.3.16 TCustomIniFile.ReadTime

Synopsis: Read a time value

Declaration: `function ReadTime(const Section: String;const Ident: String;  
Default: TDateTime) : TDateTime; Virtual`

Visibility: public

Description: `ReadTime` reads the key `Ident` in section `Section`, and returns the value as a time (`TDateTime`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid time value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct time.

See also: `WriteTime` (??), `ReadInteger` (??), `ReadBool` (??), `ReadDate` (??), `ReadDateTime` (??), `ReadString` (??), `ReadFloat` (??), `ReadBinaryStream` (??)

### 19.3.17 TCustomIniFile.ReadBinaryStream

Synopsis: Read binary data

Declaration: `function ReadBinaryStream(const Section: String;const Name: String;  
Value: TStream) : Integer; Virtual`

Visibility: public

Description: `ReadBinaryStream` reads the key `Name` in section `Section`, and returns the value in the stream `Value`. If the specified key or section do not exist, then the contents of `Value` are left untouched. The stream is not cleared prior to adding data to it.

The data is interpreted as a series of 2-byte hexadecimal values, each representing a byte in the data stream, i.e, it should always be an even number of hexadecimal characters.

See also: `WriteBinaryStream` (??), `ReadInteger` (??), `ReadBool` (??), `ReadDate` (??), `ReadDateTime` (??), `ReadTime` (??), `ReadFloat` (??), `ReadString` (??)

### 19.3.18 TCustomIniFile.WriteDate

Synopsis: Write date value

Declaration: `procedure WriteDate(const Section: String;const Ident: String;  
Value: TDateTime); Virtual`

Visibility: public

Description: `WriteDate` writes the date `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The date is written using the internationalization settings in the `SysUtils` unit.

See also: `ReadDate` (??), `WriteInteger` (??), `WriteBool` (??), `WriteString` (??), `WriteDateTime` (??), `WriteTime` (??), `WriteFloat` (??), `WriteBinaryStream` (??)

### 19.3.19 TCustomIniFile.WriteDateTime

Synopsis: Write date/time value

Declaration: `procedure WriteDateTime(const Section: String;const Ident: String;  
Value: TDateTime); Virtual`

Visibility: public

Description: `WriteDateTime` writes the date/time `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The date/time is written using the internationalization settings in the `SysUtils` unit.

See also: `ReadDateTime` (??), `WriteInteger` (??), `WriteBool` (??), `WriteDate` (??), `WriteString` (??), `WriteTime` (??), `WriteFloat` (??), `WriteBinaryStream` (??)

### 19.3.20 TCustomIniFile.WriteFloat

Synopsis: Write a floating-point value

Declaration: `procedure WriteFloat(const Section: String;const Ident: String;  
Value: Double); Virtual`

Visibility: public

Description: `WriteFloat` writes the time `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The floating point value is written using the internationalization settings in the `SysUtils` unit.

See also: `ReadFloat` (??), `WriteInteger` (??), `WriteBool` (??), `WriteDate` (??), `WriteDateTime` (??), `WriteTime` (??), `WriteString` (??), `WriteBinaryStream` (??)

### 19.3.21 TCustomIniFile.WriteTime

Synopsis: Write time value

Declaration: `procedure WriteTime(const Section: String;const Ident: String;  
Value: TDateTime); Virtual`

Visibility: public

**Description:** `WriteTime` writes the time `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The time is written using the internationalization settings in the `SysUtils` unit.

**See also:** `ReadTime` (??), `WriteInteger` (??), `WriteBool` (??), `WriteDate` (??), `WriteDateTime` (??), `WriteString` (??), `WriteFloat` (??), `WriteBinaryStream` (??)

### 19.3.22 TCustomIniFile.WriteBinaryStream

**Synopsis:** Write binary data

**Declaration:** `procedure WriteBinaryStream(const Section: String;const Name: String; Value: TStream); Virtual`

**Visibility:** public

**Description:** `WriteBinaryStream` writes the binary data in `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

The binary data is encoded using a 2-byte hexadecimal value per byte in the data stream. The data stream must be seekable, so it's size can be determined. The data stream is not repositioned, it must be at the correct position.

**See also:** `ReadBinaryStream` (??), `WriteInteger` (??), `WriteBool` (??), `WriteDate` (??), `WriteDateTime` (??), `WriteTime` (??), `WriteFloat` (??), `WriteString` (??)

### 19.3.23 TCustomIniFile.ReadSection

**Synopsis:** Read the key names in a section

**Declaration:** `procedure ReadSection(const Section: String;Strings: TStrings); Virtual; Abstract`

**Visibility:** public

**Description:** `ReadSection` will return the names of the keys in section `Section` in `Strings`, one string per key. If a non-existing section is specified, the list is cleared. To return the values of the keys as well, the `ReadSectionValues` (??) method should be used.

**See also:** `ReadSections` (??), `SectionExists` (??), `ReadSectionValues` (??)

### 19.3.24 TCustomIniFile.ReadSections

**Synopsis:** Read the list of sections

**Declaration:** `procedure ReadSections(Strings: TStrings); Virtual; Abstract`

**Visibility:** public

**Description:** `ReadSections` returns the names of existing sections in `Strings`. It also returns names of empty sections.

**See also:** `SectionExists` (??), `ReadSectionValues` (??), `ReadSection` (??)

**19.3.25 TCustomIniFile.ReadSectionValues**

Synopsis: Read names and values of a section

Declaration: `procedure ReadSectionValues(const Section: String; Strings: TStrings)  
; Virtual; Abstract`

Visibility: public

Description: `ReadSectionValues` returns the keys and their values in the section `Section` in `Strings`. They are returned as `Key=Value` strings, one per key, so the `Values` property of the stringlist can be used to read the values. To retrieve just the names of the available keys, `ReadSection (??)` can be used.

See also: `SectionExists (??)`, `ReadSections (??)`, `ReadSection (??)`

**19.3.26 TCustomIniFile.EraseSection**

Synopsis: Clear a section

Declaration: `procedure EraseSection(const Section: String); Virtual; Abstract`

Visibility: public

Description: `EraseSection` deletes all values from the section named `Section` and removes the section from the ini file. If the section didn't exist prior to a call to `EraseSection`, nothing happens.

See also: `SectionExists (??)`, `ReadSections (??)`, `DeleteKey (??)`

**19.3.27 TCustomIniFile.DeleteKey**

Synopsis: Delete a key from a section

Declaration: `procedure DeleteKey(const Section: String; const Ident: String); Virtual  
; Abstract`

Visibility: public

Description: `DeleteKey` deletes the key `Ident` from section `Section`. If the key or section didn't exist prior to the `DeleteKey` call, nothing happens.

See also: `EraseSection (??)`

**19.3.28 TCustomIniFile.UpdateFile**

Synopsis: Update the file on disk

Declaration: `procedure UpdateFile; Virtual; Abstract`

Visibility: public

Description: `UpdateFile` writes the in-memory image of the ini-file to disk. To speed up operation of the inifile class, the whole ini-file is read into memory when the class is created, and all operations are performed in-memory. If `CacheUpdates` is set to `True`, any changes to the inifile are only in memory, until they are committed to disk with a call to `UpdateFile`. If `CacheUpdates` is set to `False`, then all operations which cause a change in the .ini file will immediately be committed to disk with a call to `UpdateFile`. Since the whole file is written to disk, this may have serious impact on performance.

See also: `CacheUpdates (??)`

### 19.3.29 TCustomIniFile.ValueExists

Synopsis: Check if a value exists

Declaration: `function ValueExists(const Section: String;const Ident: String)  
: Boolean; Virtual`

Visibility: public

Description: `ValueExists` checks whether the key `Ident` exists in section `Section`. It returns `True` if a key was found, or `False` if not. The key may be empty.

See also: `SectionExists` (??)

### 19.3.30 TCustomIniFile.FileName

Synopsis: Name of the .ini file

Declaration: `Property FileName : String`

Visibility: public

Access: Read

Description: `FileName` is the name of the ini file on disk. It should be specified when the `TCustomIniFile` instance is created. Contrary to the Delphi implementation, if no path component is present in the filename, the filename is not searched in the windows directory.

See also: `Create` (??)

### 19.3.31 TCustomIniFile.EscapeLineFeeds

Synopsis: Should linefeeds be escaped ?

Declaration: `Property EscapeLineFeeds : Boolean`

Visibility: public

Access: Read

Description: `EscapeLineFeeds` determines whether escaping of linefeeds is enabled: For a description of this feature, see `Create` (??), as the value of this property must be specified when the `TCustomIniFile` instance is created.

By default, `EscapeLineFeeds` is `False`.

See also: `Create` (??), `CaseSensitive` (??)

### 19.3.32 TCustomIniFile.CaseSensitive

Synopsis: Are key and section names case sensitive

Declaration: `Property CaseSensitive : Boolean`

Visibility: public

Access: Read,Write

Description: `CaseSensitive` determines whether searches for sections and keys are performed case-sensitive or not. By default, they are not case sensitive.

See also: `EscapeLineFeeds` (??)



### 19.3.3 TCustomIniFile.StripQuotes

Synopsis: Should quotes be stripped from string values

Declaration: `Property StripQuotes : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `StripQuotes` determines whether quotes around string values are stripped from the value when reading the values from file. By default, quotes are not stripped (this is Delphi and Windows compatible).

## 19.4 THashedStringList

### 19.4.1 Description

`THashedStringList` is a `TStringList` (??) descendent which creates has values for the strings and names (in the case of a name-value pair) stored in it. The `IndexOf` (??) and `IndexOfName` (??) functions make use of these hash values to quicklier locate a value.

See also: `IndexOf` (??), `IndexOfName` (??)

### 19.4.2 Method overview

Page	Property	Description
<a href="#">464</a>	<code>Create</code>	Instantiates a new instance of <code>THashedStringList</code>
<a href="#">464</a>	<code>Destroy</code>	Clean up instance
<a href="#">465</a>	<code>IndexOf</code>	Returns the index of a string in the list of strings
<a href="#">465</a>	<code>IndexOfName</code>	Return the index of a name in the list of name=value pairs

### 19.4.3 THashedStringList.Create

Synopsis: Instantiates a new instance of `THashedStringList`

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` calls the inherited `Create`, and then instantiates the hash tables.

Errors: If no enough memory is available, an exception may be raised.

See also: `THashedStringList.Destroy` (??)

### 19.4.4 THashedStringList.Destroy

Synopsis: Clean up instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the hash tables and then calls the inherited `Destroy`.

See also: `THashedStringList.Create` (??)

### 19.4.5 THashedStringList.IndexOf

Synopsis: Returns the index of a string in the list of strings

Declaration: `function IndexOf(const S: String) : Integer; Override`

Visibility: public

Description: `IndexOf` overrides the `#rtl.classes.TStringList.IndexOf (??)` method and uses the hash values to look for the location of `S`.

See also: `#rtl.classes.TStringList.IndexOf (??)`, `THashedStringList.IndexOfName (??)`

### 19.4.6 THashedStringList.IndexOfName

Synopsis: Return the index of a name in the list of name=value pairs

Declaration: `function IndexOfName(const Name: String) : Integer; Override`

Visibility: public

Description: `IndexOfName` overrides the `#rtl.classes.TStrings.IndexOfName (??)` method and uses the hash values of the names to look for the location of `Name`.

See also: `#rtl.classes.TStrings.IndexOfName (??)`, `THashedStringList.IndexOf (??)`

## 19.5 TIniFile

### 19.5.1 Description

`TIniFile` is an implementation of `TCustomIniFile` (454) which does the same as `TMemIniFile` (474), namely it reads the whole file into memory. Unlike `TMemIniFile` it does not cache updates in memory, but immediatly writes any changes to disk.

`TIniFile` introduces no new methods, it just implements the abstract methods introduced in `TCustomIniFile`

See also: `TCustomIniFile` (454), `TMemIniFile` (474)

### 19.5.2 Method overview

Page	Property	Description
<a href="#">466</a>	Create	Create a new instance of <code>TIniFile</code>
<a href="#">468</a>	DeleteKey	Delete key
<a href="#">466</a>	Destroy	Remove the <code>TIniFile</code> instance from memory
<a href="#">468</a>	EraseSection	
<a href="#">467</a>	ReadSection	Read the key names in a section
<a href="#">467</a>	ReadSectionRaw	Read raw section
<a href="#">467</a>	ReadSections	Read section names
<a href="#">468</a>	ReadSectionValues	
<a href="#">466</a>	ReadString	Read a string
<a href="#">468</a>	UpdateFile	Update the file on disk
<a href="#">467</a>	WriteString	Write string to file

### 19.5.3 Property overview

Page	Property	Access	Description
<a href="#">469</a>	CacheUpdates	rw	Should changes be kept in memory
<a href="#">469</a>	Stream	r	Stream from which ini file was read

### 19.5.4 TIniFile.Create

Synopsis: Create a new instance of `TIniFile`

Declaration: `constructor Create(const AFileName: String; AEscapeLineFeeds: Boolean)`  
`; Override`  
`constructor Create(AStream: TStream; AEscapeLineFeeds: Boolean)`

Visibility: `public`

Description: `Create` creates a new instance of `TIniFile` and initializes the class by reading the file from disk if the filename `AFileName` is specified, or from stream in case `AStream` is specified. It also sets most variables to their initial values, i.e. `AEscapeLineFeeds` is saved prior to reading the file, and `Cacheupdates` is set to `False`.

See also: `TCustomIniFile` ([454](#)), `TMemIniFile` ([474](#))

### 19.5.5 TIniFile.Destroy

Synopsis: Remove the `TIniFile` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` writes any pending changes to disk, and cleans up the `TIniFile` structures, and then calls the inherited `Destroy`, effectively removing the instance from memory.

Errors: If an error happens when the file is written to disk, an exception will be raised.

See also: `UpdateFile` ([??](#)), `CacheUpdates` ([??](#))

### 19.5.6 TIniFile.ReadString

Synopsis: Read a string

Declaration: `function ReadString(const Section: String; const Ident: String;`  
`const Default: String) : String; Override`

Visibility: `public`

Description: `ReadString` implements the `TCustomIniFile.ReadString` ([??](#)) abstract method by looking at the in-memory copy of the ini file and returning the string found there.

See also: `TCustomIniFile.ReadString` ([??](#))

### 19.5.7 TIniFile.WriteString

Synopsis: Write string to file

Declaration: `procedure WriteString(const Section: String; const Ident: String;  
const Value: String); Override`

Visibility: public

Description: `WriteString` implements the `TCustomIniFile.WriteString` (??) abstract method by writing the string to the in-memory copy of the ini file. If `CacheUpdates` (??) property is `False`, then the whole file is immediatly written to disk as well.

Errors: If an error happens when the file is written to disk, an exception will be raised.

### 19.5.8 TIniFile.ReadSection

Synopsis: Read the key names in a section

Declaration: `procedure ReadSection(const Section: String; Strings: TStrings)  
; Override`

Visibility: public

Description: `ReadSection` reads the key names from `Section` into `Strings`, taking the in-memory copy of the ini file. This is the implementation for the abstract `TCustomIniFile.ReadSection` (??)

See also: `TCustomIniFile.ReadSection` (??), `TIniFile.ReadSectionRaw` (??)

### 19.5.9 TIniFile.ReadSectionRaw

Synopsis: Read raw section

Declaration: `procedure ReadSectionRaw(const Section: String; Strings: TStrings)`

Visibility: public

Description: `ReadSectionRaw` returns the contents of the section `Section` as it is: this includes the comments in the section. (these are also stored in memory)

See also: `TIniFile.ReadSection` (??), `TCustomIniFile.ReadSection` (??)

### 19.5.10 TIniFile.ReadSections

Synopsis: Read section names

Declaration: `procedure ReadSections(Strings: TStrings); Override`

Visibility: public

Description: `ReadSections` is the implementation of `TCustomIniFile.ReadSections` (??). It operates on the in-memory copy of the inifile, and places all section names in `Strings`.

See also: `TIniFile.ReadSection` (??), `TCustomIniFile.ReadSections` (??), `TIniFile.ReadSectionValues` (??)

### 19.5.11 TIniFile.ReadSectionValues

Synopsis:

Declaration: `procedure ReadSectionValues(const Section: String; Strings: TStrings)  
; Override`

Visibility: public

Description: `ReadSectionValues` is the implementation of `TCustomIniFile.ReadSectionValues` (?). It operates on the in-memory copy of the ini file, and places all key names from `Section` together with their values in `Strings`.

See also: `TIniFile.ReadSection` (?), `TCustomIniFile.ReadSectionValues` (?), `TIniFile.ReadSections` (??)

### 19.5.12 TIniFile.EraseSection

Synopsis:

Declaration: `procedure EraseSection(const Section: String); Override`

Visibility: public

Description: `EraseSection` deletes the section `Section` from memory, if `CacheUpdates` (??) is `False`, then the file is immediately updated on disk. This method is the implementation of the abstract `TCustomIniFile.EraseSection` (??) method.

See also: `TCustomIniFile.EraseSection` (??), `TIniFile.ReadSection` (??), `TIniFile.ReadSections` (??)

### 19.5.13 TIniFile.DeleteKey

Synopsis: Delete key

Declaration: `procedure DeleteKey(const Section: String; const Ident: String)  
; Override`

Visibility: public

Description: `DeleteKey` deletes the `Ident` from the section `Section`. This operation is performed on the in-memory copy of the ini file. if `CacheUpdates` (??) is `False`, then the file is immediately updated on disk.

See also: `CacheUpdates` (??)

### 19.5.14 TIniFile.UpdateFile

Synopsis: Update the file on disk

Declaration: `procedure UpdateFile; Override`

Visibility: public

Description: `UpdateFile` writes the in-memory data for the ini file to disk. The whole file is written. If the ini file was instantiated from a stream, then the stream is updated. Note that the stream must be seekable for this to work correctly. The ini file is marked as 'clean' after a call to `UpdateFile` (i.e. not in need of writing to disk).

Errors: If an error occurs when writing to stream or disk, an exception may be raised.

See also: `CacheUpdates` (??)

### 19.5.15 TIniFile.Stream

Synopsis: Stream from which ini file was read

Declaration: `Property Stream : TStream`

Visibility: public

Access: Read

Description: `Stream` is the stream which was used to create the `IniFile`. The `UpdateFile (??)` method will use this stream to write changes to.

See also: `Create (??)`, `UpdateFile (??)`

### 19.5.16 TIniFile.CacheUpdates

Synopsis: Should changes be kept in memory

Declaration: `Property CacheUpdates : Boolean`

Visibility: public

Access: Read,Write

Description: `CacheUpdates` determines how to deal with changes to the ini-file data: if set to `True` then changes are kept in memory till the file is written to disk with a call to `UpdateFile (??)`. If it is set to `False` then each call that changes the data of the ini-file will result in a call to `UpdateFile`. This is the default behaviour, but it may adversely affect performance.

See also: `UpdateFile (??)`

## 19.6 TIniFileKey

### 19.6.1 Description

`TIniFileKey` is used to keep the key/value pairs in the ini file in memory. It is an internal structure, used internally by the `TIniFile (465)` class.

See also: `TIniFile (465)`

### 19.6.2 Method overview

Page	Property	Description
<a href="#">470</a>	Create	Create a new instance of <code>TIniFileKey</code>

### 19.6.3 Property overview

Page	Property	Access	Description
<a href="#">470</a>	Ident	rw	Key name
<a href="#">470</a>	Value	rw	Key value

### 19.6.4 TIniFileKey.Create

Synopsis: Create a new instance of TIniFileKey

Declaration: `constructor Create(const AIdent: String; const AValue: String)`

Visibility: public

Description: `Create` instantiates a new instance of TIniFileKey on the heap. It fills `Ident` (??) with `AIdent` and `Value` (??) with `AValue`.

See also: `Ident` (??), `Value` (??)

### 19.6.5 TIniFileKey.Ident

Synopsis: Key name

Declaration: `Property Ident : String`

Visibility: public

Access: Read, Write

Description: `Ident` is the key value part of the key/value pair.

See also: `Value` (??)

### 19.6.6 TIniFileKey.Value

Synopsis: Key value

Declaration: `Property Value : String`

Visibility: public

Access: Read, Write

Description: `Value` is the value part of the key/value pair.

See also: `Ident` (??)

## 19.7 TIniFileKeyList

### 19.7.1 Description

TIniFileKeyList maintains a list of TIniFileKey (469) instances on behalf of the TIniFileSection (471) class. It stores the keys of one section of the .ini files.

See also: TIniFileKey (469), TIniFileSection (471)

### 19.7.2 Method overview

Page	Property	Description
471	Clear	Clear the list
471	Destroy	Free the instance

### 19.7.3 Property overview

Page	Property	Access	Description
<a href="#">471</a>	Items	r	Indexed access to <code>TIniFileKey</code> items in the list

### 19.7.4 `TIniFileKeyList.Destroy`

Synopsis: Free the instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears up the list using `Clear` (??) and then calls the inherited destroy.

See also: `Clear` (??)

### 19.7.5 `TIniFileKeyList.Clear`

Synopsis: Clear the list

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: `Clear` removes all `TIniFileKey` ([469](#)) instances from the list, and frees the instances.

See also: `TIniFileKey` ([469](#))

### 19.7.6 `TIniFileKeyList.Items`

Synopsis: Indexed access to `TIniFileKey` items in the list

Declaration: `Property Items[Index: Integer]: TIniFileKey; default`

Visibility: `public`

Access: `Read`

Description: `Items` provides indexed access to the `TIniFileKey` ([469](#)) items in the list. The index is zero-based and runs from 0 to `Count-1`.

See also: `TIniFileKey` ([469](#))

## 19.8 `TIniFileSection`

### 19.8.1 Description

`TIniFileSection` is a class which represents a section in the .ini, and is used internally by the `TIniFile` ([465](#)) class (one instance of `TIniFileSection` is created for each section in the file by the `TIniFileSectionList` ([473](#)) list). The name of the section is stored in the `Name` (??) property, and the key/value pairs in this section are available in the `KeyList` (??) property.

See also: `TIniFileKeyList` ([470](#)), `TIniFile` ([465](#)), `TIniFileSectionList` ([473](#))



### 19.8.2 Method overview

Page	Property	Description
<a href="#">472</a>	Create	Create a new section object
<a href="#">472</a>	Destroy	Free the section object from memory
<a href="#">472</a>	Empty	Is the section empty

### 19.8.3 Property overview

Page	Property	Access	Description
<a href="#">473</a>	KeyList	r	List of key/value pairs in this section
<a href="#">472</a>	Name	r	Name of the section

### 19.8.4 TIniFileSection.Empty

Synopsis: Is the section empty

Declaration: `function Empty : Boolean`

Visibility: public

Description: `Empty` returns `True` if the section contains no key values (even if they are empty). It may contain comments.

### 19.8.5 TIniFileSection.Create

Synopsis: Create a new section object

Declaration: `constructor Create(const AName: String)`

Visibility: public

Description: `Create` instantiates a new `TIniFileSection` class, and sets the name to `AName`. It allocates a `TIniFileKeyList` ([470](#)) instance to keep all the key/value pairs for this section.

See also: `TIniFileKeyList` ([470](#))

### 19.8.6 TIniFileSection.Destroy

Synopsis: Free the section object from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` cleans up the key list, and then calls the inherited `Destroy`, removing the `TIniFileSection` instance from memory.

See also: `Create` ([??](#)), `TIniFileKeyList` ([470](#))

### 19.8.7 TIniFileSection.Name

Synopsis: Name of the section

Declaration: `Property Name : String`

Visibility: public

Access: Read

Description: Name is the name of the section in the file.

See also: TIniFileSection.KeyList (??)

### 19.8.8 TIniFileSection.KeyList

Synopsis: List of key/value pairs in this section

Declaration: Property KeyList : TIniFileKeyList

Visibility: public

Access: Read

Description: KeyList is the TIniFileKeyList (470) instance that is used by the TIniFileSection to keep the key/value pairs of the section.

See also: TIniFileSection.Name (??), TIniFileKeyList (470)

## 19.9 TIniFileSectionList

### 19.9.1 Description

TIniFileSectionList maintains a list of TIniFileSection (471) instances, one for each section in an .ini file. TIniFileSectionList is used internally by the TIniFile (465) class to represent the sections in the file.

See also: TIniFileSection (471), TIniFile (465)

### 19.9.2 Method overview

Page	Property	Description
<a href="#">474</a>	Clear	Clear the list
<a href="#">473</a>	Destroy	Free the object from memory

### 19.9.3 Property overview

Page	Property	Access	Description
<a href="#">474</a>	Items	r	Indexed access to all the section objects in the list

### 19.9.4 TIniFileSectionList.Destroy

Synopsis: Free the object from memory

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy calls Clear (??) to clear the section list and the calls the inherited Destroy

See also: Clear (??)

### 19.9.5 TIniFileSectionList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: `Clear` removes all `TIniFileSection` (471) items from the list, and frees the items it removes from the list.

See also: `TIniFileSection` (471), `TIniFileSectionList.Items` (??)

### 19.9.6 TIniFileSectionList.Items

Synopsis: Indexed access to all the section objects in the list

Declaration: `Property Items[Index: Integer]: TIniFileSection; default`

Visibility: `public`

Access: `Read`

Description: `Items` provides indexed access to all the section objects in the list. `Index` should run from 0 to `Count-1`.

See also: `TIniFileSection` (471), `TIniFileSectionList.Clear` (??)

## 19.10 TMemIniFile

### 19.10.1 Description

`TMemIniFile` is a simple descendent of `TIniFile` (465) which introduces some extra methods to be compatible to the Delphi implementation of `TMemIniFile`. The FPC implementation of `TIniFile` is implemented as a `TMemIniFile`, except that `TIniFile` does not cache its updates, and `TMemIniFile` does.

See also: `TIniFile` (465), `TCustomIniFile` (454), `CacheUpdates` (??)

### 19.10.2 Method overview

Page	Property	Description
475	<code>Clear</code>	Clear the data
474	<code>Create</code>	Create a new instance of <code>TMemIniFile</code>
475	<code>GetStrings</code>	Get contents of ini file as stringlist
475	<code>Rename</code>	Rename the ini file
475	<code>SetStrings</code>	Set data from a stringlist

### 19.10.3 TMemIniFile.Create

Synopsis: Create a new instance of `TMemIniFile`

Declaration: `constructor Create(const AFileName: String; AEscapeLineFeeds: Boolean)  
; Override`

Visibility: `public`

**Description:** `Create` simply calls the inherited `Create` (??), and sets the `CacheUpdates` (??) to `True` so updates will be kept in memory till they are explicitly written to disk.

See also: `TIniFile.Create` (??), `CacheUpdates` (??)

#### 19.10.4 TMemIniFile.Clear

**Synopsis:** Clear the data

**Declaration:** `procedure Clear`

**Visibility:** `public`

**Description:** `Clear` removes all sections and key/value pairs from memory. If `CacheUpdates` (??) is set to `False` then the file on disk will immediatly be emptied.

See also: `SetStrings` (??), `GetStrings` (??)

#### 19.10.5 TMemIniFile.GetStrings

**Synopsis:** Get contents of ini file as stringlist

**Declaration:** `procedure GetStrings(List: TStrings)`

**Visibility:** `public`

**Description:** `GetStrings` returns the whole contents of the ini file in a single stringlist, `List`. This includes comments and empty sections.

The `GetStrings` call can be used to get data for a call to `SetStrings` (??), which can be used to copy data between 2 in-memory ini files.

See also: `SetStrings` (??), `Clear` (??)

#### 19.10.6 TMemIniFile.Rename

**Synopsis:** Rename the ini file

**Declaration:** `procedure Rename(const AFileName: String; Reload: Boolean)`

**Visibility:** `public`

**Description:** `Rename` will rename the ini file with the new name `AFileName`. If `Reload` is `True` then the in-memory contents will be cleared and replaced with the contents found in `AFileName`, if it exists. If `Reload` is `False`, the next call to `UpdateFile` will replace the contents of `AFileName` with the in-memory data.

See also: `UpdateFile` (??)

#### 19.10.7 TMemIniFile.SetStrings

**Synopsis:** Set data from a stringlist

**Declaration:** `procedure SetStrings(List: TStrings)`

**Visibility:** `public`

**Description:** `SetStrings` sets the in-memory data from the `List` stringlist. The data is first cleared.

The `SetStrings` call can be used to set the data of the ini file to a list of strings obtained with `GetStrings (??)`. The two calls combined can be used to copy data between 2 in-memory ini files.

**See also:** `GetStrings (??)`, `Clear (??)`

# Chapter 20

## Reference for unit 'iostream'

### 20.1 Used units

Table 20.1: Used units by unit 'iostream'

Name	Page
Classes	??
System	??

### 20.2 Overview

The `iostream` implements a descendent of `THandleStream` (??) streams that can be used to read from standard input and write to standard output and standard diagnostic output (`stderr`).

### 20.3 Constants, types and variables

#### 20.3.1 Types

`TIOSType = (iosInput, iosOutPut, iosError)`

Table 20.2: Enumeration values for type `TIOSType`

Value	Explanation
<code>iosError</code>	The stream can be used to write to standard diagnostic output
<code>iosInput</code>	The stream can be used to read from standard input
<code>iosOutPut</code>	The stream can be used to write to standard output

`TIOSType` is passed to the `Create` (??) constructor of `TIOStream` (478), it determines what kind of stream is created.

## 20.4 EIOStreamError

### 20.4.1 Description

Error thrown in case of an invalid operation on a TIOStream ([478](#)).

## 20.5 TIOStream

### 20.5.1 Description

TIOStream can be used to create a stream which reads from or writes to the standard input, output or stderr file descriptors. It is a descendent of THandleStream. The type of stream that is created is determined by the TIOSType ([477](#)) argument to the constructor. The handle of the standard input, output or stderr file descriptors is determined automatically.

The TIOStream keeps an internal Position, and attempts to provide minimal Seek (??) behaviour based on this position.

See also: TIOSType ([477](#)), THandleStream (??)

### 20.5.2 Method overview

Page	Property	Description
<a href="#">478</a>	Create	Construct a new instance of TIOStream ( <a href="#">478</a> )
<a href="#">478</a>	Read	Read data from the stream.
<a href="#">479</a>	Seek	Set the stream position
<a href="#">479</a>	Write	Write data to the stream

### 20.5.3 TIOStream.Create

Synopsis: Construct a new instance of TIOStream ([478](#))

Declaration: `constructor Create(aIOSType: TIOSType)`

Visibility: public

Description: Create creates a new instance of TIOStream ([478](#)), which can subsequently be used

Errors: No checking is performed to see whether the requested file descriptor is actually open for reading/writing. In that case, subsequent calls to Read or Write or seek will fail.

See also: TIOStream.Read (??), TIOStream.Write (??)

### 20.5.4 TIOStream.Read

Synopsis: Read data from the stream.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: Read checks first whether the type of the stream allows reading (type is iosInput). If not, it raises a EIOStreamError ([478](#)) exception. If the stream can be read, it calls the inherited Read to actually read the data.

**Errors:** An `EIOStreamError` exception is raised if the stream does not allow reading.

See also: `TIOSType` (477), `TIOStream.Write` (??)

### 20.5.5 TIOStream.Write

**Synopsis:** Write data to the stream

**Declaration:** `function Write(const Buffer;Count: LongInt) : LongInt; Override`

**Visibility:** `public`

**Description:** `Write` checks first whether the type of the stream allows writing (type is `iosOutput` or `iosError`). If not, it raises a `EIOStreamError` (478) exception. If the stream can be written to, it calls the inherited `Write` to actually read the data.

**Errors:** An `EIOStreamError` exception is raised if the stream does not allow writing.

See also: `TIOSType` (477), `TIOStream.Read` (??)

### 20.5.6 TIOStream.Seek

**Synopsis:** Set the stream position

**Declaration:** `function Seek(const Offset: Int64;Origin: TSeekOrigin) : Int64; Override`

**Visibility:** `public`

**Description:** `Seek` overrides the standard `Seek` implementation. Normally, standard input, output and `stderr` are not seekable. The `TIOStream` stream tries to provide seek capabilities for the following limited number of cases:

**Origin=soFromBeginning** If `Offset` is larger than the current position, then the remaining bytes are skipped by reading them from the stream and discarding them, if the stream is of type `iosInput`.

**Origin=soFromCurrent** If `Offset` is zero, the current position is returned. If it is positive, then `Offset` bytes are skipped by reading them from the stream and discarding them, if the stream is of type `iosInput`.

All other cases will result in a `EIOStreamError` exception.

**Errors:** An `EIOStreamError` (478) exception is raised if the stream does not allow the requested seek operation.

See also: `EIOStreamError` (478)



# Chapter 21

## Reference for unit 'libtar'

### 21.1 Used units

Table 21.1: Used units by unit 'libtar'

Name	Page
BaseUnix	??
Classes	??
System	??
sysutils	??
Unix	??
UnixType	??
Windows	??

### 21.2 Overview

The `libtar` units provides 2 classes to read and write `.tar` archives: `TTarArchive` ([484](#)) class can be used to read a tar file, and the `TTarWriter` ([486](#)) class can be used to write a tar file. The unit was implemented originally by Stefan Heymann.

### 21.3 Constants, types and variables

#### 21.3.1 Constants

`ALL_PERMISSIONS` = [`tpReadByOwner`, `tpWriteByOwner`, `tpExecuteByOwner`, `tpReadByGroup`, `tpWriteByGroup`, `tpExecuteByGroup`, `tpReadByOther`, `tpWriteByOther`, `tpExecuteByOther`]

`ALL_PERMISSIONS` is a set constant containing all possible permissions (read/write/execute, for all groups of users) for an archive entry.

`EXECUTE_PERMISSIONS` = [`tpExecuteByOwner`, `tpExecuteByGroup`, `tpExecuteByOther`]

`WRITE_PERMISSIONS` is a set constant containing all possible execute permissions set for an archive entry.

```
FILETYPE_NAME : Array[TFileType] of String = ('Regular', 'Link', 'Symbolic Link', 'C
```

FILETYPE\_NAME can be used to get a textual description for each of the possible entry file types.

```
READ_PERMISSIONS = [tpReadByOwner, tpReadByGroup, tpReadByOther]
```

READ\_PERMISSIONS is a set constant containing all possible read permissions set for an archive entry.

```
WRITE_PERMISSIONS = [tpWriteByOwner, tpWriteByGroup, tpWriteByOther]
```

WRITE\_PERMISSIONS is a set constant containing all possible write permissions set for an archive entry.

### 21.3.2 Types

```
TFileType = (ftNormal, ftLink, ftSymbolicLink, ftCharacter, ftBlock,
             ftDirectory, ftFifo, ftContiguous, ftDumpDir, ftMultiVolume,
             ftVolumeHeader)
```

Table 21.2: Enumeration values for type TFileType

Value	Explanation
ftBlock	Block device file
ftCharacter	Character device file
ftContiguous	Contiguous file
ftDirectory	Directory
ftDumpDir	List of files
ftFifo	FIFO file
ftLink	Hard link
ftMultiVolume	Multi-volume file part
ftNormal	Normal file
ftSymbolicLink	Symbolic link
ftVolumeHeader	Volume header, can appear only as first entry in the archive

TFileType describes the file type of a file in the archive. It is used in the FileType field of the TTarDirRec (482) record.

```
TTarDirRec = record
  Name : AnsiString;
  Size : Int64;
  DateTime : TDateTime;
  Permissions : TTarPermissions;
  FileType : TFileType;
  LinkName : AnsiString;
  UID : Integer;
  GID : Integer;
  UserName : AnsiString;
  GroupName : AnsiString;
  ChecksumOK : Boolean;
```

```

Mode : TTarModes;
Magic : AnsiString;
MajorDevNo : Integer;
MinorDevNo : Integer;
FilePos : Int64;
end

```

TTarDirRec describes an entry in the tar archive. It is similar to a directory entry as in TSearchRec (??), and is returned by the TTarArchive.FindNext (??) call.

```
TTarMode = (tmSetUid, tmSetGid, tmSaveText)
```

Table 21.3: Enumeration values for type TTarMode

Value	Explanation
tmSaveText	Bit \$200 is set
tmSetGid	File has SetGID bit set
tmSetUid	File has SetUID bit set.

TTarMode describes extra file modes. It is used in the Mode field of the TTarDirRec (482) record.

```
TTarModes= Set of (tmSaveText, tmSetGid, tmSetUid)
```

TTarModes denotes the full set of permission bits for the file in the field Mode field of the TTarDirRec (482) record.

```

TTarPermission = (tpReadByOwner, tpWriteByOwner, tpExecuteByOwner,
                  tpReadByGroup, tpWriteByGroup, tpExecuteByGroup,
                  tpReadByOther, tpWriteByOther, tpExecuteByOther)

```

Table 21.4: Enumeration values for type TTarPermission

Value	Explanation
tpExecuteByGroup	Group can execute the file
tpExecuteByOther	Other people can execute the file
tpExecuteByOwner	Owner can execute the file
tpReadByGroup	Group can read the file
tpReadByOther	Other people can read the file.
tpReadByOwner	Owner can read the file
tpWriteByGroup	Group can write the file
tpWriteByOther	Other people can write the file
tpWriteByOwner	Owner can write the file

TTarPermission denotes part of a files permission as it is stored in the .tar archive. Each of these enumerated constants correspond with one of the permission bits from a unix file permission.

```
TTarPermissions= Set of (tpExecuteByGroup, tpExecuteByOther,
                        tpExecuteByOwner, tpReadByGroup, tpReadByOther,
                        tpReadByOwner, tpWriteByGroup, tpWriteByOther,
                        tpWriteByOwner)
```

TTarPermissions describes the complete set of permissions that a file has. It is used in the Permissions field of the TTarDirRec (482) record.

## 21.4 Procedures and functions

### 21.4.1 ClearDirRec

Synopsis: Initialize tar archive entry

Declaration: `procedure ClearDirRec(var DirRec: TTarDirRec)`

Visibility: default

Description: ClearDirRec clears the DirRec entry, it basically zeroes out all fields.

See also: TTarDirRec (482)

### 21.4.2 ConvertFilename

Synopsis: Convert filename to archive format

Declaration: `function ConvertFilename(Filename: String) : String`

Visibility: default

Description: ConvertFileName converts the file name FileName to a format allowed by the tar archive. Basically, it converts directory specifiers to forward slashes.

### 21.4.3 FileTimeGMT

Synopsis: Extract filetype

Declaration: `function FileTimeGMT(FileName: String) : TDateTime; Overload`  
`function FileTimeGMT(SearchRec: TSearchRec) : TDateTime; Overload`

Visibility: default

Description: FileTimeGMT returns the timestamp of a filename (FileName must exist) or a search rec (TSearchRec) to a GMT representation that can be used in a tar entry.

See also: TTarDirRec (482)

### 21.4.4 PermissionString

Synopsis: Convert a set of permissions to a string

Declaration: `function PermissionString(Permissions: TTarPermissions) : String`

Visibility: default

Description: PermissionString can be used to convert a set of Permissions to a string in the same format as used by the unix 'ls' command.

See also: TTarPermissions (483)

## 21.5 TTarArchive

### 21.5.1 Description

`TTarArchive` is the class used to read and examine `.tar` archives. It can be constructed from a stream or from a filename. Creating an instance will not perform any operation on the stream yet.

See also: `TTarWriter` (486), `FindNext` (??)

### 21.5.2 Method overview

Page	Property	Description
484	Create	Create a new instance of the archive
484	Destroy	Destroy <code>TTarArchive</code> instance
485	FindNext	Find next archive entry
485	GetFilePos	Return current archive position
485	ReadFile	Read a file from the archive
484	Reset	Reset archive
486	SetFilePos	Set position in archive

### 21.5.3 TTarArchive.Create

Synopsis: Create a new instance of the archive

Declaration: `constructor Create(Stream: TStream); Overload`  
`constructor Create(Filename: String; FileMode: Word); Overload`

Visibility: public

Description: `Create` can be used to create a new instance of `TTarArchive` using either a `StreamTStream` (??) descendent or using a name of a file to open: `FileName`. In case of the filename, an open mode can be specified.

Errors: In case a filename is specified and the file cannot be opened, an exception will occur.

See also: `FindNext` (??)

### 21.5.4 TTarArchive.Destroy

Synopsis: Destroy `TTarArchive` instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` closes the archive stream (if it created a stream) and cleans up the `TTarArchive` instance.

See also: `TTarArchive.Create` (??)

### 21.5.5 TTarArchive.Reset

Synopsis: Reset archive

Declaration: `procedure Reset`

Visibility: public

Description: `Reset` sets the archive file position on the beginning of the archive.

See also: `TTarArchive.Create` (??)

### 21.5.6 `TTarArchive.FindNext`

Synopsis: Find next archive entry

Declaration: `function FindNext (var DirRec: TTarDirRec) : Boolean`

Visibility: public

Description: `FindNext` positions the file pointer on the next archive entry, and returns all information about the entry in `DirRec`. It returns `True` if the operation was successful, or `False` if not (for instance, when the end of the archive was reached).

Errors: In case there are no more entries, `False` is returned.

See also: `TTarArchive.ReadFile` (??)

### 21.5.7 `TTarArchive.ReadFile`

Synopsis: Read a file from the archive

Declaration: `procedure ReadFile (Buffer: POINTER); Overload`  
`procedure ReadFile (Stream: TStream); Overload`  
`procedure ReadFile (Filename: String); Overload`  
`function ReadFile : String; Overload`

Visibility: public

Description: `ReadFile` can be used to read the current file in the archive. It can be called after the archive was successfully positioned on an entry in the archive. The file can be read in various ways:

- directly in a memory buffer. No checks are performed to see whether the buffer points to enough memory.
- It can be copied to a `Stream`.
- It can be copied to a file with name `FileName`.
- The file content can be copied to a string

Errors: An exception may occur if the buffer is not large enough, or when the file specified in `filename` cannot be opened.

### 21.5.8 `TTarArchive.GetFilesPos`

Synopsis: Return current archive position

Declaration: `procedure GetFilesPos (var Current: Int64; var Size: Int64)`

Visibility: public

Description: `GetFilesPos` returns the position in the tar archive in `Current` and the complete archive size in `Size`.

See also: `TTarArchive.SetFilesPos` (??), `TTarArchive.Reset` (??)

## 21.5.9 TTarArchive.SetFilePos

Synopsis: Set position in archive

Declaration: `procedure SetFilePos(NewPos: Int64)`

Visibility: `public`

Description: `SetFilePos` can be used to set the absolute position in the tar archive.

See also: `TTarArchive.Reset` (??), `TTarArchive.GetFilePos` (??)

## 21.6 TTarWriter

### 21.6.1 Description

`TTarWriter` can be used to create `.tar` archives. It can be created using a filename, in which case the archive will be written to the filename, or it can be created using a stream, in which case the archive will be written to the stream - for instance a compression stream.

See also: `TTarArchive` ([484](#))

### 21.6.2 Method overview

Page	Property	Description
<a href="#">488</a>	<code>AddDir</code>	Add directory to archive
<a href="#">487</a>	<code>AddFile</code>	Add a file to the archive
<a href="#">489</a>	<code>AddLink</code>	Add hard link to archive
<a href="#">487</a>	<code>AddStream</code>	Add stream contents to archive.
<a href="#">488</a>	<code>AddString</code>	Add string as file data
<a href="#">488</a>	<code>AddSymbolicLink</code>	Add a symbolic link to the archive
<a href="#">489</a>	<code>AddVolumeHeader</code>	Add volume header entry
<a href="#">486</a>	<code>Create</code>	Create a new archive
<a href="#">487</a>	<code>Destroy</code>	Close archive and clean up <code>TTarWriter</code>
<a href="#">489</a>	<code>Finalize</code>	Finalize the archive

### 21.6.3 Property overview

Page	Property	Access	Description
<a href="#">490</a>	<code>GID</code>	<code>rw</code>	Archive entry group ID
<a href="#">490</a>	<code>GroupName</code>	<code>rw</code>	Archive entry group name
<a href="#">491</a>	<code>Magic</code>	<code>rw</code>	Archive entry Magic constant
<a href="#">491</a>	<code>Mode</code>	<code>rw</code>	Archive entry mode
<a href="#">489</a>	<code>Permissions</code>	<code>rw</code>	Archive entry permissions
<a href="#">490</a>	<code>UID</code>	<code>rw</code>	Archive entry user ID
<a href="#">490</a>	<code>UserName</code>	<code>rw</code>	Archive entry user name

### 21.6.4 TTarWriter.Create

Synopsis: Create a new archive

Declaration: `constructor Create(TargetStream: TStream); Overload`  
`constructor Create(TargetFilename: String; Mode: Integer); Overload`

Visibility: public

**Description:** `Create` creates a new `TTarWriter` instance. This will start a new `.tar` archive. The archive will be written to the `TargetStream` stream or to a file with name `TargetFileName`, which will be opened with filemode `Mode`.

**Errors:** In case `TargetFileName` cannot be opened, an exception will be raised.

See also: `TTarWriter.Destroy` (??)

### 21.6.5 `TTarWriter.Destroy`

**Synopsis:** Close archive and clean up `TTarWriter`

**Declaration:** `destructor Destroy; Override`

Visibility: public

**Description:** `Destroy` will close the archive (i.e. it writes the end-of-archive marker, if it was not yet written), and then frees the `TTarWriter` instance.

See also: `TTarWriter.Finalize` (??)

### 21.6.6 `TTarWriter.AddFile`

**Synopsis:** Add a file to the archive

**Declaration:** `procedure AddFile(Filename: String; TarFilename: AnsiString)`

Visibility: public

**Description:** `AddFile` adds a file to the archive: the contents is read from `FileName`. Optionally, an alternative filename can be specified in `TarFileName`. This name should contain only forward slash path separators. If it is not specified, the name will be computed from `FileName`.

The archive entry is written with the current owner data and permissions.

**Errors:** If `FileName` cannot be opened, an exception will be raised.

See also: `TTarWriter.AddStream` (??), `TTarWriter.AddString` (??), `TTarWriter.AddLink` (??), `TTarWriter.AddSymbolicLink` (??), `TTarWriter.AddDir` (??), `TTarWriter.AddVolumeHeader` (??)

### 21.6.7 `TTarWriter.AddStream`

**Synopsis:** Add stream contents to archive.

**Declaration:** `procedure AddStream(Stream: TStream; TarFilename: AnsiString;  
FileDateGmt: TDateTime)`

Visibility: public

**Description:** `AddStream` will add the contents of `Stream` to the archive. The `Stream` will not be reset: only the contents of the stream from the current position will be written to the archive. The entry will be written with file name `TarFileName`. This name should contain only forward slash path separators. The entry will be written with timestamp `FileDateGmt`.

The archive entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile` (??), `TTarWriter.AddString` (??), `TTarWriter.AddLink` (??), `TTarWriter.AddSymbolicLink` (??), `TTarWriter.AddDir` (??), `TTarWriter.AddVolumeHeader` (??)



### 21.6.8 TTarWriter.AddString

Synopsis: Add string as file data

Declaration: `procedure AddString(Contents: AnsiString; TarFilename: AnsiString;  
FileDateGmt: TDateTime)`

Visibility: public

Description: `AddString` adds the string `Contents` as the data of an entry with file name `TarFileName`. This name should contain only forward slash path separators. The entry will be written with timestamp `FileDateGmt`.

The archive entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile` (??), `TTarWriter.AddStream` (??), `TTarWriter.AddLink` (??), `TTarWriter.AddSymbolicLink` (??), `TTarWriter.AddDir` (??), `TTarWriter.AddVolumeHeader` (??)

### 21.6.9 TTarWriter.AddDir

Synopsis: Add directory to archive

Declaration: `procedure AddDir(Dirname: AnsiString; DateGmt: TDateTime;  
MaxDirSize: Int64)`

Visibility: public

Description: `AddDir` adds a directory entry to the archive. The entry is written with name `DirName`, maximum directory size `MaxDirSize` (0 means unlimited) and timestamp `DateGmt`.

Note that this call only adds an entry for a directory to the archive: if `DirName` is an existing directory, it does not write all files in the directory to the archive.

The directory entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile` (??), `TTarWriter.AddStream` (??), `TTarWriter.AddLink` (??), `TTarWriter.AddSymbolicLink` (??), `TTarWriter.AddString` (??), `TTarWriter.AddVolumeHeader` (??)

### 21.6.10 TTarWriter.AddSymbolicLink

Synopsis: Add a symbolic link to the archive

Declaration: `procedure AddSymbolicLink(Filename: AnsiString; Linkname: AnsiString;  
DateGmt: TDateTime)`

Visibility: public

Description: `AddSymbolicLink` adds a symbolic link entry to the archive, with name `FileName`, pointing to `LinkName`. The entry is written with timestamp `DateGmt`.

The link entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile` (??), `TTarWriter.AddStream` (??), `TTarWriter.AddLink` (??), `TTarWriter.AddDir` (??), `TTarWriter.AddString` (??), `TTarWriter.AddVolumeHeader` (??)

### 21.6.11 TTarWriter.AddLink

Synopsis: Add hard link to archive

Declaration: `procedure AddLink (Filename: AnsiString; Linkname: AnsiString;  
DateGmt: TDateTime)`

Visibility: public

Description: `AddLink` adds a hard link entry to the archive. The entry has name `FileName`, timestamp `DateGmt` and points to `LinkName`.

The link entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile (??)`, `TTarWriter.AddStream (??)`, `TTarWriter.AddSymbolicLink (??)`, `TTarWriter.AddDir (??)`, `TTarWriter.AddString (??)`, `TTarWriter.AddVolumeHeader (??)`

### 21.6.12 TTarWriter.AddVolumeHeader

Synopsis: Add volume header entry

Declaration: `procedure AddVolumeHeader (VolumeId: AnsiString; DateGmt: TDateTime)`

Visibility: public

Description: `AddVolumeHeader` adds a volume header entry to the archive. The entry is written with name `VolumeID` and timestamp `DateGmt`.

The volume header entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile (??)`, `TTarWriter.AddStream (??)`, `TTarWriter.AddSymbolicLink (??)`, `TTarWriter.AddDir (??)`, `TTarWriter.AddString (??)`, `TTarWriter.AddLink (??)`

### 21.6.13 TTarWriter.Finalize

Synopsis: Finalize the archive

Declaration: `procedure Finalize`

Visibility: public

Description: `Finalize` writes the end-of-archive marker to the archive. No more entries can be added after `Finalize` was called.

If the `TTarWriter` instance is destroyed, it will automatically call `finalize` if `finalize` was not yet called.

See also: `TTarWriter.Destroy (??)`

### 21.6.14 TTarWriter.Permissions

Synopsis: Archive entry permissions

Declaration: `Property Permissions : TTarPermissions`

Visibility: public

Access: Read, Write

Description: `Permissions` is used for the permissions field of the archive entries.

See also: `TTarDirRec (482)`

### 21.6.15 TTarWriter.UID

Synopsis: Archive entry user ID

Declaration: `Property UID : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `UID` is used for the `UID` field of the archive entries.

See also: `TTarDirRec` ([482](#))

### 21.6.16 TTarWriter.GID

Synopsis: Archive entry group ID

Declaration: `Property GID : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `GID` is used for the `GID` field of the archive entries.

See also: `TTarDirRec` ([482](#))

### 21.6.17 TTarWriter.UserName

Synopsis: Archive entry user name

Declaration: `Property UserName : AnsiString`

Visibility: `public`

Access: `Read,Write`

Description: `UserName` is used for the `UserName` field of the archive entries.

See also: `TTarDirRec` ([482](#))

### 21.6.18 TTarWriter.GroupName

Synopsis: Archive entry group name

Declaration: `Property GroupName : AnsiString`

Visibility: `public`

Access: `Read,Write`

Description: `GroupName` is used for the `GroupName` field of the archive entries.

See also: `TTarDirRec` ([482](#))

### 21.6.19 TTarWriter.Mode

Synopsis: Archive entry mode

Declaration: `Property Mode : TTarModes`

Visibility: `public`

Access: `Read,Write`

Description: `Mode` is used for the `Mode` field of the archive entries.

See also: `TTarDirRec` ([482](#))

### 21.6.20 TTarWriter.Magic

Synopsis: Archive entry Magic constant

Declaration: `Property Magic : AnsiString`

Visibility: `public`

Access: `Read,Write`

Description: `Magic` is used for the `Magic` field of the archive entries.

See also: `TTarDirRec` ([482](#))

## Chapter 22

# Reference for unit 'Pipes'

### 22.1 Used units

Table 22.1: Used units by unit 'Pipes'

Name	Page
Classes	??
System	??
sysutils	??

### 22.2 Overview

The Pipes unit implements streams that are wrappers around the OS's pipe functionality. It creates a pair of streams, and what is written to one stream can be read from another.

### 22.3 Constants, types and variables

#### 22.3.1 Constants

`ENoSeekMsg = 'Cannot seek on pipes'`

Constant used in `EPipeSeek` ([493](#)) exception.

`EPipeMsg = 'Failed to create pipe.'`

Constant used in `EPipeCreation` ([493](#)) exception.

### 22.4 Procedures and functions

#### 22.4.1 CreatePipeHandles

Synopsis: Function to create a set of pipe handles

**Declaration:** `function CreatePipeHandles(var InHandle: THandle; var OutHandle: THandle)  
: Boolean`

**Visibility:** default

**Description:** `CreatePipeHandles` provides an OS-independent way to create a set of pipe filehandles. These handles are inheritable to child processes. The reading end of the pipe is returned in `InHandle`, the writing end in `OutHandle`.

**Errors:** On error, `False` is returned.

**See also:** `CreatePipeStreams` (493)

## 22.4.2 CreatePipeStreams

**Synopsis:** Create a pair of pipe stream.

**Declaration:** `procedure CreatePipeStreams(var InPipe: TInputPipeStream;  
var OutPipe: TOutputPipeStream)`

**Visibility:** default

**Description:** `CreatePipeStreams` creates a set of pipe file descriptors with `CreatePipeHandles` (492), and if that call is successful, a pair of streams is created: `InPipe` and `OutPipe`.

**Errors:** If no pipe handles could be created, an `EPipeCreation` (493) exception is raised.

**See also:** `CreatePipeHandles` (492), `TInputPipeStream` (493), `TOutputPipeStream` (495)

## 22.5 EPipeCreation

### 22.5.1 Description

Exception raised when an error occurred during the creation of a pipe pair.

## 22.6 EPipeError

### 22.6.1 Description

Exception raised when an invalid operation is performed on a pipe stream.

## 22.7 EPipeSeek

### 22.7.1 Description

Exception raised when an invalid seek operation is attempted on a pipe.

## 22.8 TInputPipeStream

### 22.8.1 Description

`TInputPipeStream` is created by the `CreatePipeStreams` (493) call to represent the reading end of a pipe. It is a `TStream` (??) descendent which does not allow writing, and which mimics the seek operation.

See also: TStream (??), CreatePipeStreams (493), TOutputPipeStream (495)

### 22.8.2 Method overview

Page	Property	Description
495	Read	Read data from the stream to a buffer.
494	Seek	Set the current position of the stream
494	Write	Write data to the stream.

### 22.8.3 Property overview

Page	Property	Access	Description
495	NumBytesAvailable	r	Number of bytes available for reading.

### 22.8.4 TInputPipeStream.Write

Synopsis: Write data to the stream.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` overrides the parent implementation of `Write`. On a `TInputPipeStream` will always raise an exception, as the pipe is read-only.

Errors: An `EStreamError` (??) exception is raised when this function is called.

See also: `Read` (??), `Seek` (??)

### 22.8.5 TInputPipeStream.Seek

Synopsis: Set the current position of the stream

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: public

Description: `Seek` overrides the standard `Seek` implementation. Normally, pipe streams `stderr` are not seekable. The `TInputPipeStream` stream tries to provide seek capabilities for the following limited number of cases:

**Origin=soFromBeginning** If `Offset` is larger than the current position, then the remaining bytes are skipped by reading them from the stream and discarding them.

**Origin=soFromCurrent** If `Offset` is zero, the current position is returned. If it is positive, then `Offset` bytes are skipped by reading them from the stream and discarding them, if the stream is of type `iosInput`.

All other cases will result in a `EPipeSeek` exception.

Errors: An `EPipeSeek` (493) exception is raised if the stream does not allow the requested seek operation.

See also: `EPipeSeek` (493), `Seek` (??)

### 22.8.6 TInputPipeStream.Read

Synopsis: Read data from the stream to a buffer.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: Read calls the inherited read and adjusts the internal position pointer of the stream.

Errors: None.

See also: Write (??), Seek (??)

### 22.8.7 TInputPipeStream.NumBytesAvailable

Synopsis: Number of bytes available for reading.

Declaration: `Property NumBytesAvailable : DWord`

Visibility: public

Access: Read

Description: NumBytesAvailable is the number of bytes available for reading. This is the number of bytes in the OS buffer for the pipe. It is not a number of bytes in an internal buffer.

If this number is nonzero, then reading NumBytesAvailable bytes from the stream will not block the process. Reading more than NumBytesAvailable bytes will block the process, while it waits for the requested number of bytes to become available.

See also: TInputPipeStream.Read (??)

## 22.9 TOutputPipeStream

### 22.9.1 Description

TOutputPipeStream is created by the CreatePipeStreams (493) call to represent the writing end of a pipe. It is a TStream (??) descendent which does not allow reading.

See also: TStream (??), CreatePipeStreams (493), TInputPipeStream (493)

### 22.9.2 Method overview

Page	Property	Description
<a href="#">496</a>	Read	Read data from the stream.
<a href="#">495</a>	Seek	Sets the position in the stream

### 22.9.3 TOutputPipeStream.Seek

Synopsis: Sets the position in the stream

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: public



**Description:** `Seek` is overridden in `TOutputPipeStream`. Calling this method will always raise an exception: an output pipe is not seekable.

**Errors:** An `EPipeSeek` (493) exception is raised if this method is called.

#### 22.9.4 TOutputPipeStream.Read

**Synopsis:** Read data from the stream.

**Declaration:** `function Read(var Buffer; Count: LongInt) : LongInt; Override`

**Visibility:** `public`

**Description:** `Read` overrides the parent `Read` implementation. It always raises an exception, because a output pipe is write-only.

**Errors:** An `EStreamError` (??) exception is raised when this function is called.

**See also:** `Seek` (??)

## Chapter 23

# Reference for unit 'pooledmm'

### 23.1 Used units

Table 23.1: Used units by unit 'pooledmm'

Name	Page
Classes	??
System	??

### 23.2 Overview

`pooledmm` is a memory manager class which uses pools of blocks. Since it is a higher-level implementation of a memory manager which works on top of the FPC memory manager, It also offers more debugging and analysis tools. It is used mainly in the LCL and Lazarus IDE.

### 23.3 Constants, types and variables

#### 23.3.1 Types

```
PPooledMemManagerItem = ^TPooledMemManagerItem
```

`PPooledMemManagerItem` is a pointer type, pointing to a `TPooledMemManagerItem` (498) item, used in a linked list.

```
TEnumItemsMethod = procedure(Item: Pointer) of object
```

`TEnumItemsMethod` is a prototype for the callback used in the `TNonFreePooledMemManager.EnumerateItems` (??) call. The parameter `Item` will be set to each of the pointers in the item list of `TNonFreePooledMemManager` (498).

```
TPooledMemManagerItem = record
  Next : PPooledMemManagerItem;
end
```

`TPooledMemManagerItem` is used internally by the `TPooledMemManager` (500) class to maintain the free list block. It simply points to the next free block.

## 23.4 TNonFreePooledMemManager

### 23.4.1 Description

`TNonFreePooledMemManager` keeps a list of fixed-size memory blocks in memory. Each block has the same size, making it suitable for storing a lot of records of the same type. It does not free the items stored in it, except when the list is cleared as a whole.

It allocates memory for the blocks in an exponential way, i.e. each time a new block of memory must be allocated, its size is the double of the last block. The first block will contain 8 items.

### 23.4.2 Method overview

Page	Property	Description
498	Clear	Clears the memory
498	Create	Creates a new instance of <code>TNonFreePooledMemManager</code>
499	Destroy	Removes the <code>TNonFreePooledMemManager</code> instance from memory
499	EnumerateItems	Enumerate all items in the list
499	NewItem	Return a pointer to a new memory block

### 23.4.3 Property overview

Page	Property	Access	Description
499	ItemSize	r	Size of an item in the list

### 23.4.4 TNonFreePooledMemManager.Clear

Synopsis: Clears the memory

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` clears all blocks from memory, freeing the allocated memory blocks. None of the pointers returned by `NewItem` (??) is valid after a call to `Clear`

See also: `NewItem` (??)

### 23.4.5 TNonFreePooledMemManager.Create

Synopsis: Creates a new instance of `TNonFreePooledMemManager`

Declaration: `constructor Create(TheItemSize: Integer)`

Visibility: `public`

Description: `Create` creates a new instance of `TNonFreePooledMemManager` and sets the item size to `TheItemSize`.

Errors: If not enough memory is available, an exception may be raised.

See also: `TNonFreePooledMemManager.ItemSize` (??)

### 23.4.6 TNonFreePooledMemManager.Destroy

Synopsis: Removes the `TNonFreePooledMemManager` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the list, clears the internal structures, and then calls the inherited `Destroy`.

`Destroy` should never be called directly. Instead `Free` should be used, or `FreeAndNil`

See also: `TNonFreePooledMemManager.Create (??)`, `TNonFreePooledMemManager.Clear (??)`

### 23.4.7 TNonFreePooledMemManager.NewItem

Synopsis: Return a pointer to a new memory block

Declaration: `function NewItem : Pointer`

Visibility: `public`

Description: `NewItem` returns a pointer to an unused memory block of size `ItemSize (??)`. It will allocate new memory on the heap if necessary.

Note that there is no way to mark the memory block as free, except by clearing the whole list.

Errors: If no more memory is available, an exception may be raised.

See also: `TNonFreePooledMemManager.Clear (??)`

### 23.4.8 TNonFreePooledMemManager.EnumerateItems

Synopsis: Enumerate all items in the list

Declaration: `procedure EnumerateItems (const Method: TEnumItemsMethod)`

Visibility: `public`

Description: `EnumerateItems` will enumerate over all items in the list, passing the items to `Method`. This can be used to execute certain operations on all items in the list. (for example, simply list them)

### 23.4.9 TNonFreePooledMemManager.ItemSize

Synopsis: Size of an item in the list

Declaration: `Property ItemSize : Integer`

Visibility: `public`

Access: `Read`

Description: `ItemSize` is the size of a single block in the list. It's a fixed size determined when the list is created.

See also: `TNonFreePooledMemManager.Create (??)`

## 23.5 TPooledMemManager

### 23.5.1 Description

`TPooledMemManager` is a class which maintains a linked list of blocks, represented by the `TPooledMemManagerItem` (498) record. It should not be used directly, but should be descended from and the descendent should implement the actual memory manager.

See also: `TPooledMemManagerItem` (498)

### 23.5.2 Method overview

Page	Property	Description
<a href="#">500</a>	<code>Clear</code>	Clears the list
<a href="#">500</a>	<code>Create</code>	Creates a new instance of the <code>TPooledMemManager</code> class
<a href="#">501</a>	<code>Destroy</code>	Removes an instance of <code>TPooledMemManager</code> class from memory

### 23.5.3 Property overview

Page	Property	Access	Description
<a href="#">502</a>	<code>AllocatedCount</code>	r	Total number of allocated items in the list
<a href="#">501</a>	<code>Count</code>	r	Number of items in the list
<a href="#">502</a>	<code>FreeCount</code>	r	Number of free items in the list
<a href="#">502</a>	<code>FreedCount</code>	r	Total number of freed items in the list.
<a href="#">501</a>	<code>MaximumFreeCountRatio</code>	rw	Maximum ratio of free items over total items
<a href="#">501</a>	<code>MinimumFreeCount</code>	rw	Minimum count of free items in the list

### 23.5.4 TPooledMemManager.Clear

Synopsis: Clears the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` clears the list, it disposes all items in the list.

See also: `TPooledMemManager.FreedCount` (??)

### 23.5.5 TPooledMemManager.Create

Synopsis: Creates a new instance of the `TPooledMemManager` class

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes all necessary properties and then calls the inherited `create`.

See also: `TPooledMemManager.Destroy` (??)

### 23.5.6 TPooledMemManager.Destroy

Synopsis: Removes an instance of `TPooledMemManager` class from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` calls `Clear (??)` and then calls the inherited `destroy`.

`Destroy` should never be called directly. Instead `Free` should be used, or `FreeAndNil`

See also: `TPooledMemManager.Create (??)`

### 23.5.7 TPooledMemManager.MinimumFreeCount

Synopsis: Minimum count of free items in the list

Declaration: `Property MinimumFreeCount : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `MinimumFreeCount` is the minimum number of free items in the linked list. When disposing an item in the list, the number of items is checked, and only if the required number of free items is present, the item is actually freed.

The default value is 100000

See also: `TPooledMemManager.MaximumFreeCountRatio (??)`

### 23.5.8 TPooledMemManager.MaximumFreeCountRatio

Synopsis: Maximum ratio of free items over total items

Declaration: `Property MaximumFreeCountRatio : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `MaximumFreeCountRatio` is the maximum ratio (divided by 8) of free elements over the total amount of elements: When disposing an item in the list, if the number of free items is higher than this ratio, the item is freed.

The default value is 8.

See also: `TPooledMemManager.MinimumFreeCount (??)`

### 23.5.9 TPooledMemManager.Count

Synopsis: Number of items in the list

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: `Count` is the total number of items allocated from the list.

See also: `TPooledMemManager.FreeCount (??)`, `TPooledMemManager.AllocatedCount (??)`, `TPooledMemManager.FreedCount (??)`

### 23.5.10 TPooledMemManager.FreeCount

Synopsis: Number of free items in the list

Declaration: `Property FreeCount : Integer`

Visibility: `public`

Access: `Read`

Description: `FreeCount` is the current total number of free items in the list.

See also: `TPooledMemManager.Count (??)`, `TPooledMemManager.AllocatedCount (??)`, `TPooledMemManager.FreedCount (??)`

### 23.5.11 TPooledMemManager.AllocatedCount

Synopsis: Total number of allocated items in the list

Declaration: `Property AllocatedCount : Int64`

Visibility: `public`

Access: `Read`

Description: `AllocatedCount` is the total number of newly allocated items on the list.

See also: `TPooledMemManager.Count (??)`, `TPooledMemManager.FreeCount (??)`, `TPooledMemManager.FreedCount (??)`

### 23.5.12 TPooledMemManager.FreedCount

Synopsis: Total number of freed items in the list.

Declaration: `Property FreedCount : Int64`

Visibility: `public`

Access: `Read`

Description: `FreedCount` is the total number of elements actually freed in the list.

See also: `TPooledMemManager.Count (??)`, `TPooledMemManager.FreeCount (??)`, `TPooledMemManager.AllocatedCount (??)`

## Chapter 24

# Reference for unit 'process'

### 24.1 Used units

Table 24.1: Used units by unit 'process'

Name	Page
Classes	??
Pipes	<a href="#">492</a>
System	??
sysutils	??

### 24.2 Overview

The `Process` unit contains the code for the `TProcess` ([506](#)) component, a cross-platform component to start and control other programs, offering also access to standard input and output for these programs.

`TProcess` does not handle wildcard expansion, does not support complex pipelines as in Unix. If this behaviour is desired, the shell can be executed with the pipeline as the command it should execute.

### 24.3 Constants, types and variables

#### 24.3.1 Types

`TProcessForkEvent` = procedure

`TProcessForkEvent` is the prototype for `TProcess.OnForkEvent` ([??](#)). It is a simple procedure, as the idea is that only process-global things should be performed in this event handler.

```
TProcessOption = (poRunSuspended, poWaitOnExit, poUsePipes,
                  poStderrToOutPut, poNoConsole, poNewConsole,
                  poDefaultErrorMode, poNewProcessGroup, poDebugProcess,
                  poDebugOnlyThisProcess)
```



Table 24.2: Enumeration values for type TProcessOption

Value	Explanation
poDebugOnlyThisProcess	Do not follow processes started by this process (Win32 only)
poDebugProcess	Allow debugging of the process (Win32 only)
poDefaultErrorMode	Use default error handling.
poNewConsole	Start a new console window for the process (Win32 only)
poNewProcessGroup	Start the process in a new process group (Win32 only)
poNoConsole	Do not allow access to the console window for the process (Win32 only)
poRunSuspended	Start the process in suspended state.
poStderrToOutPut	Redirect standard error to the standard output stream.
poUsePipes	Use pipes to redirect standard input and output.
poWaitOnExit	Wait for the process to terminate before returning.

When a new process is started using TProcess.Execute(??), these options control the way the process is started. Note that not all options are supported on all platforms.

```
TProcessOptions= Set of (poDebugOnlyThisProcess, poDebugProcess,
                          poDefaultErrorMode, poNewConsole,
                          poNewProcessGroup, poNoConsole, poRunSuspended,
                          poStderrToOutPut, poUsePipes, poWaitOnExit)
```

Set of TProcessOption (504).

```
TProcessPriority = (ppHigh, ppIdle, ppNormal, ppRealTime)
```

Table 24.3: Enumeration values for type TProcessPriority

Value	Explanation
ppHigh	The process runs at higher than normal priority.
ppIdle	The process only runs when the system is idle (i.e. has nothing else to do)
ppNormal	The process runs at normal priority.
ppRealTime	The process runs at real-time priority.

This enumerated type determines the priority of the newly started process. It translates to default platform specific constants. If finer control is needed, then platform-dependent mechanism need to be used to set the priority.

```
TShowWindowOptions = (swoNone, swoHIDE, swoMaximize, swoMinimize,
                      swoRestore, swoShow, swoShowDefault,
                      swoShowMaximized, swoShowMinimized,
                      swoshowMinNOActive, swoShowNA, swoShowNoActivate,
                      swoShowNormal)
```

Table 24.4: Enumeration values for type TShowWindowOptions

Value	Explanation
swoHIDE	The main window is hidden.
swoMaximize	The main window is maximized.
swoMinimize	The main window is minimized.
swoNone	Allow system to position the window.
swoRestore	Restore the previous position.
swoShow	Show the main window.
swoShowDefault	When showing Show the main window on
swoShowMaximized	The main window is shown maximized
swoShowMinimized	The main window is shown minimized
swoshowMinNOActive	The main window is shown minimized but not activated
swoShowNA	The main window is shown but not activated
swoShowNoActivate	The main window is shown but not activated
swoShowNormal	The main window is shown normally

This type describes what the new process' main window should look like. Most of these have only effect on Windows. They are ignored on other systems.

```
TStartupOption = (suoUseShowWindow, suoUseSize, suoUsePosition,
                  suoUseCountChars, suoUseFillAttribute)
```

Table 24.5: Enumeration values for type TStartupOption

Value	Explanation
suoUseCountChars	Use the console character width as specified in TProcess (506).
suoUseFillAttribute	Use the console fill attribute as specified in TProcess (506).
suoUsePosition	Use the window sizes as specified in TProcess (506).
suoUseShowWindow	Use the Show Window options specified in TShowWindowOption (504)
suoUseSize	Use the window sizes as specified in TProcess (506)

These options are mainly for Win32, and determine what should be done with the application once it's started.

```
TStartupOptions= Set of (suoUseCountChars, suoUseFillAttribute,
                          suoUsePosition, suoUseShowWindow, suoUseSize)
```

Set of TStartUpOption (505).

## 24.3.2 Variables

```
TryTerminals : Array of String
```

TryTerminals is used under unix to test for available terminal programs in the DetectXTerm (506) function. If XTermProgram (506) is empty, each item in this list will be searched in the path, and used as a terminal program if it was found.

```
XTermProgram : String
```

`XTermProgram` is the terminal program that is used. If empty, it will be set the first time `DetectXTerm` (506) is called.

## 24.4 Procedures and functions

### 24.4.1 CommandToList

Declaration: `procedure CommandToList(S: String; List: TStrings)`

Visibility: default

### 24.4.2 DetectXTerm

Synopsis: Detect the terminal program.

Declaration: `function DetectXTerm : String`

Visibility: default

Description: `DetectXTerm` checks if `XTermProgram` (506) is set. if so, it returns that. If `XTermProgram` is empty, the list specified in `TryTerminals` (505) is tested for existence. If none is found, then the `DESKTOP_SESSION` environment variable is examined:

**kdekonsole** is used if it is found.

**gnome** `gnome-terminal` is used if it is found

**windowmaker** `aterm` or `xterm` are used if found.

If after all this, no terminal is found, then a list of default programs is tested: `'x-terminal-emulator'`, `'xterm'`, `'aterm'`, `'wterm'`, `'rxvt'`

If a terminal program is found, then it is saved in `XTermProgram`, so the next call to `DetectXTerm` will re-use the value. If the search must be performed again, it is sufficient to set `XTermProgram` to the empty string.

See also: `XTermProgram` (506), `TryTerminals` (505), `TProcess.XTermProgram` (??)

## 24.5 EProcess

### 24.5.1 Description

Exception raised when an error occurs in a `TProcess` routine.

See also: `TProcess` (506)

## 24.6 TProcess

### 24.6.1 Description

`TProcess` is a component that can be used to start and control other processes (programs/binaries). It contains a lot of options that control how the process is started. Many of these are Win32 specific, and have no effect on other platforms, so they should be used with care.

The simplest way to use this component is to create an instance, set the `CommandLine` (??) property to the full pathname of the program that should be executed, and call `Execute` (??). To determine

whether the process is still running (i.e. has not stopped executing), the `Running` (??) property can be checked.

More advanced techniques can be used with the `Options` (??) settings.

See also: `Create` (??), `Execute` (??), `Running` (??), `CommandLin` (??), `Options` (??)

### 24.6.2 Method overview

Page	Property	Description
<a href="#">509</a>	<code>CloseInput</code>	Close the input stream of the process
<a href="#">510</a>	<code>CloseOutput</code>	Close the output stream of the process
<a href="#">510</a>	<code>CloseStderr</code>	Close the error stream of the process
<a href="#">508</a>	<code>Create</code>	Create a new instance of the <code>TProcess</code> class.
<a href="#">509</a>	<code>Destroy</code>	Destroy this instance of <code>TProcess</code>
<a href="#">509</a>	<code>Execute</code>	Execute the program with the given options
<a href="#">510</a>	<code>Resume</code>	Resume execution of a suspended process
<a href="#">510</a>	<code>Suspend</code>	Suspend a running process
<a href="#">511</a>	<code>Terminate</code>	Terminate a running process
<a href="#">511</a>	<code>WaitOnExit</code>	Wait for the program to stop executing.

### 24.6.3 Property overview

Page	Property	Access	Description
<a href="#">515</a>	Active	rw	Start or stop the process.
<a href="#">515</a>	ApplicationName	rw	Name of the application to start (deprecated)
<a href="#">515</a>	CommandLine	rw	Command-line to execute (deprecated)
<a href="#">517</a>	ConsoleTitle	rw	Title of the console window
<a href="#">517</a>	CurrentDirectory	rw	Working directory of the process.
<a href="#">518</a>	Desktop	rw	Desktop on which to start the process.
<a href="#">518</a>	Environment	rw	Environment variables for the new process
<a href="#">516</a>	Executable	rw	Executable name. Supersedes <code>CommandLine</code> and <code>ApplicationName</code> .
<a href="#">514</a>	ExitStatus	r	Exit status of the process.
<a href="#">523</a>	FillAttribute	rw	Color attributes of the characters in the console window (Windows only)
<a href="#">511</a>	Handle	r	Handle of the process
<a href="#">514</a>	InheritHandles	rw	Should the created process inherit the open handles of the current process.
<a href="#">513</a>	Input	r	Stream connected to standard input of the process.
<a href="#">515</a>	OnForkEvent	rw	Event triggered after fork occurred on Linux
<a href="#">518</a>	Options	rw	Options to be used when starting the process.
<a href="#">513</a>	Output	r	Stream connected to standard output of the process.
<a href="#">516</a>	Parameters	rw	Command-line arguments. Supersedes <code>CommandLine</code> .
<a href="#">519</a>	Priority	rw	Priority at which the process is running.
<a href="#">512</a>	ProcessHandle	r	Alias for <code>Handle</code> ( <a href="#">511</a> )
<a href="#">512</a>	ProcessID	r	ID of the process.
<a href="#">520</a>	Running	r	Determines whether the process is still running.
<a href="#">520</a>	ShowWindow	rw	Determines how the process main window is shown (Windows only)
<a href="#">520</a>	StartupOptions	rw	Additional (Windows) startup options
<a href="#">514</a>	Stderr	r	Stream connected to standard diagnostic output of the process.
<a href="#">512</a>	ThreadHandle	r	Main process thread handle
<a href="#">513</a>	ThreadID	r	ID of the main process thread
<a href="#">521</a>	WindowColumns	rw	Number of columns in console window (windows only)
<a href="#">521</a>	WindowHeight	rw	Height of the process main window
<a href="#">522</a>	WindowLeft	rw	X-coordinate of the initial window (Windows only)
<a href="#">511</a>	WindowRect	rw	Positions for the main program window.
<a href="#">522</a>	WindowRows	rw	Number of rows in console window (Windows only)
<a href="#">522</a>	WindowTop	rw	Y-coordinate of the initial window (Windows only)
<a href="#">522</a>	WindowWidth	rw	Height of the process main window (Windows only)
<a href="#">523</a>	XTermProgram	rw	XTerm program to use (unix only)

### 24.6.4 TProcess.Create

**Synopsis:** Create a new instance of the `TProcess` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` creates a new instance of the `TProcess` class. After calling the inherited constructor, it simply sets some default values.

### 24.6.5 TProcess.Destroy

Synopsis: Destroy this instance of TProcess

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up this instance of TProcess. Prior to calling the inherited destructor, it cleans up any streams that may have been created. If a process was started and is still executed, it is *not* stopped, but the standard input/output/stderr streams are no longer available, because they have been destroyed.

Errors: None.

See also: `Create (??)`

### 24.6.6 TProcess.Execute

Synopsis: Execute the program with the given options

Declaration: `procedure Execute; Virtual`

Visibility: `public`

Description: `Execute` actually executes the program as specified in `CommandLine (??)`, applying as much as of the specified options as supported on the current platform.

If the `poWaitOnExit` option is specified in `Options (??)`, then the call will only return when the program has finished executing (or if an error occurred). If this option is not given, the call returns immediately, but the `WaitOnExit (??)` call can be used to wait for it to close, or the `Running (??)` call can be used to check whether it is still running.

The `TProcess.Terminate (??)` call can be used to terminate the program if it is still running, or the `Suspend (??)` call can be used to temporarily stop the program's execution.

The `ExitStatus (??)` function can be used to check the program's exit status, after it has stopped executing.

Errors: On error a `EProcess (506)` exception is raised.

See also: `TProcess.Running (??)`, `TProcess.WaitOnExit (??)`, `TProcess.Terminate (??)`, `TProcess.Suspend (??)`, `TProcess.Resume (??)`, `TProcess.ExitStatus (??)`

### 24.6.7 TProcess.CloseInput

Synopsis: Close the input stream of the process

Declaration: `procedure CloseInput; Virtual`

Visibility: `public`

Description: `CloseInput` closes the input file descriptor of the process, that is, it closes the handle of the pipe to standard input of the process.

See also: `Input (??)`, `StdErr (??)`, `Output (??)`, `CloseOutput (??)`, `CloseStdErr (??)`

### 24.6.8 TProcess.CloseOutput

Synopsis: Close the output stream of the process

Declaration: `procedure CloseOutput; Virtual`

Visibility: `public`

Description: `CloseOutput` closes the output file descriptor of the process, that is, it closes the handle of the pipe to standard output of the process.

See also: `Output (??)`, `Input (??)`, `StdErr (??)`, `CloseInput (??)`, `CloseStdErr (??)`

### 24.6.9 TProcess.CloseStderr

Synopsis: Close the error stream of the process

Declaration: `procedure CloseStderr; Virtual`

Visibility: `public`

Description: `CloseStdErr` closes the standard error file descriptor of the process, that is, it closes the handle of the pipe to standard error output of the process.

See also: `Output (??)`, `Input (??)`, `StdErr (??)`, `CloseInput (??)`, `CloseStdErr (??)`

### 24.6.10 TProcess.Resume

Synopsis: Resume execution of a suspended process

Declaration: `function Resume : Integer; Virtual`

Visibility: `public`

Description: `Resume` should be used to let a suspended process resume its execution. It should be called in particular when the `poRunSuspended` flag is set in `Options (??)`.

Errors: None.

See also: `TProcess.Suspend (??)`, `TProcess.Options (??)`, `TProcess.Execute (??)`, `TProcess.Terminate (??)`

### 24.6.11 TProcess.Suspend

Synopsis: Suspend a running process

Declaration: `function Suspend : Integer; Virtual`

Visibility: `public`

Description: `Suspend` suspends a running process. If the call is successful, the process is suspended: it stops running, but can be made to execute again using the `Resume (??)` call.

`Suspend` is fundamentally different from `TProcess.Terminate (??)` which actually stops the process.

Errors: On error, a nonzero result is returned.

See also: `TProcess.Options (??)`, `TProcess.Resume (??)`, `TProcess.Terminate (??)`, `TProcess.Execute (??)`

### 24.6.12 TProcess.Terminate

Synopsis: Terminate a running process

Declaration: `function Terminate(AExitCode: Integer) : Boolean; Virtual`

Visibility: `public`

Description: `Terminate` stops the execution of the running program. It effectively stops the program.

On Windows, the program will report an exit code of `AExitCode`, on other systems, this value is ignored.

Errors: On error, a nonzero value is returned.

See also: `TProcess.ExitStatus` (??), `TProcess.Suspend` (??), `TProcess.Execute` (??), `TProcess.WaitOnExit` (??)

### 24.6.13 TProcess.WaitOnExit

Synopsis: Wait for the program to stop executing.

Declaration: `function WaitOnExit : Boolean`

Visibility: `public`

Description: `WaitOnExit` waits for the running program to exit. It returns `True` if the wait was succesful, or `False` if there was some error waiting for the program to exit.

Note that the return value of this function has changed. The old return value was a `DWord` with a platform dependent error code. To make things consistent and cross-platform, a boolean return type was used.

Errors: On error, `False` is returned. No extended error information is available, as it is highly system dependent.

See also: `TProcess.ExitStatus` (??), `TProcess.Terminate` (??), `TProcess.Running` (??)

### 24.6.14 TProcess.WindowRect

Synopsis: Positions for the main program window.

Declaration: `Property WindowRect : TRect`

Visibility: `public`

Access: `Read,Write`

Description: `WindowRect` can be used to specify the position of

### 24.6.15 TProcess.Handle

Synopsis: Handle of the process

Declaration: `Property Handle : THandle`

Visibility: `public`

Access: `Read`



**Description:** `Handle` identifies the process. In Unix systems, this is the process ID. On windows, this is the process handle. It can be used to signal the process.

The handle is only valid after `TProcess.Execute (??)` has been called. It is not reset after the process stopped.

See also: `TProcess.ThreadHandle (??)`, `TProcess.ProcessID (??)`, `TProcess.ThreadID (??)`

### 24.6.16 TProcess.ProcessHandle

**Synopsis:** Alias for `Handle` ([511](#))

**Declaration:** `Property ProcessHandle : THandle`

**Visibility:** `public`

**Access:** `Read`

**Description:** `ProcessHandle` equals `Handle (??)` and is provided for completeness only.

See also: `TProcess.Handle (??)`, `TProcess.ThreadHandle (??)`, `TProcess.ProcessID (??)`, `TProcess.ThreadID (??)`

### 24.6.17 TProcess.ThreadHandle

**Synopsis:** Main process thread handle

**Declaration:** `Property ThreadHandle : THandle`

**Visibility:** `public`

**Access:** `Read`

**Description:** `ThreadHandle` is the main process thread handle. On Unix, this is the same as the process ID, on Windows, this may be a different handle than the process handle.

The handle is only valid after `TProcess.Execute (??)` has been called. It is not reset after the process stopped.

See also: `TProcess.Handle (??)`, `TProcess.ProcessID (??)`, `TProcess.ThreadID (??)`

### 24.6.18 TProcess.ProcessID

**Synopsis:** ID of the process.

**Declaration:** `Property ProcessID : Integer`

**Visibility:** `public`

**Access:** `Read`

**Description:** `ProcessID` is the ID of the process. It is the same as the handle of the process on Unix systems, but on Windows it is different from the process `Handle`.

The ID is only valid after `TProcess.Execute (??)` has been called. It is not reset after the process stopped.

See also: `TProcess.Handle (??)`, `TProcess.ThreadHandle (??)`, `TProcess.ThreadID (??)`

### 24.6.19 TProcess.ThreadID

Synopsis: ID of the main process thread

Declaration: `Property ThreadID : Integer`

Visibility: `public`

Access: `Read`

Description: `ProcessID` is the ID of the main process thread. It is the same as the handle of the main process thread (or the process itself) on Unix systems, but on Windows it is different from the thread Handle.

The ID is only valid after `TProcess.Execute (??)` has been called. It is not reset after the process stopped.

See also: `TProcess.ProcessID (??)`, `TProcess.Handle (??)`, `TProcess.ThreadHandle (??)`

### 24.6.20 TProcess.Input

Synopsis: Stream connected to standard input of the process.

Declaration: `Property Input : TOutputPipeStream`

Visibility: `public`

Access: `Read`

Description: `Input` is a stream which is connected to the process' standard input file handle. Anything written to this stream can be read by the process.

The `Input` stream is only instantiated when the `poUsePipes` flag is used in `Options (??)`.

Note that writing to the stream may cause the calling process to be suspended when the created process is not reading from it's input, or to cause errors when the process has terminated.

See also: `TProcess.OutPut (??)`, `TProcess.StdErr (??)`, `TProcess.Options (??)`, `TProcessOption (504)`

### 24.6.21 TProcess.Output

Synopsis: Stream connected to standard output of the process.

Declaration: `Property Output : TInputPipeStream`

Visibility: `public`

Access: `Read`

Description: `Output` is a stream which is connected to the process' standard output file handle. Anything written to standard output by the created process can be read from this stream.

The `Output` stream is only instantiated when the `poUsePipes` flag is used in `Options (??)`.

The `Output` stream also contains any data written to standard diagnostic output (`stderr`) when the `poStdErrToOutPut` flag is used in `Options (??)`.

Note that reading from the stream may cause the calling process to be suspended when the created process is not writing anything to standard output, or to cause errors when the process has terminated.

See also: `TProcess.InPut (??)`, `TProcess.StdErr (??)`, `TProcess.Options (??)`, `TProcessOption (504)`

### 24.6.22 TProcess.Stderr

Synopsis: Stream connected to standard diagnostic output of the process.

Declaration: `Property Stderr : TInputPipeStream`

Visibility: public

Access: Read

Description: `StdErr` is a stream which is connected to the process' standard diagnostic output file handle (`StdErr`). Anything written to standard diagnostic output by the created process can be read from this stream.

The `StdErr` stream is only instantiated when the `poUsePipes` flag is used in `Options` (??).

The Output stream equals the Output (??) when the `poStdErrToOutPut` flag is used in `Options` (??).

Note that reading from the stream may cause the calling process to be suspended when the created process is not writing anything to standard output, or to cause errors when the process has terminated.

See also: `TProcess.InPut` (??), `TProcess.Output` (??), `TProcess.Options` (??), `TProcessOption` (504)

### 24.6.23 TProcess.ExitStatus

Synopsis: Exit status of the process.

Declaration: `Property ExitStatus : Integer`

Visibility: public

Access: Read

Description: `ExitStatus` contains the exit status as reported by the process when it stopped executing. The value of this property is only meaningful when the process is no longer running. If it is not running then the value is zero.

See also: `TProcess.Running` (??), `TProcess.Terminate` (??)

### 24.6.24 TProcess.InheritHandles

Synopsis: Should the created process inherit the open handles of the current process.

Declaration: `Property InheritHandles : Boolean`

Visibility: public

Access: Read,Write

Description: `InheritHandles` determines whether the created process inherits the open handles of the current process (value `True`) or not (`False`).

On Unix, setting this variable has no effect.

See also: `TProcess.InPut` (??), `TProcess.Output` (??), `TProcess.StdErr` (??)

### 24.6.25 TProcess.OnForkEvent

Synopsis: Event triggered after fork occurred on Linux

Declaration: `Property OnForkEvent : TProcessForkEvent`

Visibility: public

Access: Read,Write

Description: `OnForkEvent` is triggered after the `fpFork` (??) call in the child process. It can be used to e.g. close file descriptors and make changes to other resources before the `fpexecv` (??) call. This event is not used on windows.

See also: `Output` (??), `Input` (??), `StdErr` (??), `CloseInput` (??), `CloseStdErr` (??), `TProcessForkEvent` ([503](#))

### 24.6.26 TProcess.Active

Synopsis: Start or stop the process.

Declaration: `Property Active : Boolean`

Visibility: published

Access: Read,Write

Description: `Active` starts the process if it is set to `True`, or terminates the process if set to `False`. It's mostly intended for use in an IDE.

See also: `TProcess.Execute` (??), `TProcess.Terminate` (??)

### 24.6.27 TProcess.ApplicationName

Synopsis: Name of the application to start (deprecated)

Declaration: `Property ApplicationName : String; deprecated;`

Visibility: published

Access: Read,Write

Description: `ApplicationName` is an alias for `TProcess.CommandLine` (??). It's mostly for use in the Windows `CreateProcess` call. If `CommandLine` is not set, then `ApplicationName` will be used instead.

`ApplicationName` is deprecated. New code should use `Executable` (??) instead, and leave `ApplicationName` empty.

See also: `TProcess.CommandLine` (??), `TProcess.Executable` (??), `TProcess.Parameters` (??)

### 24.6.28 TProcess.CommandLine

Synopsis: Command-line to execute (deprecated)

Declaration: `Property CommandLine : String; deprecated;`

Visibility: published

Access: Read,Write

**Description:** `CommandLine` is deprecated. To avoid problems with command-line options with spaces in them and the quoting problems that this entails, it has been superseded by the properties `TProcess.Executable` (??) and `TProcess.Parameters` (??) , which should be used instead of `CommandLine`. New code should leave `CommandLine` empty.

`CommandLine` is the command-line to be executed: this is the name of the program to be executed, followed by any options it should be passed.

If the command to be executed or any of the arguments contains whitespace (space, tab character, linefeed character) it should be enclosed in single or double quotes.

If no absolute pathname is given for the command to be executed, it is searched for in the `PATH` environment variable. On Windows, the current directory always will be searched first. On other platforms, this is not so.

Note that either `CommandLine` or `ApplicationName` must be set prior to calling `Execute`.

See also: `TProcess.ApplicationName` (??), `TProcess.Executable` (??), `TProcess.Parameters` (??)

### 24.6.29 TProcess.Executable

**Synopsis:** Executable name. Supersedes `CommandLine` and `ApplicationName`.

**Declaration:** `Property Executable : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `Executable` is the name of the executable to start. It should not contain any command-line arguments. If no path is given, it will be searched in the `PATH` environment variable.

The extension must be given, none will be added by the component itself. It may be that the OS adds the extension, but this behaviour is not guaranteed.

Arguments should be passed in `Parameters` (??).

`Executable` supersedes the `CommandLine` (??) and `ApplicationName` (??) properties, which have been deprecated. However, if either of `CommandLine` or `ApplicationName` is specified, they will be used instead of `Executable`.

See also: `CommandLine` (??), `ApplicationName` (??), `Parameters` (??)

### 24.6.30 TProcess.Parameters

**Synopsis:** Command-line arguments. Supersedes `CommandLine`.

**Declaration:** `Property Parameters : TStrings`

**Visibility:** published

**Access:** Read,Write

**Description:** `Parameters` contains the command-line arguments that should be passed to the program specified in `Executable` (??).

Commandline arguments should be specified one per item in `Parameters`: each item in `Parameters` will be passed as a separate command-line item. It is therefor not necessary to quote whitespace in the items. As a consequence, it is not allowed to specify multiple command-line parameters in 1 item in the stringlist. If a command needs 2 options `-t` and `-s`, the following is not correct:

```
With Parameters do
begin
add('-t -s');
end;
```

Instead, the code should read:

```
With Parameters do
begin
add('-t');
Add('-s');
end;
```

Note that `Parameters` is ignored if either of `CommandLine` or `ApplicationName` is specified. It can only be used with `Executable`.

See also: `Executable` (??), `CommandLine` (??), `ApplicationName` (??)

### 24.6.31 TProcess.ConsoleTitle

Synopsis: Title of the console window

Declaration: `Property ConsoleTitle : String`

Visibility: published

Access: Read,Write

Description: `ConsoleTitle` is used on Windows when executing a console application: it specifies the title caption of the console window. On other platforms, this property is currently ignored.

Changing this property after the process was started has no effect.

See also: `TProcess.WindowColumns` (??), `TProcess.WindowRows` (??)

### 24.6.32 TProcess.CurrentDirectory

Synopsis: Working directory of the process.

Declaration: `Property CurrentDirectory : String`

Visibility: published

Access: Read,Write

Description: `CurrentDirectory` specifies the working directory of the newly started process.

Changing this property after the process was started has no effect.

See also: `TProcess.Environment` (??)

### 24.6.33 TProcess.Desktop

Synopsis: Desktop on which to start the process.

Declaration: `Property Desktop : String`

Visibility: published

Access: Read,Write

Description: `Desktop` is used on Windows to determine on which desktop the process' main window should be shown. Leaving this empty means the process is started on the same desktop as the currently running process.

Changing this property after the process was started has no effect.

On unix, this parameter is ignored.

See also: `TProcess.Input (??)`, `TProcess.Output (??)`, `TProcess.StdErr (??)`

### 24.6.34 TProcess.Environment

Synopsis: Environment variables for the new process

Declaration: `Property Environment : TStringList`

Visibility: published

Access: Read,Write

Description: `Environment` contains the environment for the new process; it's a list of `Name=Value` pairs, one per line.

If it is empty, the environment of the current process is passed on to the new process.

See also: `TProcess.Options (??)`

### 24.6.35 TProcess.Options

Synopsis: Options to be used when starting the process.

Declaration: `Property Options : TProcessOptions`

Visibility: published

Access: Read,Write

Description: `Options` determine how the process is started. They should be set before the `Execute (??)` call is made.

Table 24.6:

Option	Meaning
<code>poRunSuspended</code>	Start the process in suspended state.
<code>poWaitOnExit</code>	Wait for the process to terminate before returning.
<code>poUsePipes</code>	Use pipes to redirect standard input and output.
<code>poStderrToOutPut</code>	Redirect standard error to the standard output stream.
<code>poNoConsole</code>	Do not allow access to the console window for the process (Win32 only)
<code>poNewConsole</code>	Start a new console window for the process (Win32 only)
<code>poDefaultErrorMode</code>	Use default error handling.
<code>poNewProcessGroup</code>	Start the process in a new process group (Win32 only)
<code>poDebugProcess</code>	Allow debugging of the process (Win32 only)
<code>poDebugOnlyThisProcess</code>	Do not follow processes started by this process (Win32 only)

See also: `TProcessOption` (504), `TProcessOptions` (504), `TProcess.Priority` (??), `TProcess.StartupOptions` (??)

### 24.6.36 TProcess.Priority

Synopsis: Priority at which the process is running.

Declaration: `Property Priority : TProcessPriority`

Visibility: published

Access: Read,Write

Description: `Priority` determines the priority at which the process is running.

Table 24.7:

Priority	Meaning
<code>ppHigh</code>	The process runs at higher than normal priority.
<code>ppIdle</code>	The process only runs when the system is idle (i.e. has nothing else to do)
<code>ppNormal</code>	The process runs at normal priority.
<code>ppRealTime</code>	The process runs at real-time priority.

Note that not all priorities can be set by any user. Usually, only users with administrative rights (the root user on Unix) can set a higher process priority.

On unix, the process priority is mapped on `Nice` values as follows:

Table 24.8:

Priority	Nice value
<code>ppHigh</code>	20
<code>ppIdle</code>	20
<code>ppNormal</code>	0
<code>ppRealTime</code>	-20



See also: `TProcessPriority` ([504](#))

### 24.6.37 `TProcess.StartupOptions`

Synopsis: Additional (Windows) startup options

Declaration: `Property StartupOptions : TStartupOptions`

Visibility: published

Access: Read,Write

Description: `StartupOptions` contains additional startup options, used mostly on Windows system. They determine which other window layout properties are taken into account when starting the new process.

Table 24.9:

Priority	Meaning
<code>suoUseShowWindow</code>	Use the Show Window options specified in <code>ShowWindow</code> (??)
<code>suoUseSize</code>	Use the specified window sizes
<code>suoUsePosition</code>	Use the specified window sizes.
<code>suoUseCountChars</code>	Use the specified console character width.
<code>suoUseFillAttribute</code>	Use the console fill attribute specified in <code>FillAttribute</code> (??).

See also: `TProcess.ShowWindow` (??), `TProcess.WindowHeight` (??), `TProcess.WindowWidth` (??), `TProcess.WindowLeft` (??), `TProcess.WindowTop` (??), `TProcess.WindowColumns` (??), `TProcess.WindowRows` (??), `TProcess.FillAttribute` (??)

### 24.6.38 `TProcess.Running`

Synopsis: Determines wheter the process is still running.

Declaration: `Property Running : Boolean`

Visibility: published

Access: Read

Description: `Running` can be read to determine whether the process is still running.

See also: `TProcess.Terminate` (??), `TProcess.Active` (??), `TProcess.ExitStatus` (??)

### 24.6.39 `TProcess.ShowWindow`

Synopsis: Determines how the process main window is shown (Windows only)

Declaration: `Property ShowWindow : TShowWindowOptions`

Visibility: published

Access: Read,Write

**Description:** ShowWindow determines how the process' main window is shown. It is useful only on Windows.

Table 24.10:

Option	Meaning
swoNone	Allow system to position the window.
swoHIDE	The main window is hidden.
swoMaximize	The main window is maximized.
swoMinimize	The main window is minimized.
swoRestore	Restore the previous position.
swoShow	Show the main window.
swoShowDefault	When showing Show the main window on a default position
swoShowMaximized	The main window is shown maximized
swoShowMinimized	The main window is shown minimized
swoshowMinNOActive	The main window is shown minimized but not activated
swoShowNA	The main window is shown but not activated
swoShowNoActivate	The main window is shown but not activated
swoShowNormal	The main window is shown normally

#### 24.6.40 TProcess.WindowColumns

**Synopsis:** Number of columns in console window (windows only)

**Declaration:** Property WindowColumns : Cardinal

**Visibility:** published

**Access:** Read,Write

**Description:** WindowColumns is the number of columns in the console window, used to run the command in.

This property is only effective if suoUseCountChars is specified in StartupOptions (??)

**See also:** TProcess.WindowHeight (??), TProcess.WindowWidth (??), TProcess.WindowLeft (??), TProcess.WindowTop (??), TProcess.WindowRows (??), TProcess.FillAttribute (??), TProcess.StartupOptions (??)

#### 24.6.41 TProcess.WindowHeight

**Synopsis:** Height of the process main window

**Declaration:** Property WindowHeight : Cardinal

**Visibility:** published

**Access:** Read,Write

**Description:** WindowHeight is the initial height (in pixels) of the process' main window. This property is only effective if suoUseSize is specified in StartupOptions (??)

**See also:** TProcess.WindowWidth (??), TProcess.WindowLeft (??), TProcess.WindowTop (??), TProcess.WindowColumns (??), TProcess.WindowRows (??), TProcess.FillAttribute (??), TProcess.StartupOptions (??)

### 24.6.42 TProcess.WindowLeft

Synopsis: X-coordinate of the initial window (Windows only)

Declaration: `Property WindowLeft : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowLeft` is the initial X coordinate (in pixels) of the process' main window, relative to the left border of the desktop. This property is only effective if `suoUsePosition` is specified in `StartupOptions` (??)

See also: `TProcess.WindowHeight` (??), `TProcess.WindowWidth` (??), `TProcess.WindowTop` (??), `TProcess.WindowColumns` (??), `TProcess.WindowRows` (??), `TProcess.FillAttribute` (??), `TProcess.StartupOptions` (??)

### 24.6.43 TProcess.WindowRows

Synopsis: Number of rows in console window (Windows only)

Declaration: `Property WindowRows : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowRows` is the number of rows in the console window, used to run the command in. This property is only effective if `suoUseCountChars` is specified in `StartupOptions` (??)

See also: `TProcess.WindowHeight` (??), `TProcess.WindowWidth` (??), `TProcess.WindowLeft` (??), `TProcess.WindowTop` (??), `TProcess.WindowColumns` (??), `TProcess.FillAttribute` (??), `TProcess.StartupOptions` (??)

### 24.6.44 TProcess.WindowTop

Synopsis: Y-coordinate of the initial window (Windows only)

Declaration: `Property WindowTop : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowTop` is the initial Y coordinate (in pixels) of the process' main window, relative to the top border of the desktop. This property is only effective if `suoUsePosition` is specified in `StartupOptions` (??)

See also: `TProcess.WindowHeight` (??), `TProcess.WindowWidth` (??), `TProcess.WindowLeft` (??), `TProcess.WindowColumns` (??), `TProcess.WindowRows` (??), `TProcess.FillAttribute` (??), `TProcess.StartupOptions` (??)

### 24.6.45 TProcess.WindowWidth

Synopsis: Height of the process main window (Windows only)

Declaration: `Property WindowWidth : Cardinal`

Visibility: published

Access: Read,Write

**Description:** `WindowWidth` is the initial width (in pixels) of the process' main window. This property is only effective if `suoUseSize` is specified in `StartupOptions` (??)

**See also:** `TProcess.WindowHeight` (??), `TProcess.WindowLeft` (??), `TProcess.WindowTop` (??), `TProcess.WindowColumns` (??), `TProcess.WindowRows` (??), `TProcess.FillAttribute` (??), `TProcess.StartupOptions` (??)

### 24.6.46 TProcess.FillAttribute

**Synopsis:** Color attributes of the characters in the console window (Windows only)

**Declaration:** `Property FillAttribute : Cardinal`

**Visibility:** published

**Access:** Read,Write

**Description:** `FillAttribute` is a WORD value which specifies the background and foreground colors of the console window.

**See also:** `TProcess.WindowHeight` (??), `TProcess.WindowWidth` (??), `TProcess.WindowLeft` (??), `TProcess.WindowTop` (??), `TProcess.WindowColumns` (??), `TProcess.WindowRows` (??), `TProcess.StartupOptions` (??)

### 24.6.47 TProcess.XTermProgram

**Synopsis:** XTerm program to use (unix only)

**Declaration:** `Property XTermProgram : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `XTermProgram` can be used to specify the console program to use when `poConsole` is specified in `TProcess.Options` (??).

If none is specified, `DetectXTerm` (506) is used to detect the terminal program to use. the list specified in `TryTerminals` is tried. If none is found, then the `DESKTOP_SESSION` environment variable is examined:

**kdekonsole** is used if it is found.

**gnome**gnome-terminal is used if it is found

**windowmaker**aterm or xterm are used if found.

If after all this, no terminal is found, then a list of default programs is tested: 'x-terminal-emulator', 'xterm', 'aterm', 'wterm', 'rxvt'

**See also:** `TProcess.Options` (??), `DetectXTerm` (506)

## Chapter 25

# Reference for unit 'rttiutils'

### 25.1 Used units

Table 25.1: Used units by unit 'rttiutils'

Name	Page
Classes	??
StrUtils	??
System	??
sysutils	??
typinfo	??

### 25.2 Overview

The `rttiutils` unit is a unit providing simplified access to the RTTI information from published properties using the `TPropInfoList` ([526](#)) class. This access can be used when saving or restoring form properties at runtime, or for persisting other objects whose RTTI is available: the `TPropsStorage` ([529](#)) class can be used for this. The implementation is based on the `apputils` unit from `RXLib` by *AO ROSNO* and *Master-Bank*

### 25.3 Constants, types and variables

#### 25.3.1 Constants

```
sPropNameDelimiter : String = '_'
```

Separator used when constructing section/key names

#### 25.3.2 Types

```
TEraseSectEvent = procedure(const ASection: String) of object
```

`TEraseSectEvent` is used by `TPropsStorage` (529) to clear a storage section, in a .ini file like fashion: The call should remove all keys in the section `ASection`, and remove the section from storage.

```
TFindComponentEvent = function(const Name: String) : TComponent
```

`TFindComponentEvent` should return the component instance for the component with name path `Name`. The name path should be relative to the global list of loaded components.

```
TReadStrEvent = function(const ASection: String;const Item: String;
                        const Default: String) : String of object
```

`TReadStrEvent` is used by `TPropsStorage` (529) to read strings from a storage mechanism, in a .ini file like fashion: The call should read the string in `ASection` with key `Item`, and if it does not exist, `Default` should be returned.

```
TWriteStrEvent = procedure(const ASection: String;const Item: String;
                          const Value: String) of object
```

`TWriteStrEvent` is used by `TPropsStorage` (529) to write strings to a storage mechanism, in a .ini file like fashion: The call should write the string `Value` in `ASection` with key `Item`. The section and key should be created if they didn't exist yet.

### 25.3.3 Variables

```
FindGlobalComponentCallBack : TFindComponentEvent
```

`FindGlobalComponentCallBack` is called by `UpdateStoredList` (526) whenever it needs to resolve component references. It should be set to a routine that locates a loaded component in the global list of loaded components.

## 25.4 Procedures and functions

### 25.4.1 CreateStoredItem

**Synopsis:** Concatenates component and property name

**Declaration:** `function CreateStoredItem(const CompName: String;const PropName: String) : String`

**Visibility:** default

**Description:** `CreateStoredItem` concatenates `CompName` and `PropName` if they are both empty. The names are separated by a dot (.) character. If either of the names is empty, an empty string is returned.

This function can be used to create items for the list of properties such as used in `UpdateStoredList` (526), `TPropsStorage.StoreObjectsProps` (??) or `TPropsStorage.LoadObjectsProps` (??).

**See also:** `ParseStoredItem` (526), `UpdateStoredList` (526), `TPropsStorage.StoreObjectsProps` (??), `TPropsStorage.LoadObjectsProps` (??)

### 25.4.2 ParseStoredItem

Synopsis: Split a property reference to component reference and property name

Declaration: `function ParseStoredItem(const Item: String; var CompName: String;  
var PropName: String) : Boolean`

Visibility: default

Description: `ParseStoredItem` parses the property reference `Item` and splits it in a reference to a component (returned in `CompName`) and a name of a property (returned in `PropName`). This function basically does the opposite of `CreateStoredItem` (525). Note that both names should be non-empty, i.e., at least 1 dot character must appear in `Item`.

Errors: If an error occurred during parsing, `False` is returned.

See also: `CreateStoredItem` (525), `UpdateStoredList` (526), `TPropsStorage.StoreObjectsProps` (??), `TPropsStorage.LoadObjectsProps` (??)

### 25.4.3 UpdateStoredList

Synopsis: Update a stringlist with object references

Declaration: `procedure UpdateStoredList (AComponent: TComponent; AStoredList: TStrings;  
FromForm: Boolean)`

Visibility: default

Description: `UpdateStoredList` will parse the strings in `AStoredList` using `ParseStoredItem` (526) and will replace the `Objects` properties with the instance of the object whose name each property path in the list refers to. If `FromForm` is `True`, then all instances are searched relative to `AComponent`, i.e. they must be owned by `AComponent`. If `FromForm` is `False` the instances are searched in the global list of streamed components. (the `FindGlobalComponentCallBack` (525) callback must be set for the search to work correctly in this case)

If a component cannot be found, the reference string to the property is removed from the stringlist.

Errors: If `AComponent` is `Nil`, an exception may be raised.

See also: `ParseStoredItem` (526), `TPropsStorage.StoreObjectsProps` (??), `TPropsStorage.LoadObjectsProps` (??), `FindGlobalComponentCallBack` (525)

## 25.5 TPropInfoList

### 25.5.1 Description

`TPropInfoList` is a class which can be used to maintain a list with information about published properties of a class (or an instance). It is used internally by `TPropsStorage` (529)

See also: `TPropsStorage` (529)

### 25.5.2 Method overview

Page	Property	Description
<a href="#">527</a>	Contains	Check whether a certain property is included
<a href="#">527</a>	Create	Create a new instance of <code>TPropInfoList</code>
<a href="#">528</a>	Delete	Delete property information from the list
<a href="#">527</a>	Destroy	Remove the <code>TPropInfoList</code> instance from memory
<a href="#">528</a>	Find	Retrieve property information based on name
<a href="#">528</a>	Intersect	Intersect 2 property lists

### 25.5.3 Property overview

Page	Property	Access	Description
<a href="#">528</a>	Count	r	Number of items in the list
<a href="#">529</a>	Items	r	Indexed access to the property type pointers

### 25.5.4 TPropInfoList.Create

Synopsis: Create a new instance of `TPropInfoList`

Declaration: constructor `Create(AObject: TObject; Filter: TTypeKinds)`

Visibility: public

Description: `Create` allocates and initializes a new instance of `TPropInfoList` on the heap. It retrieves a list of published properties from `AObject`: if `Filter` is empty, then all properties are retrieved. If it is not empty, then only properties of the kind specified in the set are retrieved. Instance should not be `Nil`

See also: `Destroy` (??)

### 25.5.5 TPropInfoList.Destroy

Synopsis: Remove the `TPropInfoList` instance from memory

Declaration: destructor `Destroy`; Override

Visibility: public

Description: `Destroy` cleans up the internal structures maintained by `TPropInfoList` and then calls the inherited `Destroy`.

See also: `Create` (??)

### 25.5.6 TPropInfoList.Contains

Synopsis: Check whether a certain property is included

Declaration: function `Contains(P: PPropInfo) : Boolean`

Visibility: public

Description: `Contains` checks whether `P` is included in the list of properties, and returns `True` if it does. If `P` cannot be found, `False` is returned.

See also: `Find` (??), `Intersect` (??)



### 25.5.7 TPropInfoList.Find

Synopsis: Retrieve property information based on name

Declaration: `function Find(const AName: String) : PPropInfo`

Visibility: public

Description: `Find` returns a pointer to the type information of the property `AName`. If no such information is available, the function returns `Nil`. The search is performed case insensitive.

See also: `Intersect (??)`, `Contains (??)`

### 25.5.8 TPropInfoList.Delete

Synopsis: Delete property information from the list

Declaration: `procedure Delete(Index: Integer)`

Visibility: public

Description: `Delete` deletes the property information at position `Index` from the list. It's mainly of use in the `Intersect (??)` call.

Errors: No checking on the validity of `Index` is performed.

See also: `Intersect (??)`

### 25.5.9 TPropInfoList.Intersect

Synopsis: Intersect 2 property lists

Declaration: `procedure Intersect(List: TPropInfoList)`

Visibility: public

Description: `Intersect` reduces the list of properties to the ones also contained in `List`, i.e. all properties which are not also present in `List` are removed.

See also: `Delete (??)`, `Contains (??)`

### 25.5.10 TPropInfoList.Count

Synopsis: Number of items in the list

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` is the number of property type pointers in the list.

See also: `Items (??)`

### 25.5.11 TPropInfoList.Items

Synopsis: Indexed access to the property type pointers

Declaration: `Property Items[Index: Integer]: PPropInfo; default`

Visibility: public

Access: Read

Description: `Items` provides access to the property type pointers stored in the list. `Index` runs from 0 to `Count-1`.

See also: `Count` (??)

## 25.6 TPropsStorage

### 25.6.1 Description

`TPropsStorage` provides a mechanism to store properties from any class which has published properties (usually a `TPersistent` descendent) in a storage mechanism.

`TPropsStorage` does not handle the storage by itself, instead, the storage is handled through a series of callbacks to read and/or write strings. Conversion of property types to string is handled by `TPropsStorage` itself: all that needs to be done is set the 3 handlers. The storage mechanism is assumed to have the structure of an .ini file : sections with key/value pairs. The three callbacks should take this into account, but they do not need to create an actual .ini file.

See also: `TPropInfoList` ([526](#))

### 25.6.2 Method overview

Page	Property	Description
<a href="#">530</a>	<code>LoadAnyProperty</code>	Load a property value
<a href="#">531</a>	<code>LoadObjectsProps</code>	Load a list of component properties
<a href="#">530</a>	<code>LoadProperties</code>	Load a list of properties
<a href="#">529</a>	<code>StoreAnyProperty</code>	Store a property value
<a href="#">531</a>	<code>StoreObjectsProps</code>	Store a list of component properties
<a href="#">530</a>	<code>StoreProperties</code>	Store a list of properties

### 25.6.3 Property overview

Page	Property	Access	Description
<a href="#">532</a>	<code>AObject</code>	rw	Object to load or store properties from
<a href="#">533</a>	<code>OnEraseSection</code>	rw	Erase a section in storage
<a href="#">533</a>	<code>OnReadString</code>	rw	Read a string value from storage
<a href="#">533</a>	<code>OnWriteString</code>	rw	Write a string value to storage
<a href="#">532</a>	<code>Prefix</code>	rw	Prefix to use in storage
<a href="#">532</a>	<code>Section</code>	rw	Section name for storage

### 25.6.4 TPropsStorage.StoreAnyProperty

Synopsis: Store a property value

Declaration: `procedure StoreAnyProperty(PropInfo: PPropInfo)`

Visibility: public

**Description:** `StoreAnyProperty` stores the property with information specified in `PropInfo` in the storage mechanism. The property value is retrieved from the object instance specified in the `AObject (??)` property of `TPropsStorage`.

**Errors:** If the property pointer is invalid or `AObject` is invalid, an exception will be raised.

**See also:** `AObject (??)`, `LoadAnyProperty (??)`, `LoadProperties (??)`, `StoreProperties (??)`

### 25.6.5 TPropsStorage.LoadAnyProperty

**Synopsis:** Load a property value

**Declaration:** `procedure LoadAnyProperty (PropInfo: PPropInfo)`

Visibility: public

**Description:** `LoadAnyProperty` loads the property with information specified in `PropInfo` from the storage mechanism. The value is then applied to the object instance specified in the `AObject (??)` property of `TPropsStorage`.

**Errors:** If the property pointer is invalid or `AObject` is invalid, an exception will be raised.

**See also:** `AObject (??)`, `StoreAnyProperty (??)`, `LoadProperties (??)`, `StoreProperties (??)`

### 25.6.6 TPropsStorage.StoreProperties

**Synopsis:** Store a list of properties

**Declaration:** `procedure StoreProperties (PropList: TStrings)`

Visibility: public

**Description:** `StoreProperties` stores the values of all properties in `PropList` in the storage mechanism. The list should contain names of published properties of the `AObject (??)` object.

**Errors:** If an invalid property name is specified, an exception will be raised.

**See also:** `AObject (??)`, `StoreAnyProperty (??)`, `LoadProperties (??)`, `LoadAnyProperty (??)`

### 25.6.7 TPropsStorage.LoadProperties

**Synopsis:** Load a list of properties

**Declaration:** `procedure LoadProperties (PropList: TStrings)`

Visibility: public

**Description:** `LoadProperties` loads the values of all properties in `PropList` from the storage mechanism. The list should contain names of published properties of the `AObject (??)` object.

**Errors:** If an invalid property name is specified, an exception will be raised.

**See also:** `AObject (??)`, `StoreAnyProperty (??)`, `StoreProperties (??)`, `LoadAnyProperty (??)`

### 25.6.8 TPropsStorage.LoadObjectsProps

Synopsis: Load a list of component properties

Declaration: `procedure LoadObjectsProps (AComponent: TComponent; StoredList: TStrings)`

Visibility: `public`

Description: `LoadObjectsProps` loads a list of component properties, relative to `AComponent`: the names of the component properties to load are specified as follows:

```
ComponentName1.PropertyName
ComponentName2.Subcomponent1.PropertyName
```

The component instances will be located relative to `AComponent`, and must therefore be names of components owned by `AComponent`, followed by a valid property of these components. If the componentname is missing, the property name will be assumed to be a property of `AComponent` itself.

The `Objects` property of the stringlist should be filled with the instances of the components the property references refer to: they can be filled with the `UpdateStoredList` (526) call.

For example, to load the checked state of a checkbox named 'CBCheckMe' and the caption of a button named 'BPressMe', both owned by a form, the following strings should be passed:

```
CBCheckMe.Checked
BPressMe.Caption
```

and the `AComponent` should be the form component that owns the button and checkbox.

Note that this call removes the value of the `AObject (??)` property.

Errors: If an invalid component is specified, an exception will be raised.

See also: `UpdateStoredList` (526), `StoreObjectsProps (??)`, `LoadProperties (??)`, `LoadAnyProperty (??)`

### 25.6.9 TPropsStorage.StoreObjectsProps

Synopsis: Store a list of component properties

Declaration: `procedure StoreObjectsProps (AComponent: TComponent; StoredList: TStrings)`

Visibility: `public`

Description: `StoreObjectsProps` stores a list of component properties, relative to `AComponent`: the names of the component properties to store are specified as follows:

```
ComponentName1.PropertyName
ComponentName2.Subcomponent1.PropertyName
```

The component instances will be located relative to `AComponent`, and must therefore be names of components owned by `AComponent`, followed by a valid property of these components. If the componentname is missing, the property name will be assumed to be a property of `AComponent` itself.

The `Objects` property of the stringlist should be filled with the instances of the components the property references refer to: they can be filled with the `UpdateStoredList` (526) call.

For example, to store the checked state of a checkbox named 'CBCheckMe' and the caption of a button named 'BPressMe', both owned by a form, the following strings should be passed:

CBCheckMe.Checked  
BPressMe.Caption

and the AComponent should be the form component that owns the button and checkbox.

Note that this call removes the value of the AObject (??) property.

See also: UpdateStoredList (526), LoadObjectsProps (??), LoadProperties (??), LoadAnyProperty (??)

### 25.6.10 TPropsStorage.AObject

Synopsis: Object to load or store properties from

Declaration: Property AObject : TObject

Visibility: public

Access: Read,Write

Description: AObject is the object instance whose properties will be loaded or stored with any of the methods in the TPropsStorage class. Note that a call to StoreObjectProps (??) or LoadObjectProps (??) will destroy any value that this property might have.

See also: LoadProperties (??), LoadAnyProperty (??), StoreProperties (??), StoreAnyProperty (??), StoreObjectProps (??), LoadObjectProps (??)

### 25.6.11 TPropsStorage.Prefix

Synopsis: Prefix to use in storage

Declaration: Property Prefix : String

Visibility: public

Access: Read,Write

Description: Prefix is prepended to all property names to form the key name when writing a property to storage, or when reading a value from storage. This is useful when storing properties of multiple forms in a single section.

See also: TPropsStorage.Section (??)

### 25.6.12 TPropsStorage.Section

Synopsis: Section name for storage

Declaration: Property Section : String

Visibility: public

Access: Read,Write

Description: Section is used as the section name when writing values to storage. Note that when writing properties of subcomponents, their names will be appended to the value specified here.

See also: TPropsStorage.Section (??)

### 25.6.13 TPropsStorage.OnReadString

Synopsis: Read a string value from storage

Declaration: `Property OnReadString : TReadStrEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnReadString` is the event handler called whenever `TPropsStorage` needs to read a string from storage. It should be set whenever properties need to be loaded, or an exception will be raised.

See also: `OnWriteString` (??), `OnEraseSection` (??), `TReadStrEvent` ([525](#))

### 25.6.14 TPropsStorage.OnWriteString

Synopsis: Write a string value to storage

Declaration: `Property OnWriteString : TWriteStrEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnWriteString` is the event handler called whenever `TPropsStorage` needs to write a string to storage. It should be set whenever properties need to be stored, or an exception will be raised.

See also: `OnReadString` (??), `OnEraseSection` (??), `TWriteStrEvent` ([525](#))

### 25.6.15 TPropsStorage.OnEraseSection

Synopsis: Erase a section in storage

Declaration: `Property OnEraseSection : TEraseSectEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnEraseSection` is the event handler called whenever `TPropsStorage` needs to clear a complete storage section. It should be set whenever stringlist properties need to be stored, or an exception will be raised.

See also: `OnReadString` (??), `OnWriteString` (??), `TEraseSectEvent` ([524](#))

## Chapter 26

# Reference for unit 'simpleipc'

### 26.1 Used units

Table 26.1: Used units by unit 'simpleipc'

Name	Page
Classes	??
System	??
sysutils	??

### 26.2 Overview

The SimpleIPC unit provides classes to implement a simple, one-way IPC mechanism using string messages. It provides a TSimpleIPCServer (545) component for the server, and a TSimpleIPCClient (542) component for the client. The components are cross-platform, and should work both on Windows and unix-like systems.

The Unix implementation of the SimpleIPC unit uses file-based sockets. It will attempt to clean up any registered server socket files that were not removed cleanly.

It does this in the unit finalization code. It does not install a signal handler by itself, that is the task of the programmer. But program crashes (access violations and such) that are handled by the RTL will be handled gracefully.

This also means that if the process is killed with the KILL signal, it has no chance of removing the files (KILL signals cannot be caught), in which case socket files may remain in the filesystem.

### 26.3 Constants, types and variables

#### 26.3.1 Resource strings

```
SErrActive = '''This operation is illegal when the server is active.'''
```

Error message if client/server is active.

```
SErrInactive = '''This operation is illegal when the server is inactive.'''
```

Error message if client/server is not active.

```
SErrServerNotActive = '''Server with ID %s is not active.'''
```

Error message if server is not active

### 26.3.2 Constants

```
MsgVersion = 1
```

Current version of the messaging protocol

```
mtString = 1
```

String message type

```
mtUnknown = 0
```

Unknown message type

### 26.3.3 Types

```
TIPCClientCommClass = Class of TIPCClientComm
```

`TIPCClientCommClass` is used by `TSimpleIPCClient` ([542](#)) to decide which kind of communication channel to set up.

```
TIPCServerCommClass = Class of TIPCServerComm
```

`TIPCServerCommClass` is used by `TSimpleIPCServer` ([545](#)) to decide which kind of communication channel to set up.

```
TMessageType = LongInt
```

`TMessageType` is provided for backward compatibility with earlier versions of the `simpleipc` unit.

```
TMsgHeader = packed record
  Version : Byte;
  MsgType : TMessageType;
  MsgLen : Integer;
end
```

`TMsgHeader` is used internally by the IPC client and server components to transmit data. The `Version` field denotes the protocol version. The `MsgType` field denotes the type of data (`mtString` for string messages), and `MsgLen` is the length of the message which will follow.



### 26.3.4 Variables

```
DefaultIPCClientClass : TIPCCClientCommClass = nil
```

`DefaultIPCClientClass` is filled with a class pointer indicating which kind of communication protocol class should be instantiated by the `TSimpleIPCCClient` (542) class. It is set to a default value by the default implementation in the `SimpleIPC` unit, but can be set to another class if another method of transport is desired. (it should match the communication protocol used by the server, obviously).

```
DefaultIPCServerClass : TIPCServerCommClass = nil
```

`DefaultIPCServerClass` is filled with a class pointer indicating which kind of communication protocol class should be instantiated by the `TSimpleIPCServer` (545) class. It is set to a default value by the default implementation in the `SimpleIPC` unit, but can be set to another class if another method of transport is desired.

## 26.4 EIPCErrors

### 26.4.1 Description

`EIPCErrors` is the exception used by the various classes in the `SimpleIPC` unit to report errors.

## 26.5 TIPCCClientComm

### 26.5.1 Description

`TIPCCClientComm` is an abstract component which implements the client-side communication protocol. The behaviour expected of this class must be implemented in a platform-dependent descendent class.

The `TSimpleIPCCClient` (542) class does not implement the messaging protocol by itself. Instead, it creates an instance of a (platform dependent) descendent of `TIPCCClientComm` which handles the internals of the communication protocol.

The server side of the messaging protocol is handled by the `TIPCServerComm` (538) component. The descendent components must always be implemented in pairs.

See also: `TSimpleIPCCClient` (542), `TIPCServerComm` (538), `TSimpleIPCServer` (545)

### 26.5.2 Method overview

Page	Property	Description
<a href="#">537</a>	<code>Connect</code>	Connect to the server
<a href="#">537</a>	<code>Create</code>	Create a new instance of the <code>TIPCCClientComm</code>
<a href="#">537</a>	<code>Disconnect</code>	Disconnect from the server
<a href="#">538</a>	<code>SendMessage</code>	Send a message
<a href="#">538</a>	<code>ServerRunning</code>	Check if the server is running.

### 26.5.3 Property overview

Page	Property	Access	Description
<a href="#">538</a>	<code>Owner</code>	<code>r</code>	<code>TSimpleIPCCClient</code> instance for which communication must be handled.

### 26.5.4 TIPCCliantComm.Create

Synopsis: Create a new instance of the `TIPCCliantComm`

Declaration: `constructor Create(AOwner: TSimpleIPCCliant); Virtual`

Visibility: `public`

Description: `Create` instantiates a new instance of the `TIPCCliantComm` class, and stores the `AOwner` reference to the `TSimpleIPCCliant` (542) instance for which it will handle communication. It can be retrieved later using the `Owner` (??) property.

See also: `Owner` (??), `TSimpleIPCCliant` (542)

### 26.5.5 TIPCCliantComm.Connect

Synopsis: Connect to the server

Declaration: `procedure Connect; Virtual; Abstract`

Visibility: `public`

Description: `Connect` must establish a communication channel with the server. The server endpoint must be constructed from the `ServerID` (??) and `ServerInstance` (??) properties of the owning `TSimpleIPCCliant` (542) instance.

`Connect` is called by the `TSimpleIPCCliant.Connect` (??) call or when the `Active` (??) property is set to `True`

Messages can be sent only after `Connect` was called successfully.

Errors: If the connection setup fails, or the connection was already set up, then an exception may be raised.

See also: `TSimpleIPCCliant.Connect` (??), `Active` (??), `Disconnect` (??)

### 26.5.6 TIPCCliantComm.Disconnect

Synopsis: Disconnect from the server

Declaration: `procedure Disconnect; Virtual; Abstract`

Visibility: `public`

Description: `Disconnect` closes the communication channel with the server. Any calls to `SendMessage` are invalid after `Disconnect` was called.

`Disconnect` is called by the `TSimpleIPCCliant.Disconnect` (??) call or when the `Active` (??) property is set to `False`.

Messages can no longer be sent after `Disconnect` was called.

Errors: If the connection shutdown fails, or the connection was already shut down, then an exception may be raised.

See also: `TSimpleIPCCliant.Disconnect` (??), `Active` (??), `Connect` (??)

### 26.5.7 TIPCCliantComm.ServerRunning

Synopsis: Check if the server is running.

Declaration: `function ServerRunning : Boolean; Virtual; Abstract`

Visibility: public

Description: `ServerRunning` returns `True` if the server endpoint of the communication channel can be found, or `False` if not. The server endpoint should be obtained from the `ServerID` and `InstanceID` properties of the owning `TSimpleIPCCliant` (542) component.

See also: `TSimpleIPCCliant.InstanceID` (??), `TSimpleIPCCliant.ServerID` (??)

### 26.5.8 TIPCCliantComm.SendMessage

Synopsis: Send a message

Declaration: `procedure SendMessage (MsgType: TMessageType; Stream: TStream); Virtual; Abstract`

Visibility: public

Description: `SendMessage` should deliver the message with type `MsgType` and data in `Stream` to the server. It should not return until the message was delivered.

Errors: If the delivery of the message fails, an exception will be raised.

### 26.5.9 TIPCCliantComm.Owner

Synopsis: `TSimpleIPCCliant` instance for which communication must be handled.

Declaration: `Property Owner : TSimpleIPCCliant`

Visibility: public

Access: Read

Description: `Owner` is the `TSimpleIPCCliant` (542) instance for which the communication must be handled. It cannot be changed, and must be specified when the `TIPCCliantComm` instance is created.

See also: `TSimpleIPCCliant` (542), `TIPCCliantComm.Create` (??)

## 26.6 TIPCTServerComm

### 26.6.1 Description

`TIPCTServerComm` is an abstract component which implements the server-side communication protocol. The behaviour expected of this class must be implemented in a platform-dependent descendent class.

The `TSimpleIPCTServer` (545) class does not implement the messaging protocol by itself. Instead, it creates an instance of a (platform dependent) descendent of `TIPCTServerComm` which handles the internals of the communication protocol.

The client side of the messaging protocol is handled by the `TIPCCliantComm` (536) component. The descendent components must always be implemented in pairs.

See also: `TSimpleIPCTServer` (545), `TIPCCliantComm` (536)

### 26.6.2 Method overview

Page	Property	Description
<a href="#">539</a>	Create	Create a new instance of the communication handler
<a href="#">540</a>	PeekMessage	See if a message is available.
<a href="#">540</a>	ReadMessage	Read message from the channel.
<a href="#">539</a>	StartServer	Start the server-side of the communication channel
<a href="#">539</a>	StopServer	Stop the server side of the communication channel.

### 26.6.3 Property overview

Page	Property	Access	Description
<a href="#">541</a>	InstanceID	r	Unique identifier for the communication channel.
<a href="#">540</a>	Owner	r	TSimpleIPCServer instance for which to handle transport

### 26.6.4 TIPCServerComm.Create

Synopsis: Create a new instance of the communication handler

Declaration: `constructor Create(AOwner: TSimpleIPCServer); Virtual`

Visibility: public

Description: `Create` initializes a new instance of the communication handler. It simply saves the `AOwner` parameter in the `Owner` (??) property.

See also: `Owner` (??)

### 26.6.5 TIPCServerComm.StartServer

Synopsis: Start the server-side of the communication channel

Declaration: `procedure StartServer; Virtual; Abstract`

Visibility: public

Description: `StartServer` sets up the server-side of the communication channel. After `StartServer` was called, a client can connect to the communication channel, and send messages to the server.

It is called when the `TSimpleIPC.Active` (??) property of the `TSimpleIPCServer` ([545](#)) instance is set to `True`.

Errors: In case of an error, an `EIPCError` ([536](#)) exception is raised.

See also: `TSimpleIPCServer` ([545](#)), `TSimpleIPC.Active` (??)

### 26.6.6 TIPCServerComm.StopServer

Synopsis: Stop the server side of the communication channel.

Declaration: `procedure StopServer; Virtual; Abstract`

Visibility: public

**Description:** `StartServer` closes down the server-side of the communication channel. After `StartServer` was called, a client can no longer connect to the communication channel, or even send messages to the server if it was previously connected (i.e. it will be disconnected).

It is called when the `TSimpleIPC.Active (??)` property of the `TSimpleIPCServer (545)` instance is set to `False`.

**Errors:** In case of an error, an `EIPCError (536)` exception is raised.

**See also:** `TSimpleIPCServer (545)`, `TSimpleIPC.Active (??)`

### 26.6.7 TIPCServerComm.PeekMessage

**Synopsis:** See if a message is available.

**Declaration:** `function PeekMessage (TimeOut: Integer) : Boolean; Virtual; Abstract`

**Visibility:** `public`

**Description:** `PeekMessage` can be used to see if a message is available: it returns `True` if a message is available. It will wait maximum `TimeOut` milliseconds for a message to arrive. If no message was available after this time, it will return `False`.

If a message was available, it can be read with the `ReadMessage (??)` call.

**See also:** `ReadMessage (??)`

### 26.6.8 TIPCServerComm.ReadMessage

**Synopsis:** Read message from the channel.

**Declaration:** `procedure ReadMessage; Virtual; Abstract`

**Visibility:** `public`

**Description:** `ReadMessage` reads the message for the channel, and stores the information in the data structures in the `Owner` class.

`ReadMessage` is a blocking call: if no message is available, the program will wait till a message arrives. Use `PeekMessage (??)` to see if a message is available.

**See also:** `TSimpleIPCServer (545)`

### 26.6.9 TIPCServerComm.Owner

**Synopsis:** `TSimpleIPCServer` instance for which to handle transport

**Declaration:** `Property Owner : TSimpleIPCServer`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Owner` refers to the `TSimpleIPCServer (545)` instance for which this instance of `TSimpleIPCServer` handles the transport. It is specified when the `TIPCServerComm` is created.

**See also:** `TSimpleIPCServer (545)`

### 26.6.10 TIPServerComm.InstanceID

Synopsis: Unique identifier for the communication channel.

Declaration: `Property InstanceID : String`

Visibility: public

Access: Read

Description: `InstanceID` returns a textual representation which uniquely identifies the communication channel on the server. The value is system dependent, and should be usable by the client-side to establish a communication channel with this instance.

## 26.7 TSimpleIPC

### 26.7.1 Description

`TSimpleIPC` is the common ancestor for the `TSimpleIPCTServer` (545) and `TSimpleIPCClient` (542) classes. It implements some common properties between client and server.

See also: `TSimpleIPCTServer` (545), `TSimpleIPCClient` (542)

### 26.7.2 Property overview

Page	Property	Access	Description
<a href="#">541</a>	Active	rw	Communication channel active
<a href="#">541</a>	ServerID	rw	Unique server identification

### 26.7.3 TSimpleIPC.Active

Synopsis: Communication channel active

Declaration: `Property Active : Boolean`

Visibility: published

Access: Read,Write

Description: `Active` can be set to `True` to set up the client or server end of the communication channel. For the server this means that the server end is set up, for the client it means that the client tries to connect to the server with `ServerID` (??) identification.

See also: `ServerID` (??)

### 26.7.4 TSimpleIPC.ServerID

Synopsis: Unique server identification

Declaration: `Property ServerID : String`

Visibility: published

Access: Read,Write

Description: `ServerID` is the unique server identification: on the server, it determines how the server channel is set up, on the client it determines the server with which to connect.

See also: `Active` (??)

## 26.8 TSimpleIPCClient

### 26.8.1 Description

`TSimpleIPCClient` is the client side of the simple IPC communication protocol. The client program should create a `TSimpleIPCClient` instance, set its `ServerID` (??) property to the unique name for the server it wants to send messages to, and then set the `Active` (??) property to `True` (or call `Connect` (??)).

After the connection with the server was established, messages can be sent to the server with the `SendMessage` (??) or `SendStringMessage` (??) calls.

See also: `TSimpleIPCServer` (545), `TSimpleIPC` (541), `TIPCClientComm` (536)

### 26.8.2 Method overview

Page	Property	Description
<a href="#">543</a>	<code>Connect</code>	Connect to the server
<a href="#">542</a>	<code>Create</code>	Create a new instance of <code>TSimpleIPCClient</code>
<a href="#">542</a>	<code>Destroy</code>	Remove the <code>TSimpleIPCClient</code> instance from memory
<a href="#">543</a>	<code>Disconnect</code>	Disconnect from the server
<a href="#">544</a>	<code>SendMessage</code>	Send a message to the server
<a href="#">544</a>	<code>SendStringMessage</code>	Send a string message to the server
<a href="#">544</a>	<code>SendStringMessageFmt</code>	Send a formatted string message
<a href="#">543</a>	<code>ServerRunning</code>	Check if the server is running.

### 26.8.3 Property overview

Page	Property	Access	Description
<a href="#">544</a>	<code>ServerInstance</code>	rw	Server instance identification

### 26.8.4 TSimpleIPCClient.Create

Synopsis: Create a new instance of `TSimpleIPCClient`

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` instantiates a new instance of the `TSimpleIPCClient` class. It initializes the data structures needed to handle the client side of the communication.

See also: `Destroy` (??)

### 26.8.5 TSimpleIPCClient.Destroy

Synopsis: Remove the `TSimpleIPCClient` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` disconnects the client from the server if need be, and cleans up the internal data structures maintained by `TSimpleIPCClient` and then calls the inherited `Destroy`, which will remove the instance from memory.

Never call `Destroy` directly, use the `Free` method instead or the `FreeAndNil` procedure in `SysUtils`.

See also: `Create` (??)

### 26.8.6 `TSimpleIPClient.Connect`

Synopsis: Connect to the server

Declaration: `procedure Connect`

Visibility: `public`

Description: `Connect` connects to the server indicated in the `ServerID` (??) and `InstanceID` (??) properties. `Connect` is called automatically if the `Active` (??) property is set to `True`.

After a successful call to `Connect`, messages can be sent to the server using `SendMessage` (??) or `SendStringMessage` (??).

Calling `Connect` if the connection is already open has no effect.

Errors: If creating the connection fails, an `EIPError` (536) exception may be raised.

See also: `ServerID` (??), `InstanceID` (??), `Active` (??), `SendMessage` (??), `SendStringMessage` (??), `Disconnect` (??)

### 26.8.7 `TSimpleIPClient.Disconnect`

Synopsis: Disconnect from the server

Declaration: `procedure Disconnect`

Visibility: `public`

Description: `Disconnect` shuts down the connection with the server as previously set up with `Connect` (??). `Disconnect` is called automatically if the `Active` (??) property is set to `False`.

After a successful call to `Disconnect`, messages can no longer be sent to the server. Attempting to do so will result in an exception.

Calling `Disconnect` if there is no connection has no effect.

Errors: If creating the connection fails, an `EIPError` (536) exception may be raised.

See also: `Active` (??), `Connect` (??)

### 26.8.8 `TSimpleIPClient.ServerRunning`

Synopsis: Check if the server is running.

Declaration: `function ServerRunning : Boolean`

Visibility: `public`

Description: `ServerRunning` verifies if the server indicated in the `ServerID` (??) and `InstanceID` (??) properties is running. It returns `True` if the server communication endpoint can be reached, `False` otherwise. This function can be called before a connection is made.

See also: `Connect` (??)



### 26.8.9 TSimpleIPCClient.SendMessage

Synopsis: Send a message to the server

Declaration: `procedure SendMessage(MsgType: TMessageType; Stream: TStream)`

Visibility: public

Description: `SendMessage` sends a message of type `MsgType` and data from `stream` to the server. The client must be connected for this call to work.

Errors: In case an error occurs, or there is no connection to the server, an `EIPCErr` (536) exception is raised.

See also: `Connect` (??), `SendStringMessage` (??)

### 26.8.10 TSimpleIPCClient.SendStringMessage

Synopsis: Send a string message to the server

Declaration: `procedure SendStringMessage(const Msg: String)`  
`procedure SendStringMessage(MsgType: TMessageType; const Msg: String)`

Visibility: public

Description: `SendStringMessage` sends a string message with type `MsgType` and data `Msg` to the server. This is a convenience function: a small wrapper around the `SendMessage` (??) method

Errors: Same as for `SendMessage`.

See also: `SendMessage` (??), `Connect` (??), `SendStringMessageFmt` (??)

### 26.8.11 TSimpleIPCClient.SendStringMessageFmt

Synopsis: Send a formatted string message

Declaration: `procedure SendStringMessageFmt(const Msg: String; Args: Array of const)`  
`procedure SendStringMessageFmt(MsgType: TMessageType; const Msg: String; Args: Array of const)`

Visibility: public

Description: `SendStringMessageFmt` sends a string message with type `MsgType` and message formatted from `Msg` and `Args` to the server. This is a convenience function: a small wrapper around the `SendStringMessage` (??) method

Errors: Same as for `SendMessage`.

See also: `SendMessage` (??), `Connect` (??), `SendStringMessage` (??)

### 26.8.12 TSimpleIPCClient.ServerInstance

Synopsis: Server instance identification

Declaration: `Property ServerInstance : String`

Visibility: public

Access: Read, Write

**Description:** `ServerInstance` should be used in case a particular instance of the server identified with `ServerID` should be contacted. This must be used if the server has its `Global (??)` property set to `False`, and should match the server's `InstanceID (??)` property.

See also: `ServerID (??)`, `Global (??)`, `InstanceID (??)`

## 26.9 TSimpleIPCServer

### 26.9.1 Description

`TSimpleIPCServer` is the server side of the simple IPC communication protocol. The server program should create a `TSimpleIPCServer` instance, set its `ServerID (??)` property to a unique name for the system, and then set the `Active (??)` property to `True` (or call `StartServer (??)`).

After the server was started, it can check for availability of messages with the `PeekMessage (??)` call, and read the message with `ReadMessage (??)`.

See also: `TSimpleIPCClient (542)`, `TSimpleIPC (541)`, `TIPCServerComm (538)`

### 26.9.2 Method overview

Page	Property	Description
<a href="#">545</a>	Create	Create a new instance of <code>TSimpleIPCServer</code>
<a href="#">546</a>	Destroy	Remove the <code>TSimpleIPCServer</code> instance from memory
<a href="#">547</a>	GetMessageData	Read the data of the last message in a stream
<a href="#">546</a>	PeekMessage	Check if a client message is available.
<a href="#">546</a>	StartServer	Start the server
<a href="#">546</a>	StopServer	Stop the server

### 26.9.3 Property overview

Page	Property	Access	Description
<a href="#">548</a>	Global	rw	Is the server reachable to all users or not
<a href="#">548</a>	InstanceID	r	Instance ID
<a href="#">548</a>	MsgData	r	Last message data
<a href="#">547</a>	MsgType	r	Last message type
<a href="#">548</a>	OnMessage	rw	Event triggered when a message arrives
<a href="#">547</a>	StringMessage	r	Last message as a string.

### 26.9.4 TSimpleIPCServer.Create

**Synopsis:** Create a new instance of `TSimpleIPCServer`

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` instantiates a new instance of the `TSimpleIPCServer` class. It initializes the data structures needed to handle the server side of the communication.

See also: `Destroy (??)`

### 26.9.5 TSimpleIPCServer.Destroy

Synopsis: Remove the TSimpleIPCServer instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` stops the server, cleans up the internal data structures maintained by TSimpleIPCServer and then calls the inherited `Destroy`, which will remove the instance from memory.

Never call `Destroy` directly, use the `Free` method instead or the `FreeAndNil` procedure in `SysUtils`.

See also: `Create` (??)

### 26.9.6 TSimpleIPCServer.StartServer

Synopsis: Start the server

Declaration: `procedure StartServer`

Visibility: `public`

Description: `StartServer` starts the server side of the communication channel. It is called automatically when the `Active` property is set to `True`. It creates the internal communication object (a `TIPCServerComm` (538) descendent) and activates the communication channel.

After this method was called, clients can connect and send messages.

Prior to calling this method, the `ServerID` (??) property must be set.

Errors: If an error occurs a `EIPCErr` (536) exception may be raised.

See also: `TIPCServerComm` (538), `Active` (??), `ServerID` (??), `StopServer` (??)

### 26.9.7 TSimpleIPCServer.StopServer

Synopsis: Stop the server

Declaration: `procedure StopServer`

Visibility: `public`

Description: `StopServer` stops the server side of the communication channel. It is called automatically when the `Active` property is set to `False`. It deactivates the communication channel and frees the internal communication object (a `TIPCServerComm` (538) descendent).

See also: `TIPCServerComm` (538), `Active` (??), `ServerID` (??), `StartServer` (??)

### 26.9.8 TSimpleIPCServer.PeekMessage

Synopsis: Check if a client message is available.

Declaration: `function PeekMessage (TimeOut: Integer; DoReadMessage: Boolean) : Boolean`

Visibility: `public`

**Description:** `PeekMessage` checks if a message from a client is available. It will return `True` if a message is available. The call will wait for `Timeout` milliseconds for a message to arrive: if after `Timeout` milliseconds, no message is available, the function will return `False`.

If `DoReadMessage` is `True` then `PeekMessage` will read the message. If it is `False`, it does not read the message. The message should then be read manually with `ReadMessage (??)`.

See also: `ReadMessage (??)`

### 26.9.9 TSimpleIPCServer.GetMessageData

**Synopsis:** Read the data of the last message in a stream

**Declaration:** `procedure GetMessageData(Stream: TStream)`

**Visibility:** `public`

**Description:** `GetMessageData` reads the data of the last message from `TSimpleIPCServer.MsgData (??)` and stores it in stream `Stream`. If no data was available, the stream will be cleared.

This function will return valid data only after a succesful call to `ReadMessage (??)`. It will also not clear the data buffer.

See also: `StringMessage (??)`, `MsgData (??)`, `MsgType (??)`

### 26.9.10 TSimpleIPCServer.StringMessage

**Synopsis:** Last message as a string.

**Declaration:** `Property StringMessage : String`

**Visibility:** `public`

**Access:** `Read`

**Description:** `StringMessage` is the content of the last message as a string.

This property will contain valid data only after a succesful call to `ReadMessage (??)`.

See also: `GetMessageData (??)`

### 26.9.11 TSimpleIPCServer.MsgType

**Synopsis:** Last message type

**Declaration:** `Property MsgType : TMessageType`

**Visibility:** `public`

**Access:** `Read`

**Description:** `MsgType` contains the message type of the last message.

This property will contain valid data only after a succesful call to `ReadMessage (??)`.

See also: `ReadMessage (??)`

### 26.9.12 TSimpleIPCServer.MsgData

Synopsis: Last message data

Declaration: `Property MsgData : TStream`

Visibility: `public`

Access: `Read`

Description: `MsgData` contains the actual data from the last read message. If the data is a string, then `StringMessage (??)` is better suited to read the data.

This property will contain valid data only after a succesful call to `ReadMessage (??)`.

See also: `StringMessage (??)`, `ReadMessage (??)`

### 26.9.13 TSimpleIPCServer.InstanceID

Synopsis: Instance ID

Declaration: `Property InstanceID : String`

Visibility: `public`

Access: `Read`

Description: `InstanceID` is the unique identifier for this server communication channel endpoint, and will be appended to the `ServerID (??)` property to form the unique server endpoint which a client should use.

See also: `ServerID (??)`, `Global (??)`

### 26.9.14 TSimpleIPCServer.Global

Synopsis: Is the server reachable to all users or not

Declaration: `Property Global : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `Global` indicates whether the server is reachable to all users (`True`) or if it is private to the current process (`False`). In the latter case, the unique channel endpoint identification may change: a unique identification of the current process is appended to the `ServerID` name.

See also: `ServerID (??)`, `InstanceID (??)`

### 26.9.15 TSimpleIPCServer.OnMessage

Synopsis: Event triggered when a message arrives

Declaration: `Property OnMessage : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: `OnMessage` is called by `ReadMessage (??)` when a message has been read. The actual message data can be retrieved with one of the `StringMessage (??)`, `MsgData (??)` or `MsgType (??)` properties.

See also: `StringMessage (??)`, `MsgData (??)`, `MsgType (??)`

## Chapter 27

# Reference for unit 'streamcoll'

### 27.1 Used units

Table 27.1: Used units by unit 'streamcoll'

Name	Page
Classes	??
System	??
sysutils	??

### 27.2 Overview

The `streamcoll` unit contains the implementation of a collection (and corresponding collection item) which implements routines for saving or loading the collection to/from a stream. The collection item should implement 2 routines to implement the streaming; the streaming itself is not performed by the `TStreamCollection` (552) collection item.

The streaming performed here is not compatible with the streaming implemented in the `Classes` unit for components. It is independent of the latter and can be used without a component to hold the collection.

The collection item introduces mostly protected methods, and the unit contains a lot of auxiliary routines which aid in streaming.

### 27.3 Procedures and functions

#### 27.3.1 ColReadBoolean

Synopsis: Read a boolean value from a stream

Declaration: `function ColReadBoolean(S: TStream) : Boolean`

Visibility: default

Description: `ColReadBoolean` reads a boolean from the stream `S` as it was written by `ColWriteBoolean` (551) and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColReadDateTime \(550\)](#), [ColWriteBoolean \(551\)](#), [ColReadString \(551\)](#), [ColReadInteger \(550\)](#), [ColReadFloat \(550\)](#), [ColReadCurrency \(550\)](#)

### 27.3.2 ColReadCurrency

Synopsis: Read a currency value from the stream

Declaration: `function ColReadCurrency(S: TStream) : Currency`

Visibility: default

Description: `ColReadCurrency` reads a currency value from the stream `S` as it was written by `ColWriteCurrency (551)` and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColReadDateTime \(550\)](#), [ColReadBoolean \(549\)](#), [ColReadString \(551\)](#), [ColReadInteger \(550\)](#), [ColReadFloat \(550\)](#), [ColWriteCurrency \(551\)](#)

### 27.3.3 ColReadDateTime

Synopsis: Read a `TDateTime` value from a stream

Declaration: `function ColReadDateTime(S: TStream) : TDateTime`

Visibility: default

Description: `ColReadDateTime` reads a currency value from the stream `S` as it was written by `ColWriteDateTime (551)` and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColWriteDateTime \(551\)](#), [ColReadBoolean \(549\)](#), [ColReadString \(551\)](#), [ColReadInteger \(550\)](#), [ColReadFloat \(550\)](#), [ColReadCurrency \(550\)](#)

### 27.3.4 ColReadFloat

Synopsis: Read a floating point value from a stream

Declaration: `function ColReadFloat(S: TStream) : Double`

Visibility: default

Description: `ColReadFloat` reads a double value from the stream `S` as it was written by `ColWriteFloat (552)` and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColReadDateTime \(550\)](#), [ColReadBoolean \(549\)](#), [ColReadString \(551\)](#), [ColReadInteger \(550\)](#), [ColWriteFloat \(552\)](#), [ColReadCurrency \(550\)](#)

### 27.3.5 ColReadInteger

Synopsis: Read a 32-bit integer from a stream.

Declaration: `function ColReadInteger(S: TStream) : Integer`

Visibility: default

**Description:** `ColReadInteger` reads a 32-bit integer from the stream `S` as it was written by `ColWriteInteger` (552) and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: `ColReadDateTime` (550), `ColReadBoolean` (549), `ColReadString` (551), `ColWriteInteger` (552), `ColReadFloat` (550), `ColReadCurrency` (550)

### 27.3.6 ColReadString

**Synopsis:** Read a string from a stream

**Declaration:** `function ColReadString(S: TStream) : String`

**Visibility:** default

**Description:** `ColReadStream` reads a string value from the stream `S` as it was written by `ColWriteString` (552) and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: `ColReadDateTime` (550), `ColReadBoolean` (549), `ColWriteString` (552), `ColReadInteger` (550), `ColReadFloat` (550), `ColReadCurrency` (550)

### 27.3.7 ColWriteBoolean

**Synopsis:** Write a boolean to a stream

**Declaration:** `procedure ColWriteBoolean(S: TStream; AValue: Boolean)`

**Visibility:** default

**Description:** `ColWriteBoolean` writes the boolean `AValue` to the stream. `S`.

See also: `ColReadBoolean` (549), `ColWriteString` (552), `ColWriteInteger` (552), `ColWriteCurrency` (551), `ColWriteDateTime` (551), `ColWriteFloat` (552)

### 27.3.8 ColWriteCurrency

**Synopsis:** Write a currency value to stream

**Declaration:** `procedure ColWriteCurrency(S: TStream; AValue: Currency)`

**Visibility:** default

**Description:** `ColWriteCurrency` writes the currency `AValue` to the stream `S`.

See also: `ColWriteBoolean` (551), `ColWriteString` (552), `ColWriteInteger` (552), `ColWriteDateTime` (551), `ColWriteFloat` (552), `ColReadCurrency` (550)

### 27.3.9 ColWriteDateTime

**Synopsis:** Write a `TDateTime` value to stream

**Declaration:** `procedure ColWriteDateTime(S: TStream; AValue: TDateTime)`

**Visibility:** default

**Description:** `ColWriteDateTime` writes the `TDateTime` `AValue` to the stream `S`.

See also: `ColReadDateTime` (550), `ColWriteBoolean` (551), `ColWriteString` (552), `ColWriteInteger` (552), `ColWriteFloat` (552), `ColWriteCurrency` (551)



### 27.3.10 ColWriteFloat

Synopsis: Write floating point value to stream

Declaration: `procedure ColWriteFloat (S: TStream; AValue: Double)`

Visibility: default

Description: `ColWriteFloat` writes the double `AValue` to the stream `S`.

See also: [ColWriteDateTime \(551\)](#), [ColWriteBoolean \(551\)](#), [ColWriteString \(552\)](#), [ColWriteInteger \(552\)](#), [ColReadFloat \(550\)](#), [ColWriteCurrency \(551\)](#)

### 27.3.11 ColWriteInteger

Synopsis: Write a 32-bit integer to a stream

Declaration: `procedure ColWriteInteger (S: TStream; AValue: Integer)`

Visibility: default

Description: `ColWriteInteger` writes the 32-bit integer `AValue` to the stream `S`. No endianness is observed.

See also: [ColWriteBoolean \(551\)](#), [ColWriteString \(552\)](#), [ColReadInteger \(550\)](#), [ColWriteCurrency \(551\)](#), [ColWriteDateTime \(551\)](#)

### 27.3.12 ColWriteString

Synopsis: Write a string value to the stream

Declaration: `procedure ColWriteString (S: TStream; AValue: String)`

Visibility: default

Description: `ColWriteString` writes the string value `AValue` to the stream `S`.

See also: [ColWriteBoolean \(551\)](#), [ColReadString \(551\)](#), [ColWriteInteger \(552\)](#), [ColWriteCurrency \(551\)](#), [ColWriteDateTime \(551\)](#), [ColWriteFloat \(552\)](#)

## 27.4 EStreamColl

### 27.4.1 Description

Exception raised when an error occurs when streaming the collection.

## 27.5 TStreamCollection

### 27.5.1 Description

`TStreamCollection` is a `TCollection` (??) descendent which implements 2 calls `LoadFromStream` (??) and `SaveToStream` (??) which load and save the contents of the collection to a stream.

The collection items must be descendents of the `TStreamCollectionItem` ([554](#)) class for the streaming to work correctly.

Note that the stream must be used to load collections of the same type.

See also: [TStreamCollectionItem \(554\)](#)

### 27.5.2 Method overview

Page	Property	Description
<a href="#">553</a>	LoadFromStream	Load the collection from a stream
<a href="#">553</a>	SaveToStream	Load the collection from the stream.

### 27.5.3 Property overview

Page	Property	Access	Description
<a href="#">553</a>	Streaming	r	Indicates whether the collection is currently being written to stream

### 27.5.4 TStreamCollection.LoadFromStream

Synopsis: Load the collection from a stream

Declaration: `procedure LoadFromStream(S: TStream)`

Visibility: public

Description: `LoadFromStream` loads the collection from the stream `S`, if the collection was saved using `SaveToStream` (??). It reads the number of items in the collection, and then creates and loads the items one by one from the stream.

Errors: An exception may be raised if the stream contains invalid data.

See also: `TStreamCollection.SaveToStream` (??)

### 27.5.5 TStreamCollection.SaveToStream

Synopsis: Load the collection from the stream.

Declaration: `procedure SaveToStream(S: TStream)`

Visibility: public

Description: `SaveToStream` saves the collection to the stream `S` so it can be read from the stream with `LoadFromStream` (??). It does this by writing the number of collection items to the stream, and then streaming all items in the collection by calling their `SaveToStream` method.

Errors: None.

See also: `TStreamCollection.LoadFromStream` (??)

### 27.5.6 TStreamCollection.Streaming

Synopsis: Indicates whether the collection is currently being written to stream

Declaration: `Property Streaming : Boolean`

Visibility: public

Access: Read

Description: `Streaming` is set to `True` if the collection is written to or loaded from stream, and is set again to `False` if the streaming process is finished.

See also: `TStreamCollection.LoadFromStream` (??), `TStreamCollection.SaveToStream` (??)

## 27.6 TStreamCollectionItem

### 27.6.1 Description

TStreamCollectionItem is a TCollectionItem (??) descendent which implements 2 abstract routines: LoadFromStream and SaveToStream which must be overridden in a descendent class.

These 2 routines will be called by the TStreamCollection ([552](#)) to save or load the item from the stream.

See also: TStreamCollection ([552](#))

## Chapter 28

# Reference for unit 'streamex'

### 28.1 Used units

Table 28.1: Used units by unit 'streamex'

Name	Page
Classes	??
System	??

### 28.2 Overview

streamex implements some extensions to be used together with streams from the classes unit.

### 28.3 TBidirBinaryObjectReader

#### 28.3.1 Description

TBidirBinaryObjectReader is a class descendent from TBinaryObjectReader (??), which implements the necessary support for BiDi data: the position in the stream (not available in the standard streaming) is emulated.

See also: TBidirBinaryObjectWriter ([556](#)), TDelphiReader ([556](#))

#### 28.3.2 Property overview

Page	Property	Access	Description
<a href="#">555</a>	Position	rw	Position in the stream

#### 28.3.3 TBidirBinaryObjectReader.Position

Synopsis: Position in the stream

Declaration: `Property Position : LongInt`

Visibility: public

Access: Read,Write

Description: `Position` exposes the position of the stream in the reader for use in the `TDelphiReader` (556) class.

See also: `TDelphiReader` (556)

## 28.4 TBidirBinaryObjectWriter

### 28.4.1 Description

`TBidirBinaryObjectReader` is a class descendent from `TBinaryObjectWriter` (??), which implements the necessary support for BiDi data.

See also: `TBidirBinaryObjectWriter` (556), `TDelphiWriter` (558)

### 28.4.2 Property overview

Page	Property	Access	Description
556	<code>Position</code>	rw	Position in the stream

### 28.4.3 TBidirBinaryObjectWriter.Position

Synopsis: Position in the stream

Declaration: `Property Position : LongInt`

Visibility: public

Access: Read,Write

Description: `Position` exposes the position of the stream in the writer for use in the `TDelphiWriter` (558) class.

See also: `TDelphiWriter` (558)

## 28.5 TDelphiReader

### 28.5.1 Description

`TDelphiReader` is a descendent of `TReader` which has support for BiDi Streaming. It overrides the stream reading methods for strings, and makes sure the stream can be positioned in the case of strings. For this purpose, it makes use of the `TBidirBinaryObjectReader` (555) driver class.

See also: `TDelphiWriter` (558), `TBidirBinaryObjectReader` (555)

### 28.5.2 Method overview

Page	Property	Description
557	<code>GetDriver</code>	Return the driver class as a <code>TBidirBinaryObjectReader</code> (555) class
557	<code>Read</code>	Read data from stream
557	<code>ReadStr</code>	Overrides the standard <code>ReadStr</code> method

### 28.5.3 Property overview

Page	Property	Access	Description
<a href="#">557</a>	Position	rw	Position in the stream

### 28.5.4 TDelphiReader.GetDriver

Synopsis: Return the driver class as a `TBidirBinaryObjectReader` ([555](#)) class

Declaration: `function GetDriver : TBidirBinaryObjectReader`

Visibility: public

Description: `GetDriver` simply returns the used driver and typecasts it as `TBidirBinaryObjectReader` ([555](#)) class.

See also: `TBidirBinaryObjectReader` ([555](#))

### 28.5.5 TDelphiReader.ReadStr

Synopsis: Overrides the standard `ReadStr` method

Declaration: `function ReadStr : String`

Visibility: public

Description: `ReadStr` makes sure the `TBidirBinaryObjectReader` ([555](#)) methods are used, to store additional information about the stream position when reading the strings.

See also: `TBidirBinaryObjectReader` ([555](#))

### 28.5.6 TDelphiReader.Read

Synopsis: Read data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Override`

Visibility: public

Description: `Read` reads raw data from the stream. It reads `Count` bytes from the stream and places them in `Buf`. It forces the use of the `TBidirBinaryObjectReader` ([555](#)) class when reading.

See also: `TBidirBinaryObjectReader` ([555](#)), `TDelphiReader.Position` (??)

### 28.5.7 TDelphiReader.Position

Synopsis: Position in the stream

Declaration: `Property Position : LongInt`

Visibility: public

Access: Read, Write

Description: Position in the stream.

See also: `TDelphiReader.Read` (??)

## 28.6 TDelphiWriter

### 28.6.1 Description

`TDelphiWriter` is a descendent of `TWriter` which has support for BiDi Streaming. It overrides the stream writing methods for strings, and makes sure the stream can be positioned in the case of strings. For this purpose, it makes use of the `TBidirBinaryObjectWriter` (556) driver class.

See also: `TDelphiReader` (556), `TBidirBinaryObjectWriter` (556)

### 28.6.2 Method overview

Page	Property	Description
558	<code>FlushBuffer</code>	Flushes the stream buffer
558	<code>GetDriver</code>	Return the driver class as a <code>TBidirBinaryObjectWriter</code> (556) class
558	<code>Write</code>	Write raw data to the stream
559	<code>WriteStr</code>	Write a string to the stream
559	<code>WriteValue</code>	Write value type

### 28.6.3 Property overview

Page	Property	Access	Description
559	<code>Position</code>	rw	Position in the stream

### 28.6.4 TDelphiWriter.GetDriver

Synopsis: Return the driver class as a `TBidirBinaryObjectWriter` (556) class

Declaration: `function GetDriver : TBidirBinaryObjectWriter`

Visibility: public

Description: `GetDriver` simply returns the used driver and typecasts it as `TBidirBinaryObjectWriter` (556) class.

See also: `TBidirBinaryObjectWriter` (556)

### 28.6.5 TDelphiWriter.FlushBuffer

Synopsis: Flushes the stream buffer

Declaration: `procedure FlushBuffer`

Visibility: public

Description: `FlushBuffer` flushes the internal buffer of the writer. It simply calls the `FlushBuffer` method of the driver class.

### 28.6.6 TDelphiWriter.Write

Synopsis: Write raw data to the stream

Declaration: `procedure Write(const Buf; Count: LongInt); Override`

Visibility: public

Description: `Write` writes `Count` bytes from `Buf` to the buffer, updating the position as needed.

### 28.6.7 TDelphiWriter.WriteString

Synopsis: Write a string to the stream

Declaration: `procedure WriteStr(const Value: String)`

Visibility: public

Description: `WriteStr` writes a string to the stream, forcing the use of the `TBidirBinaryObjectWriter` (556) class methods, which update the position of the stream.

See also: `TBidirBinaryObjectWriter` (556)

### 28.6.8 TDelphiWriter.WriteValue

Synopsis: Write value type

Declaration: `procedure WriteValue(Value: TValueType)`

Visibility: public

Description: `WriteValue` overrides the same method in `TWriter` to force the use of the `TBidirBinaryObjectWriter` (556) methods, which update the position of the stream.

See also: `TBidirBinaryObjectWriter` (556)

### 28.6.9 TDelphiWriter.Position

Synopsis: Position in the stream

Declaration: `Property Position : LongInt`

Visibility: public

Access: Read,Write

Description: `Position` exposes the position in the stream as exposed by the `TBidirBinaryObjectWriter` (556) instance used when streaming.

See also: `TBidirBinaryObjectWriter` (556)



## Chapter 29

# Reference for unit 'StreamIO'

### 29.1 Used units

Table 29.1: Used units by unit 'StreamIO'

Name	Page
Classes	??
System	??
sysutils	??

### 29.2 Overview

The `StreamIO` unit implements a call to reroute the input or output of a text file to a descendent of `TStream` (??).

This allows to use the standard pascal `Read` (??) and `Write` (??) functions (with all their possibilities), on streams.

### 29.3 Procedures and functions

#### 29.3.1 AssignStream

**Synopsis:** Assign a text file to a stream.

**Declaration:** `procedure AssignStream(var F: Textfile; Stream: TStream)`

**Visibility:** default

**Description:** `AssignStream` assigns the stream `Stream` to file `F`. The file can subsequently be used to write to the stream, using the standard `Write` (??) calls.

Before writing, call `Rewrite` (??) on the stream. Before reading, call `Reset` (??).

**Errors:** if `Stream` is `Nil`, an exception will be raised.

**See also:** `TStream` (??), `GetStream` ([561](#))

### 29.3.2 GetStream

Synopsis: Return the stream, associated with a file.

Declaration: `function GetStream(var F: TTextRec) : TStream`

Visibility: default

Description: `GetStream` returns the instance of the stream that was associated with the file `F` using `AssignStream` ([560](#)).

Errors: An invalid class reference will be returned if the file was not associated with a stream.

See also: `AssignStream` ([560](#)), `TStream` (??)

## Chapter 30

# Reference for unit 'syncobjs'

### 30.1 Used units

Table 30.1: Used units by unit 'syncobjs'

Name	Page
System	??
sysutils	??

### 30.2 Overview

The `syncobjs` unit implements some classes which can be used when synchronizing threads in routines or classes that are used in multiple threads at once. The `TCriticalSection` ([563](#)) class is a wrapper around low-level critical section routines (semaphores or mutexes). The `TEventObject` ([565](#)) class can be used to send messages between threads (also known as conditional variables in Posix threads).

### 30.3 Constants, types and variables

#### 30.3.1 Constants

`INFINITE = (-1)`

Constant denoting an infinite timeout.

#### 30.3.2 Types

`PSecurityAttributes = Pointer`

`PSecurityAttributes` is a dummy type used in non-windows implementations, so the calls remain Delphi compatible.

`TEvent = TEventObject`

`TEvent` is a simple alias for the `TEventObject` ([565](#)) class.

`TEventHandle = Pointer`

`TEventHandle` is an opaque type and should not be used in user code.

`TWaitResult = (wrSignaled, wrTimeout, wrAbandoned, wrError)`

Table 30.2: Enumeration values for type `TWaitResult`

Value	Explanation
<code>wrAbandoned</code>	Wait operation was abandoned.
<code>wrError</code>	An error occurred during the wait operation.
<code>wrSignaled</code>	Event was signaled (triggered)
<code>wrTimeout</code>	Time-out period expired

`TWaitResult` is used to report the result of a wait operation.

## 30.4 TCriticalSection

### 30.4.1 Description

`TCriticalSection` is a class wrapper around the low-level `TRTLCriticalSection` routines. It simply calls the RTL routines in the system unit for critical section support.

A critical section is a resource which can be owned by only 1 caller: it can be used to make sure that in a multithreaded application only 1 thread enters pieces of code protected by the critical section.

Typical usage is to protect a piece of code with the following code (`MySection` is a `TCriticalSection` instance):

```
// Previous code
MySection.Acquire;
Try
  // Protected code
Finally
  MySection.Release;
end;
// Other code.
```

The protected code can be executed by only 1 thread at a time. This is useful for instance for list operations in multithreaded environments.

See also: `Acquire (??)`, `Release (??)`

### 30.4.2 Method overview

Page	Property	Description
<a href="#">564</a>	<code>Acquire</code>	Enter the critical section
<a href="#">565</a>	<code>Create</code>	Create a new critical section.
<a href="#">565</a>	<code>Destroy</code>	Destroy the criticalsection instance
<a href="#">564</a>	<code>Enter</code>	Alias for <code>Acquire</code>
<a href="#">565</a>	<code>Leave</code>	Alias for <code>Release</code>
<a href="#">564</a>	<code>Release</code>	Leave the critical section
<a href="#">564</a>	<code>TryEnter</code>	Try and obtain the critical section

### 30.4.3 TCriticalSection.Acquire

Synopsis: Enter the critical section

Declaration: `procedure Acquire; Override`

Visibility: `public`

Description: `Acquire` attempts to enter the critical section. It will suspend the calling thread if the critical section is in use by another thread, and will resume as soon as the other thread has released the critical section.

See also: `Release` (??)

### 30.4.4 TCriticalSection.Release

Synopsis: Leave the critical section

Declaration: `procedure Release; Override`

Visibility: `public`

Description: `Release` leaves the critical section. It will free the critical section so another thread waiting to enter the critical section will be awakened, and will enter the critical section. This call always returns immediately.

See also: `Acquire` (??)

### 30.4.5 TCriticalSection.Enter

Synopsis: Alias for `Acquire`

Declaration: `procedure Enter`

Visibility: `public`

Description: `Enter` just calls `Acquire` (??).

See also: `Leave` (??), `Acquire` (??)

### 30.4.6 TCriticalSection.TryEnter

Synopsis: Try and obtain the critical section

Declaration: `function TryEnter : Boolean`

Visibility: `public`

Description: `TryEnter` tries to enter the critical section: it returns at once and does not wait if the critical section is owned by another thread; if the current thread owns the critical section or the critical section was obtained successfully, `true` is returned. If the critical section is currently owned by another thread, `False` is returned.

Errors: None.

See also: `TCriticalSection.Enter` (??)

### 30.4.7 TCriticalSection.Leave

Synopsis: Alias for `Release`

Declaration: `procedure Leave`

Visibility: `public`

Description: `Leave` just calls `Release` (??)

See also: `Release` (??), `Enter` (??)

### 30.4.8 TCriticalSection.Create

Synopsis: Create a new critical section.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes a new critical section, and initializes the system objects for the critical section. It should be created only once for all threads, all threads should use the same critical section instance.

See also: `Destroy` (??)

### 30.4.9 TCriticalSection.Destroy

Synopsis: Destroy the criticalsection instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` releases the system critical section resources, and removes the `TCriticalSection` instance from memory.

Errors: Any threads trying to enter the critical section when it is destroyed, will start running with an error (an exception should be raised).

See also: `Create` (??), `Acquire` (??)

## 30.5 TEventObject

### 30.5.1 Description

`TEventObject` encapsulates the `BasicEvent` implementation of the system unit in a class. The event can be used to notify other threads of a change in conditions. (in POSIX terms, this is a conditional variable). A thread that wishes to notify other threads creates an instance of `TEventObject` with a certain name, and posts events to it. Other threads that wish to be notified of these events should create their own instances of `TEventObject` with the same name, and wait for events to arrive.

See also: `TCriticalSection` ([563](#))

### 30.5.2 Method overview

Page	Property	Description
<a href="#">566</a>	Create	Create a new event object
<a href="#">566</a>	destroy	Clean up the event and release from memory
<a href="#">566</a>	ResetEvent	Reset the event
<a href="#">567</a>	SetEvent	Set the event
<a href="#">567</a>	WaitFor	Wait for the event to be set.

### 30.5.3 Property overview

Page	Property	Access	Description
<a href="#">567</a>	ManualReset	r	Should the event be reset manually

### 30.5.4 TEventObject.Create

Synopsis: Create a new event object

Declaration: `constructor Create(EventAttributes: PSecurityAttributes;  
AManualReset: Boolean;InitialState: Boolean;  
const Name: String)`

Visibility: public

Description: `Create` creates a new event object with unique name `AName`. The object will be created security attributes `EventAttributes` (windows only).

The `AManualReset` indicates whether the event must be reset manually (if it is `False`, the event is reset immediatly after the first thread waiting for it is notified). `InitialState` determines whether the event is initially set or not.

See also: `ManualReset` (??), `ResetEvent` (??)

### 30.5.5 TEventObject.destroy

Synopsis: Clean up the event and release from memory

Declaration: `destructor destroy; Override`

Visibility: public

Description: `Destroy` cleans up the low-level resources allocated for this event and releases the event instance from memory.

See also: `Create` (??)

### 30.5.6 TEventObject.ResetEvent

Synopsis: Reset the event

Declaration: `procedure ResetEvent`

Visibility: public

Description: `ResetEvent` turns off the event. Any `WaitFor` (??) operation will suspend the calling thread.

See also: `SetEvent` (??), `WaitFor` (??)

### 30.5.7 TEventObject.SetEvent

Synopsis: Set the event

Declaration: `procedure SetEvent`

Visibility: `public`

Description: `SetEvent` sets the event. If the `ManualReset (??)` is `True` any thread that was waiting for the event to be set (using `WaitFor (??)`) will resume it's operation. After the event was set, any thread that executes `WaitFor` will return at once. If `ManualReset` is `False`, only one thread will be notified that the event was set, and the event will be immediatly reset after that.

See also: `WaitFor (??)`, `ManualReset (??)`

### 30.5.8 TEventObject.WaitFor

Synopsis: Wait for the event to be set.

Declaration: `function WaitFor (Timeout: Cardinal) : TWaitResult`

Visibility: `public`

Description: `WaitFor` should be used in threads that should be notified when the event is set. When `WaitFor` is called, and the event is not set, the thread will be suspended. As soon as the event is set by some other thread (using `SetEvent (??)`) or the timeout period (`TimeOut`) has expired, the `WaitFor` function returns. The return value depends on the condition that caused the `WaitFor` function to return.

The calling thread will wait indefinitely when the constant `INFINITE` is specified for the `TimeOut` parameter.

See also: `TEventObject.SetEvent (??)`

### 30.5.9 TEventObject.ManualReset

Synopsis: Should the event be reset manually

Declaration: `Property ManualReset : Boolean`

Visibility: `public`

Access: `Read`

Description: Should the event be reset manually

## 30.6 THandleObject

### 30.6.1 Description

`THandleObject` is a parent class for synchronization classes that need to store an operating system handle. It introduces a property `Handle (??)` which can be used to store the operating system handle. The handle is in no way manipulated by `THandleObject`, only storage is provided.

See also: `Handle (??)`



### 30.6.2 Method overview

Page	Property	Description
<a href="#">568</a>	destroy	Free the instance

### 30.6.3 Property overview

Page	Property	Access	Description
<a href="#">568</a>	Handle	r	Handle for this object
<a href="#">568</a>	LastError	r	Last operating system error

### 30.6.4 THandleObject.destroy

Synopsis: Free the instance

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` does nothing in the Free Pascal implementation of `THandleObject`.

### 30.6.5 THandleObject.Handle

Synopsis: Handle for this object

Declaration: `Property Handle : TEventHandle`

Visibility: `public`

Access: Read

Description: `Handle` provides read-only access to the operating system handle of this instance. The public access is read-only, descendent classes should set the handle by accessing it's protected field `FHandle` directly.

### 30.6.6 THandleObject.LastError

Synopsis: Last operating system error

Declaration: `Property LastError : Integer`

Visibility: `public`

Access: Read

Description: `LastError` provides read-only access to the last operating system error code for operations on `Handle` (??).

See also: `Handle` (??)

## 30.7 TSimpleEvent

### 30.7.1 Description

`TSimpleEvent` is a simple descendent of the `TEventObject` ([565](#)) class. It creates an event with no name, which must be reset manually, and which is initially not set.

See also: `TEventObject` ([565](#)), `TSimpleEvent.Create` (??)

### 30.7.2 Method overview

Page	Property	Description
<a href="#">569</a>	Create	Creates a new <code>TSimpleEvent</code> instance

### 30.7.3 `TSimpleEvent.Create`

Synopsis: Creates a new `TSimpleEvent` instance

Declaration: `constructor Create`

Visibility: default

Description: `Create` instantiates a new `TSimpleEvent` instance. It simply calls the inherited `Create (??)` with `Nil` for the security attributes, an empty name, `AManualReset` set to `True`, and `InitialState` to `False`.

See also: `TEventObject.Create (??)`

## 30.8 `TSynchroObject`

### 30.8.1 Description

`TSynchroObject` is an abstract synchronization resource object. It implements 2 virtual methods `Acquire (??)` which can be used to acquire the resource, and `Release (??)` to release the resource.

See also: `Acquire (??)`, `Release (??)`

### 30.8.2 Method overview

Page	Property	Description
<a href="#">569</a>	Acquire	Acquire synchronization resource
<a href="#">569</a>	Release	Release previously acquired synchronization resource

### 30.8.3 `TSynchroObject.Acquire`

Synopsis: Acquire synchronization resource

Declaration: `procedure Acquire; Virtual`

Visibility: default

Description: `Acquire` does nothing in `TSynchroObject`. Descendent classes must override this method to acquire the resource they manage.

See also: `Release (??)`

### 30.8.4 `TSynchroObject.Release`

Synopsis: Release previously acquired synchronization resource

Declaration: `procedure Release; Virtual`

Visibility: default

**Description:** `Release` does nothing in `TSynchroObject`. Descendent classes must override this method to release the resource they acquired through the `Acquire (??)` call.

See also: `Acquire (??)`

## Chapter 31

# Reference for unit 'URIParser'

### 31.1 Overview

The `URIParser` unit contains a basic type (`TURI` ([571](#))) and some routines for the parsing (`ParseURI` ([572](#))) and construction (`EncodeURI` ([571](#))) of Uniform Resource Indicators, commonly referred to as URL: Uniform Resource Location. It is used in various other units, and in itself contains no classes. It supports all protocols, username/password/port specification, query parameters and bookmarks etc..

### 31.2 Constants, types and variables

#### 31.2.1 Types

```
TURI = record
  Protocol : String;
  Username : String;
  Password : String;
  Host : String;
  Port : Word;
  Path : String;
  Document : String;
  Params : String;
  Bookmark : String;
  HasAuthority : Boolean;
end
```

`TURI` is the basic record that can be filled by the `ParseURI` ([572](#)) call. It contains the contents of a URI, parsed out in it's various pieces.

### 31.3 Procedures and functions

#### 31.3.1 EncodeURI

Synopsis: Form a string representation of the URI

Declaration: `function EncodeURI(const URI: TURI) : String`

Visibility: default

Description: `EncodeURI` will return a valid text representation of the URI in the URI record.

See also: `ParseURI` ([572](#))

### 31.3.2 FilenameToURI

Synopsis: Construct a URI from a filename

Declaration: `function FilenameToURI(const Filename: String) : String`

Visibility: default

Description: `FilenameToURI` takes `Filename` and constructs a `file:` protocol URI from it.

Errors: None.

See also: `URIToFilename` ([573](#))

### 31.3.3 IsAbsoluteURI

Synopsis: Check whether a URI is absolute.

Declaration: `function IsAbsoluteURI(const UriReference: String) : Boolean`

Visibility: default

Description: `IsAbsoluteURI` returns `True` if the URI in `UriReference` is absolute, i.e. contains a protocol part.

Errors: None.

See also: `FilenameToURI` ([572](#)), `URIToFileName` ([573](#))

### 31.3.4 ParseURI

Synopsis: Parse a URI and split it into its constituent parts

Declaration: `function ParseURI(const URI: String) : TURI; Overload`  
`function ParseURI(const URI: String; const DefaultProtocol: String;`  
`DefaultPort: Word) : TURI; Overload`

Visibility: default

Description: `ParseURI` decodes URI and returns the various parts of the URI in the result record.

The function accepts the most general URI scheme:

```
proto://user:pwd@host:port/path/document?params#bookmark
```

Missing (optional) parts in the URI will be left blank in the result record. If a default protocol and port are specified, they will be used in the record if the corresponding part is not present in the URI.

See also: `EncodeURI` ([571](#))

### 31.3.5 ResolveRelativeURI

Synopsis: Return a relative link

Declaration: 

```
function ResolveRelativeURI(const BaseUri: WideString;
                           const RelUri: WideString;
                           out ResultUri: WideString) : Boolean
; Overload
function ResolveRelativeURI(const BaseUri: UTF8String;
                           const RelUri: UTF8String;
                           out ResultUri: UTF8String) : Boolean
; Overload
```

Visibility: default

Description: `ResolveRelativeURI` returns in `ResultUri` an absolute link constructed from a base URI `BaseUri` and a relative link `RelUri`. One of the two URI names must have a protocol specified. If the `RelUri` argument contains a protocol, it is considered a complete (absolute) URI and is returned as the result.

The function returns `True` if a link was successfully returned.

Errors: If no protocols are specified, the function returns `False`

### 31.3.6 URIToFilename

Synopsis: Convert a URI to a filename

Declaration: 

```
function URIToFilename(const URI: String; out Filename: String) : Boolean
```

Visibility: default

Description: `URIToFilename` returns a filename (using the correct Path Delimiter character) from URI. The URI must be of protocol `File` or have no protocol.

Errors: If the URI contains an unsupported protocol, `False` is returned.

See also: `ResolveRelativeURI` (573), `FilenameToURI` (572)

# Chapter 32

## Reference for unit 'zstream'

### 32.1 Used units

Table 32.1: Used units by unit 'zstream'

Name	Page
Classes	??
gzio	??
System	??
zbase	??

### 32.2 Overview

The ZStream unit implements a TStream (??) descendent (TCompressionStream (575)) which uses the deflate algorithm to compress everything that is written to it. The compressed data is written to the output stream, which is specified when the compressor class is created.

Likewise, a TStream descendent is implemented which reads data from an input stream (TDecompressionStream (578)) and decompresses it with the inflate algorithm.

### 32.3 Constants, types and variables

#### 32.3.1 Types

`Tcompressionlevel = (clnone, clfastest, cldefault, clmax)`

Table 32.2: Enumeration values for type Tcompressionlevel

Value	Explanation
cldefault	Use default compression
clfastest	Use fast (but less) compression.
clmax	Use maximum compression
clnone	Do not use compression, just copy data.

Compression level for the deflate algorithm

`Tgzopenmode = (gzopenread, gzopenwrite)`

Table 32.3: Enumeration values for type `Tgzopenmode`

Value	Explanation
<code>gzopenread</code>	Open file for reading
<code>gzopenwrite</code>	Open file for writing

Open mode for gzip file.

## 32.4 Ecompressionerror

### 32.4.1 Description

`ECompressionError` is the exception class used by the `TCompressionStream` (575) class.

## 32.5 Edecompressionerror

### 32.5.1 Description

`EDecompressionError` is the exception class used by the `TDeCompressionStream` (578) class.

## 32.6 Egzfileerror

### 32.6.1 Description

`Egzfileerror` is the exception class used to report errors by the `Tgzfilestream` (580) class.

See also: `Tgzfilestream` (580)

## 32.7 Ezliberror

### 32.7.1 Description

Errors which occur in the `zstream` unit are signaled by raising an `EZLibError` exception descendant.

## 32.8 Tcompressionstream

### 32.8.1 Description

`TCompressionStream`



### 32.8.2 Method overview

Page	Property	Description
<a href="#">576</a>	create	Create a new instance of the compression stream.
<a href="#">576</a>	destroy	Flushe data to the output stream and destroys the compression stream.
<a href="#">577</a>	flush	Flush remaining data to the target stream
<a href="#">577</a>	get\_compressionrate	Get the current compression rate
<a href="#">576</a>	write	Write data to the stream

### 32.8.3 Tcompressionstream.create

Synopsis: Create a new instance of the compression stream.

Declaration: `constructor create(level: Tcompressionlevel; dest: TStream; Askipheader: Boolean)`

Visibility: public

Description: `Create` creates a new instance of the compression stream. It merely calls the inherited constructor with the destination stream `Dest` and stores the compression level.

If `ASkipHeader` is set to `True`, the method will not write the block header to the stream. This is required for deflated data in a zip file.

Note that the compressed data is only completely written after the compression stream is destroyed.

See also: `Destroy` (??)

### 32.8.4 Tcompressionstream.destroy

Synopsis: Flushe data to the output stream and destroys the compression stream.

Declaration: `destructor destroy; Override`

Visibility: public

Description: `Destroy` flushes the output stream: any compressed data not yet written to the output stream are written, and the deflate structures are cleaned up.

Errors: None.

See also: `Create` (??)

### 32.8.5 Tcompressionstream.write

Synopsis: Write data to the stream

Declaration: `function write(const buffer; count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` takes `Count` bytes from `Buffer` and comresseses (deflates) them. The compressed result is written to the output stream.

Errors: If an error occurs, an `ECompressionError` ([575](#)) exception is raised.

See also: `Read` (??), `Seek` (??)

### 32.8.6 Tcompressionstream.flush

Synopsis: Flush remaining data to the target stream

Declaration: `procedure flush`

Visibility: `public`

Description: `flush` writes any remaining data in the memory buffers to the target stream, and clears the memory buffer.

### 32.8.7 Tcompressionstream.get\_compressionrate

Synopsis: Get the current compression rate

Declaration: `function get_compressionrate : single`

Visibility: `public`

Description: `get_compressionrate` returns the percentage of the number of written compressed bytes relative to the number of written bytes.

Errors: If no bytes were written, an exception is raised.

## 32.9 Tcustomzlibstream

### 32.9.1 Description

`TCustomZlibStream` serves as the ancestor class for the `TCompressionStream` (575) and `TDecompressionStream` (578) classes.

It introduces support for a progress handler, and stores the input or output stream.

### 32.9.2 Method overview

Page	Property	Description
577	<code>create</code>	Create a new instance of <code>TCustomZlibStream</code>
578	<code>destroy</code>	Clear up instance

### 32.9.3 Tcustomzlibstream.create

Synopsis: Create a new instance of `TCustomZlibStream`

Declaration: `constructor create(stream: TStream)`

Visibility: `public`

Description: `Create` creates a new instance of `TCustomZlibStream`. It stores a reference to the input/output stream, and initializes the deflate compression mechanism so they can be used by the descendents.

See also: `TCompressionStream` (575), `TDecompressionStream` (578)

### 32.9.4 Tcustomzlibstream.destroy

Synopsis: Clear up instance

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the internal memory buffer and calls the inherited `destroy`.

See also: `Tcustomzlibstream.create` (??)

## 32.10 Tdecompressionstream

### 32.10.1 Description

`TDecompressionStream` performs the inverse operation of `TCompressionStream` (575). A read operation reads data from an input stream and decompresses (inflates) the data it as it goes along.

The decompression stream reads it's compressed data from a stream with deflated data. This data can be created e.g. with a `TCompressionStream` (575) compression stream.

See also: `TCompressionStream` (575)

### 32.10.2 Method overview

Page	Property	Description
<a href="#">578</a>	<code>create</code>	Creates a new instance of the <code>TDecompressionStream</code> stream
<a href="#">579</a>	<code>destroy</code>	Destroys the <code>TDecompressionStream</code> instance
<a href="#">580</a>	<code>get\_compressionrate</code>	Get the current compression rate
<a href="#">579</a>	<code>read</code>	Read data from the compressed stream
<a href="#">579</a>	<code>seek</code>	Move stream position to a certain location in the stream.

### 32.10.3 Tdecompressionstream.create

Synopsis: Creates a new instance of the `TDecompressionStream` stream

Declaration: `constructor create(Asource: TStream; Askipheader: Boolean)`

Visibility: `public`

Description: `Create` creates and initializes a new instance of the `TDecompressionStream` class. It calls the inherited `Create` and passes it the `Source` stream. The source stream is the stream from which the compressed (deflated) data is read.

If `ASkipHeader` is true, then the gzip data header is skipped, allowing `TDecompressionStream` to read deflated data in a .zip file. (this data does not have the gzip header record prepended to it).

Note that the source stream is by default not owned by the decompression stream, and is not freed when the decompression stream is destroyed.

See also: `Destroy` (??)

### 32.10.4 TDecompressionStream.destroy

Synopsis: Destroys the `TDecompressionStream` instance

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the inflate structure, and then simply calls the inherited `destroy`.

By default the source stream is not freed when calling `Destroy`.

See also: `Create` (??)

### 32.10.5 TDecompressionStream.read

Synopsis: Read data from the compressed stream

Declaration: `function read(var buffer; count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` will read data from the compressed stream until the decompressed data size is `Count` or there is no more compressed data available. The decompressed data is written in `Buffer`. The function returns the number of bytes written in the buffer.

Errors: If an error occurs, an `EDeCompressionError` (575) exception is raised.

See also: `Write` (??)

### 32.10.6 TDecompressionStream.seek

Synopsis: Move stream position to a certain location in the stream.

Declaration: `function seek(offset: LongInt; origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` overrides the standard `Seek` implementation. There are a few differences between the implementation of `Seek` in Free Pascal compared to Delphi:

- In Free Pascal, you can perform any seek. In case of a forward seek, the Free Pascal implementation will read some bytes until the desired position is reached, in case of a backward seek it will seek the source stream backwards to the position it had at the creation time of the `TDecompressionStream` and then again read some bytes until the desired position has been reached.
- In Free Pascal, a seek with `soFromBeginning` will reset the source stream to the position it had when the `TDecompressionStream` was created. In Delphi, the source stream is reset to position 0. This means that at creation time the source stream must always be at the start of the `zstream`, you cannot use `TDecompressionStream.Seek` to reset the source stream to the begin of the file.

Errors: An `EDeCompressionError` (575) exception is raised if the stream does not allow the requested seek operation.

See also: `Read` (??)

### 32.10.7 Tdecompressionstream.get\_compressionrate

Synopsis: Get the current compression rate

Declaration: `function get_compressionrate : single`

Visibility: public

Description: `get_compressionrate` returns the percentage of the number of read compressed bytes relative to the total number of read bytes.

Errors: If no bytes were written, an exception is raised.

## 32.11 TGZFileStream

### 32.11.1 Description

`TGZFileStream` can be used to read data from a gzip file, or to write data to a gzip file.

See also: `TCompressionStream` ([575](#)), `TDeCompressionStream` ([578](#))

### 32.11.2 Method overview

Page	Property	Description
<a href="#">580</a>	<code>create</code>	Create a new instance of <code>TGZFileStream</code>
<a href="#">582</a>	<code>destroy</code>	Removes <code>TGZFileStream</code> instance
<a href="#">581</a>	<code>read</code>	Read data from the compressed file
<a href="#">581</a>	<code>seek</code>	Set the position in the compressed stream.
<a href="#">581</a>	<code>write</code>	Write data to be compressed

### 32.11.3 TGZFileStream.create

Synopsis: Create a new instance of `TGZFileStream`

Declaration: `constructor create(filename: ansistring; filemode: Tgzopenmode)`

Visibility: public

Description: `Create` creates a new instance of the `TGZFileStream` class. It opens `FileName` for reading or writing, depending on the `FileMode` parameter. It is not possible to open the file read-write. If the file is opened for reading, it must exist.

If the file is opened for reading, the `TGZFileStream.Read (??)` method can be used for reading the data in uncompressed form.

If the file is opened for writing, any data written using the `TGZFileStream.Write (??)` method will be stored in the file in compressed (deflated) form.

Errors: If the file is not found, an `EZlibError` ([575](#)) exception is raised.

See also: `Destroy (??)`, `TGZOpenMode` ([575](#))

### 32.11.4 TGZFileStream.read

Synopsis: Read data from the compressed file

Declaration: `function read(var buffer;count: LongInt) : LongInt; Override`

Visibility: public

Description: `Read` overrides the `Read` method of `TStream` to read the data from the compressed file. The `Buffer` parameter indicates where the read data should be stored. The `Count` parameter specifies the number of bytes (*uncompressed*) that should be read from the compressed file. Note that it is not possible to read from the stream if it was opened in write mode.

The function returns the number of uncompressed bytes actually read.

Errors: If `Buffer` points to an invalid location, or does not have enough room for `Count` bytes, an exception will be raised.

See also: `Create (??)`, `Write (??)`, `Seek (??)`

### 32.11.5 TGZFileStream.write

Synopsis: Write data to be compressed

Declaration: `function write(const buffer;count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` writes `Count` bytes from `Buffer` to the compressed file. The data is compressed as it is written, so ideally, less than `Count` bytes end up in the compressed file. Note that it is not possible to write to the stream if it was opened in read mode.

The function returns the number of (uncompressed) bytes that were actually written.

Errors: In case of an error, an `EZlibError (575)` exception is raised.

See also: `Create (??)`, `Read (??)`, `Seek (??)`

### 32.11.6 TGZFileStream.seek

Synopsis: Set the position in the compressed stream.

Declaration: `function seek(offset: LongInt;origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` sets the position to `Offset` bytes, starting from `Origin`. Not all combinations are possible, see `TDecompressionStream.Seek (??)` for a list of possibilities.

Errors: In case an impossible combination is asked, an `EZlibError (575)` exception is raised.

See also: `TDecompressionStream.Seek (??)`

### 32.11.7 TGZFileStream.destroy

Synopsis: Removes TGZFileStream instance

Declaration: destructor destroy; Override

Visibility: public

Description: Destroy closes the file and releases the TGZFileStream instance from memory.

See also: Create (??)