

globus gsi cert utils

8.6

Generated by Doxygen 1.8.3.1

Thu Dec 5 2013 13:19:18

## Contents

<b>1</b>	<b>Globus GSI Certificate Handling Utilities</b>	<b>1</b>
<b>2</b>	<b>Module Index</b>	<b>1</b>
2.1	Modules . . . . .	1
<b>3</b>	<b>Module Documentation</b>	<b>1</b>
3.1	Activation . . . . .	1
3.1.1	Detailed Description . . . . .	1
3.1.2	Macro Definition Documentation . . . . .	2
3.2	Cert Utils Functions . . . . .	3
3.2.1	Detailed Description . . . . .	3
3.2.2	Function Documentation . . . . .	3
3.3	Cert Utils Constants . . . . .	4
3.3.1	Detailed Description . . . . .	4
3.3.2	Typedef Documentation . . . . .	4
3.3.3	Enumeration Type Documentation . . . . .	5

## 1 Globus GSI Certificate Handling Utilities

The Globus GSI Certificate Handling Utilities library. This library contains helper functions for dealing with certificates.

- **Activation** (p. 1)
- **Cert Utils Functions** (p. 3)
- **Cert Utils Constants** (p. 4)

## 2 Module Index

### 2.1 Modules

Here is a list of all modules:

<b>Activation</b>	<b>1</b>
<b>Cert Utils Functions</b>	<b>3</b>
<b>Cert Utils Constants</b>	<b>4</b>

## 3 Module Documentation

### 3.1 Activation

## Macros

- **#define GLOBUS\_GSI\_CERT\_UTILS\_MODULE**

### 3.1.1 Detailed Description

Globus GSI Cert Utils uses standard Globus module activation and deactivation. Before any Globus GSI Cert Utils functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_CERT_UTILS_MODULE)
```

This function returns GLOBUS\_SUCCESS if Globus GSI Credential was successfully initialized, and you are therefore allowed to subsequently call Globus GSI Cert Utils functions. Otherwise, an error code is returned, and Globus GSI Cert Utils functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSI Cert Utils, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_CERT_UTILS_MODULE)
```

This function should be called once for each time Globus GSI Cert Utils was activated.

### 3.1.2 Macro Definition Documentation

#### 3.1.2.1 #define GLOBUS\_GSI\_CERT\_UTILS\_MODULE

Module descriptor.

## 3.2 Cert Utils Functions

### Functions

- globus\_result\_t **globus\_gsi\_cert\_utils\_get\_eec** (STACK\_OF(X509)\*cert\_chain, X509 \*\*eec)
- globus\_result\_t **globus\_gsi\_cert\_utils\_get\_identity\_cert** (STACK\_OF(X509)\*cert\_chain, X509 \*\*identity\_cert)

### 3.2.1 Detailed Description

A generic set of utility functions for manipulating OpenSSL objects, such as X509 certificates.

### 3.2.2 Function Documentation

#### 3.2.2.1 globus\_result\_t globus\_gsi\_cert\_utils\_get\_eec ( STACK\_OF(X509)\* cert\_chain, X509 \*\* eec )

Get the end-entity certificate associated with a certificate chain.

#### Parameters

<i>cert_chain</i>	Certificate chain to inspect.
<i>eec</i>	Pointer to be set to the EEC value from within the cert chain. Must freed by the caller.

References GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_DETERMINING\_CERT\_TYPE, and GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC.

#### 3.2.2.2 globus\_result\_t globus\_gsi\_cert\_utils\_get\_identity\_cert ( STACK\_OF(X509)\* cert\_chain, X509 \*\* identity\_cert )

Get the identity-providing certificate associated with a certificate chain.

This may be an independent proxy or a end-entity certificate.

#### Parameters

<i>cert_chain</i>	Certificate chain to inspect.
<i>identity_cert</i>	Pointer to be set to the certificate value from within the cert chain. Must freed by the caller.

References GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_DETERMINING\_CERT\_TYPE, GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC, and GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_INDEPENDENT\_PROXY.

### 3.3 Cert Utils Constants

#### Typedefs

- typedef enum  
**globus\_gsi\_cert\_utils\_cert\_type\_e globus\_gsi\_cert\_utils\_cert\_type\_t**

#### Enumerations

- enum **globus\_gsi\_cert\_utils\_error\_t** {  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_SUCCESS** = 0,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_NAME\_ENTRY\_OF\_SUBJECT** = 1,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_COPYING\_SUBJECT** = 2,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_CN\_ENTRY** = 3,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_ADDING\_CN\_TO\_SUBJECT** = 4,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_OUT\_OF\_MEMORY** = 5,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_UNEXPECTED\_FORMAT** = 6,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_NON\_COMPLIANT\_PROXY** = 7,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_DETERMINING\_CERT\_TYPE** = 8,  
    **GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_LAST** = 9 }
- enum **globus\_gsi\_cert\_utils\_cert\_type\_e** {  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_DEFAULT** = 0,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC** = (1 << 0),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_CA** = (1 << 1),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2** = (1 << 2),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3** = (1 << 3),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC** = (1 << 4),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_FORMAT\_MASK**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_IMPERSONATION\_PROXY** = (1 << 5),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_LIMITED\_PROXY** = (1 << 6),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RESTRICTED\_PROXY** = (1 << 7),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_INDEPENDENT\_PROXY** = (1 << 8),  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_PROXY\_MASK**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_IMPERSONATION\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_INDEPENDENT\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_LIMITED\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_RESTRICTED\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_LIMITED\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_IMPERSONATION\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_INDEPENDENT\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_LIMITED\_PROXY**,  
    **GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_RESTRICTED\_PROXY** }

#### 3.3.1 Detailed Description

#### 3.3.2 Typedef Documentation

##### 3.3.2.1 typedef enum **globus\_gsi\_cert\_utils\_cert\_type\_e** **globus\_gsi\_cert\_utils\_cert\_type\_t**

#### Certificate Types.

These certificate types are used to describe some properties of a certificate and to specify what type of proxy should be generated in the proxy core code. There are two non-proxy types of certificates understood by Globus: EEC (End-Entity Certificate) and CA (Certificate Authority Certificates), three proxy formats (GSI 2 "legacy" proxies, GSI

3 "Draft" proxies, and RFC 3820-compliant proxies), and four types of proxy (limited, impersonation "full", restricted, and independent). The latter two types are not expressible in the GSI 2 format.

In addition to enumerations for the concrete renderings of certificate format and type combined, there are default, formats-without-types and types-without-formats so that application logic which uses the proxy library can request default proxy formats which are compatible with the issuing certificate.

### 3.3.3 Enumeration Type Documentation

#### 3.3.3.1 `enum globus_gsi_cert_utils_error_t`

Cert Utils Error Codes.

Enumerator

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_SUCCESS** Success - never used.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_NAME\_ENTRY\_OF\_SUBJECT** Failed to retrieve a sub-component of the subject.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_COPYING\_SUBJECT** A error occurred while trying to copy a X.509 subject.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_CN\_ENTRY** Failed to retrieve a CN subcomponent of the subject.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_ADDING\_CN\_TO\_SUBJECT** Failed to add a CN component to a X.509 subject name.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_OUT\_OF\_MEMORY** Out of memory.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_UNEXPECTED\_FORMAT** Something unexpected happen while converting a string subject to a X509\_NAME structure.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_NON\_COMPLIANT\_PROXY** Proxy does not comply with the expected format.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_DETERMINING\_CERT\_TYPE** Couldn't determine the certificate type.

**GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_LAST** Last marker - never used.

#### 3.3.3.2 `enum globus_gsi_cert_utils_cert_type_e`

Certificate Types.

These certificate types are used to describe some properties of a certificate and to specify what type of proxy should be generated in the proxy core code. There are two non-proxy types of certificates understood by Globus: EEC (End-Entity Certificate) and CA (Certificate Authority Certificates), three proxy formats (GSI 2 "legacy" proxies, GSI 3 "Draft" proxies, and RFC 3820-compliant proxies), and four types of proxy (limited, impersonation "full", restricted, and independent). The latter two types are not expressible in the GSI 2 format.

In addition to enumerations for the concrete renderings of certificate format and type combined, there are default, formats-without-types and types-without-formats so that application logic which uses the proxy library can request default proxy formats which are compatible with the issuing certificate.

Enumerator

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_DEFAULT** Default proxy type.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC** A end entity certificate.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_CA** A CA certificate.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2** Legacy Proxy Format.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3** X.509 Proxy Certificate Profile (draft) Proxy Format.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC** X.509 Proxy Certificate Profile Compliant Proxy Format.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_FORMAT\_MASK** Proxy certificate formats mask.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_IMPERSONATION\_PROXY** Impersonation proxy type.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_LIMITED\_PROXY** Limited proxy type.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RESTRICTED\_PROXY** Restricted proxy type.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_INDEPENDENT\_PROXY** Independent proxy type.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_PROXY\_MASK** Proxy types mask.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_IMPERSONATION\_PROXY** A X.509 Proxy Certificate Profile (pre-RFC) compliant impersonation proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_INDEPENDENT\_PROXY** A X.509 Proxy Certificate Profile (pre-RFC) compliant independent proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_LIMITED\_PROXY** A X.509 Proxy Certificate Profile (pre-RFC) compliant limited proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_RESTRICTED\_PROXY** A X.509 Proxy Certificate Profile (pre-RFC) compliant restricted proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_PROXY** A legacy Globus impersonation proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_LIMITED\_PROXY** A legacy Globus limited impersonation proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_IMPERSONATION\_PROXY** A X.509 Proxy Certificate Profile RFC compliant impersonation proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_INDEPENDENT\_PROXY** A X.509 Proxy Certificate Profile RFC compliant independent proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_LIMITED\_PROXY** A X.509 Proxy Certificate Profile RFC compliant limited proxy.

**GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_RESTRICTED\_PROXY** A X.509 Proxy Certificate Profile RFC compliant restricted proxy.

## Index

Activation, 1

    GLOBUS\_GSI\_CERT\_UTILS\_MODULE, 2

Cert Utils Constants, 4

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_ADDING\_CN\_TO\_SUBJECT, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_COPYING\_SUBJECT, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_DETERMINING\_CERT\_TYPE, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_CN\_ENTRY, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_NAME\_ENTRY\_OF\_SUBJECT, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_LAST, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_NON\_COMPLIANT\_PROXY, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_OUT\_OF\_MEMORY, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_SUCCESS, 5

    GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_UNEXPECTED\_FORMAT, 5

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_CA, 5

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_DEFAULT, 5

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC, 5

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_FORMAT\_MASK, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2, 5

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_LIMITED\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_2\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3, 5

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_IMPERSONATION\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_INDEPENDENT\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_LIMITED\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_GSI\_3\_RESTRICTED\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_IMPERSONATION\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_INDEPENDENT\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_LIMITED\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_PROXY\_MASK, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RESTRICTED\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_IMPERSONATION\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_INDEPENDENT\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_LIMITED\_PROXY, 6

    GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_RFC\_RESTRICTED\_PROXY, 6

    globus\_gsi\_cert\_utils\_cert\_type\_e, 5

    globus\_gsi\_cert\_utils\_cert\_type\_t, 4

    globus\_gsi\_cert\_utils\_error\_t, 5

Cert Utils Functions, 3

    globus\_gsi\_cert\_utils\_get\_eec, 3

    globus\_gsi\_cert\_utils\_get\_identity\_cert, 3

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_ADDING\_CN\_TO\_SUBJECT

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_COPYING\_SUBJECT

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_DETERMINING\_CERT\_TYPE

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_CN\_ENTRY

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_GETTING\_NAME\_ENTRY\_OF\_SUBJECT

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_LAST

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_NON\_COMPLIANT\_PROXY

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_OUT\_OF\_MEMORY

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_SUCCESS

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_ERROR\_UNEXPECTED\_FORMAT

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_MODULE

    Activation, 2

GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_CA

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_DEFAULT

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_EEC

    Cert Utils Constants, 5

GLOBUS\_GSI\_CERT\_UTILS\_TYPE\_FORMAT\_MASK



Cert Utils Constants, 6	globus_gsi_cert_utils_get_eec
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2	Cert Utils Functions, 3
Cert Utils Constants, 5	globus_gsi_cert_utils_get_identity_cert
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_LIMITED- _PROXY	Cert Utils Functions, 3
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_2_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3	
Cert Utils Constants, 5	
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_IMPERSONATION_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_INDEPENDENT_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_LIMITED- _PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_GSI_3_RESTRICTED_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_IMPERSONATION_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_INDEPENDENT- _PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_LIMITED_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_PROXY_MASK	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_RESTRICTED- _PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_RFC	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_IMPERSONATION_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_INDEPENDENT_PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_LIMITED- _PROXY	
Cert Utils Constants, 6	
GLOBUS_GSI_CERT_UTILS_TYPE_RFC_RESTRICTED_PROXY	
Cert Utils Constants, 6	
globus_gsi_cert_utils_cert_type_e	
Cert Utils Constants, 5	
globus_gsi_cert_utils_cert_type_t	
Cert Utils Constants, 4	
globus_gsi_cert_utils_error_t	
Cert Utils Constants, 5	